

ITarian Endpoint Manager

Software Version 6.37

Administrator Guide

Guide Version 6.37.070120



Table of Contents

1. Introduction to Endpoint Manager	9
1.1.Key Concepts	14
1.2.Best Practices	15
1.3.Quick Start	16
1.4.Login into the Admin Console	16
2. The Admin Console	18
3. The Dashboard	20
4. Users and User Groups	43
4.1.Manage Users	44
4.1.1.Create New User Accounts	47
4.1.1.1.Manually Add Users	48
4.1.1.2.Import Users from a CSV File	52
4.1.2.Enroll User Devices for Management	55
4.1.2.1.Enroll Android Devices	63
4.1.2.2.Enroll iOS Devices	71
4.1.2.3.Enroll Windows Endpoints	80
4.1.2.4.Enroll Mac OS Endpoints	85
4.1.2.5.Enroll Linux OS Endpoints	89
4.1.3.View User Details	91
4.1.3.1.Update the Details of a User	97
4.1.4.Assign Configuration Profiles to User Devices	
4.1.5.Remove a User	101
4.1.6.Generate New Password for a User	102
4.1.7.Reset Two Factor Authentication Token for a User	104
4.1.8.Run Procedures on User Devices.	105
4.2.Manage User Groups	107
4.2.1.Create a New User Group	109
4.2.2.Edit a User Group	110
4.2.3.Assign Configuration Profiles to a User Group	113
4.2.4.Remove a User Group	116
4.2.5.Run Procedures on Group Devices	117
4.3.Configure Role Based Access Control for Users	119
4.3.1.Create a New Role	122
4.3.2.Manage Permissions and Users Assigned to a Role	128
4.3.3.Remove a Role	134
4.3.4.Manage Roles Assigned to a User	135
5. Devices and Device Groups	138
5.1.Manage Device Groups	140
5.1.1.Create Device Groups	142
5.1.2.Edit a Device Group	
5.1.3.Assign Configuration Profiles to a Device Group	151



5.1.4.Remove a Device Group	154
5.1.5.Run Procedures on Customer Groups	155
5.2.Manage Devices	157
5.2.1.Add New Devices	163
5.2.2.Manage Windows Devices	163
5.2.2.1.View and Edit Device Name	166
5.2.2.2.View Summary Information	168
5.2.2.3.View Hardware Information	168
5.2.2.4.View Network Information	169
5.2.2.5. View Maintenance Windows Associated with Device	170
5.2.2.6. View and Manage Profiles Associated with a Device	172
5.2.2.7. View and Manage Applications Installed on a Device	173
5.2.2.8. View the Files on a Device	175
5.2.2.9. View Exported Configurations and Import Profiles	184
5.2.2.10.View MSI Files Installed on a Device through Endpoint Manager	186
5.2.2.11. View and Manage Patches for Windows and 3rd Party Applications	188
5.2.2.12.View Antivirus Scan History	195
5.2.2.13.View and Manage Device Group Membership	198
5.2.2.14.View Device Logs	200
5.2.3.Manage Mac OS Devices	220
5.2.3.1.View and Edit Mac OS Device Name	222
5.2.3.2.Summary Information of Mac Device	223
5.2.3.3.View Installed Applications	224
5.2.3.4.View Quarantined Files	225
5.2.3.5.View and Manage Profiles Associated with a Device	226
5.2.3.6. View Mac OS Packages Installed on a Device through Endpoint Manager	228
5.2.3.7.View and Manage Device Group Memberships	229
5.2.3.8.View Mac Device Logs	231
5.2.4.Manage Linux Devices	240
5.2.4.1.View and Edit Linux Device Name	242
5.2.4.2.Summary Information of Linux Device	244
5.2.4.3. View Network Information of a Linux Device	
5.2.4.4. View and Manage Profiles Associated with a Linux Device	246
5.2.4.5. View Linux Packages Installed on a Device through Endpoint Manager	248
5.2.4.6. View and Manage Device Group Memberships	249
5.2.5.Manage Android Devices	252
5.2.5.1.View and Edit Device Name	255
5.2.5.2.View Summary Information	257
5.2.5.3.Manage Installed Applications	260
5.2.5.4. View and Manage Profiles Associated with a Device	263
5.2.5.5.View Sneak Peek Pictures to Locate Lost Devices	
5.2.5.6. View the Location of the Device	
5.2.5.7. View and Manage Device Group Memberships	269



5.2.6.Manage iOS Devices	271
5.2.6.1.View and Edit Device Name of an iOS Device	273
5.2.6.2.View Summary Information of an iOS Device	275
5.2.6.3. View Applications installed on an iOS Device	277
5.2.6.4. View and Manage Profiles Associated with an iOS Device	278
5.2.6.5.View the Location of an iOS Device	280
5.2.6.6.View and Manage Group Memberships of an iOS Device	281
5.2.7.View User Information	283
5.2.8.Remove a Device	284
5.2.9.Remote Management of Windows and Mac OS Devices	287
5.2.9.1.Transfer Items to / from the Remote Computer	299
5.2.10.Remotely Manage Folders and Files on Windows Devices	311
5.2.11.Manage Processes on Remote Windows Devices	320
5.2.12.Manage Services on Remote Windows Devices	323
5.2.13.Use the Command Prompt on Remote Windows Devices	327
5.2.14.Apply Procedures to Windows and Mac Devices	330
5.2.15.Remotely Install and Manage Packages on Windows Devices	333
5.2.16.Remotely Install Packages on Mac OS Devices	341
5.2.17.Remotely Install Packages on Linux Devices	342
5.2.18.Send Enrollment Link to iOS Devices	344
5.2.19.Install Apps on Android/iOS Devices	347
5.2.20.Generate an Alarm on Android Devices	348
5.2.21.Remotely Lock Mobile and Mac OS Devices	350
5.2.22.Wipe Selected Mobile and Mac Devices	353
5.2.23.Assign Configuration Profiles to Selected Devices	355
5.2.24.Set / Reset Screen Lock Password for Selected Devices	358
5.2.25.Update Device Information	362
5.2.26.Send Text Messages to Mobile Devices	364
5.2.27.Restart Selected Windows Devices	367
5.2.28.Change a Device's Owner	371
5.2.29.Change the Ownership Status of a Device	373
5.2.30.Generate Device List Report	375
5.3.Bulk Enrollment of Devices	376
5.3.1.Enroll Windows, Mac OS and Linux Devices by Installing the Communication Client	377
5.3.1.1.Enroll Windows Devices Via AD Group Policy	378
5.3.1.2.Enroll Windows, Mac OS and Linux Devices by Offline Installation of Agent	380
5.3.1.3.Enroll Windows Devices using Auto Discovery and Deployment Tool	383
5.3.2.Enroll the Android and iOS Devices of AD Users	385
5.4.Download and Install the Remote Control Tool	394
6. Configuration Templates	400
6.1.Create Configuration Profiles.	401
6.1.1.Profiles for Android Devices	403
6.1.2.Profiles for iOS Devices	433



5.1.3.Profiles for Windows Devices	483
6.1.3.1.Create Windows Profiles	483
6.1.3.1.1.Antivirus Settings	488
6.1.3.1.2.Communication Client and Comodo Client - Security Application Update Settings	506
6.1.3.1.3.File Rating Settings	514
6.1.3.1.4.Firewall Settings	518
6.1.3.1.5.HIPS Settings	549
6.1.3.1.6.Containment Settings	573
6.1.3.1.7.Maintenance Window Settings	611
6.1.3.1.8. Virus Scope Settings	616
6.1.3.1.9.Valkyrie Settings	618
6.1.3.1.10.Global Proxy Settings	620
6.1.3.1.11.Client Proxy Settings	621
6.1.3.1.12.Agent Discovery Settings	624
6.1.3.1.13.Communication Client and Comodo Client - Security Application UI Settings	625
6.1.3.1.14.Logging Settings	636
6.1.3.1.15.Client Access Control.	641
6.1.3.1.16.External Devices Control Settings	643
6.1.3.1.17.Monitors	650
6.1.3.1.18.Procedure Settings	653
6.1.3.1.19.Remote Control Settings.	658
6.1.3.1.20.Remote Tools Settings.	662
6.1.3.1.21.Miscellaneous Settings	665
6.1.3.1.22.Script Analysis Settings.	667
6.1.3.1.23.Data Loss Prevention Settings	673
6.1.3.1.24.Patch Management Settings	679
6.1.3.2.Import Windows Profiles	679
5.1.4.Profiles for Mac OS Devices	684
6.1.4.1.Create a Mac OS Profile	684
6.1.4.1.1.Antivirus Settings for Mac OS Profile	688
6.1.4.1.2.Certificate Settings for Mac OS Profile	704
6.1.4.1.3.Restrictions Settings for Mac OS Profile	706
6.1.4.1.4.VPN Settings for Mac OS Profile	707
6.1.4.1.5.Wi-Fi Settings for Mac OS Profile	710
6.1.4.1.6.Remote Control Settings for Mac OS Profile	712
6.1.4.1.7.Valkyrie Settings for MacOS Profile	715
6.1.4.1.8.Procedure Settings for Mac Profiles	716
6.1.4.1.9.Monitor settings for Mac OS Profile	720
6.1.5.Profiles for Linux Devices.	722
6.1.5.1.Create a Linux Profile	723
6.1.5.1.1.Antivirus Settings for Linux Profile	727
6.1.5.1.2.Communication Client and Comodo Client - Security Application Update Settings for L Profile	



6.1.5.1.3.User Interface Settings for Linux Profile	743
6.1.5.1.4.Logging Settings for Linux Profile	744
6.1.5.1.5.Clients Access Control Settings for Linux Profile	746
6.1.5.1.6. Valkyrie Settings for Linux Profile	747
6.2.View and Manage Profiles	748
6.2.1.Export and Import Configuration Profiles	752
6.2.2.Clone a Profile	754
6.3.Edit Configuration Profiles.	756
6.4.Manage Default Profiles	757
6.5.Manage Alerts	765
6.5.1.Create a New Alert	769
6.5.2.Edit / Delete an Alert	774
6.6.Manage Procedures	775
6.6.1.View and Manage Procedures	776
6.6.2.Create a Custom Procedure	783
6.6.3. Combine Procedures to Build Broader Procedures	794
6.6.4.Review / Approve / Decline New Procedures	795
6.6.5.Add a Procedure to a Profile / Procedure Schedules	797
6.6.6.Import / Export / Clone Procedures	801
6.6.7.Change Alert Settings	805
6.6.8.Apply Procedures to Devices	806
6.6.9.Edit / Delete Procedures.	810
6.6.10.View Procedure Results	819
6.7.Manage Monitors	826
6.7.1.Create Monitors and Add them to Profiles	830
6.7.1.1.Monitors for Windows Devices	831
6.7.1.2.Monitors for Mac OS Devices	839
6.7.2. View and Edit Monitors	842
6.8.Data Loss Prevention Rules	849
6.8.1.Create DLP Discovery Rules and add them to Profiles	850
6.8.2.View and Edit DLP Discovery Rules	860
6.8.3.Create DLP Monitoring Rules and add them to Profiles	
6.8.4. View and Edit DLP Monitoring Rules	865
7. Network Management	866
7.1.Create and Run Network Discovery Tasks	867
7.2.Manage Profiles for Network SNMP Devices	891
7.3.Manage Network Devices	896
7.3.1.Manage SNMP Devices	897
7.3.1.1.SNMP Device Details Interface	902
7.3.2.Discovered Devices.	906
7.4.Manage Network Monitors	
8. Applications	926
8.1.View Applications Installed on Android and iOS Devices	927



8.1.1.Blacklist and Whitelist Applications	929
8.2.Patch Management	931
8.2.1.Manage OS Patches on Windows Endpoints	933
8.2.2.Install 3rd Party Application Patches on Windows Endpoints	946
8.2.2.1.EM Supported 3rd Party Applications	954
8.3. View and Manage Applications Installed on Windows Devices	958
8.3.1.Uninstall a Windows Application from Selected Devices	961
8.3.2.Uninstall a Windows Application from All Devices	962
8.4.Vulnerability Management	964
9. Application Store	969
9.1.iOS Apps	970
9.1.1.Add iOS Apps and Install them on Devices	972
9.1.2.Manage iOS Apps	978
9.2.Android Apps	980
9.2.1.Add Android Apps and Install them on Devices	983
9.2.2.Manage Android Apps	988
9.3. Windows Apps	990
9.3.1.Install Windows Apps on Devices.	993
10. Security Sub Systems	995
10.1.Security Dashboards	996
10.1.1.View Security Events by Time	997
10.1.2.View Security Events by File	
10.1.3.View Security Events by Device	1028
10.2.View Contained Applications	1031
10.3.Manage File Trust Ratings on Windows Devices	1039
10.3.1.File Ratings Explained	1049
10.4. View List of Valkyrie Analyzed Files	1049
10.5.Antivirus and File Rating Scans	1052
10.5.1.Run Antivirus and/or File Rating Scans on Devices	
10.5.2.Handle Malware on Scanned Devices	
10.5.3.Update Virus Signature Database on Windows, Mac OS and Linux Devices	
10.6.View and Manage Identified Malware	
10.7.View and Manage Quarantined Items	
10.8.View Android Threat History	
10.9.View and Manage Autorun Items	
10.10.View History of External Device Connection Attempts	
10.11.Data Loss Prevention Scans	
10.11.1.DLP Logs	1091
10.11.2.DLP Quarantined Files.	
11. Configure Endpoint Manager	
11.1.Email Notifications, Templates and Custom Variables	
11.1.1.Configure Email Templates	
11.1.2.Configure Email Notifications	1101




11.1.3.Create and Manage Custom Variables	1103
11.1.4.Create and Manage Registry Groups	1107
11.1.5.Create and Manage COM Groups	1111
11.1.6.Create and Manage File Groups	1116
11.1.7.View and Manage Pattern Variables	1120
11.1.8.View and Manage Keyword Groups	1126
11.2.Endpoint Manager Portal Configuration	1127
11.2.1.Import User Groups from LDAP	1128
11.2.2.Configure Communication and Security Client Settings	1141
11.2.2.1.Configure the EM Android Client	1141
11.2.2.1.1.Configure Android Client General Settings	1142
11.2.2.1.2.Configure Android Client Antivirus Settings	1144
11.2.2.1.3.Add Google Cloud Messaging (GCM) Token	1145
11.2.2.2.Add Apple Push Notification Certificate	1151
11.2.2.3.Configure Windows Clients	1157
11.2.2.3.1.Configure Communication Client Settings	1157
11.2.2.3.2.Configure Client Security Settings	1161
11.2.3.Manage Endpoint Manager Extensions	1163
11.2.4.Configure Endpoint Manager Reports	1164
11.2.5.Device Removal Settings	1165
11.2.6.Account Security Settings	1167
11.2.7.Set-up Administrator's Time Zone and Language	1175
11.2.8.Configure Audit Log Settings	1176
11.3.Integrate Apple DEP with Endpoint Manager	1177
11.3.1.Link Endpoint Manager with Apple DEP	1178
11.3.2.Manage Apple DEP Devices	1183
11.3.3.Manage Apple DEP Profiles	1188
11.3.4.Configure Apple DEP Notifications	1193
11.4.View Version and Support Information	1194
12. License Management	1196
12.1.Manage your Licenses	1197
12.2.Manage License Allocation.	1206
12.3.Bill Forecast	1210
Appendix 1a: Endpoint Manager Services - IP Nos, Host Names and Port Details - EU Customers	1211
Appendix 1b: Endpoint Manager Services - IP Nos, Host Names and Port Details - US Customers	1223
Appendix 2 - Endpoint Manager License Types	1234
Appendix 3: Pre-configured Profiles	1236



1. Introduction to Endpoint Manager

Endpoint Manager (EM) lets you manage, monitor and secure devices which connect to your network.

- Admins must first add users to EM then enroll devices/endpoints for those users. Supported operating systems include Android, iOS, Mac OS, Windows and Linux.
- Once a device has been added, admins can apply profiles which determine the device's network access rights, security settings and other features.
- Each license covers one device per user. You will need additional licenses for each device you add for a user.



Guide Structure

This guide will take you through the configuration and use of Endpoint Manager and is broken down into the following sections:

Introduction to Endpoint Manager - High level overview of the service which introduces the features and concepts that are discussed later in the guide.

The Administrative Console

The Dashboard

Users and User Groups

- Manage Users
 - Create New User Accounts
 - Enroll User Devices for Management
 - View User Details
 - Assign Configuration Profiles to User Devices
 - Remove a User
 - Generate New Password for a User



- Reset Two Factor Authentication for a User
- Run Procedures on User Devices
- Manage User Groups
 - Create a New User Group
 - Edit a User Group
 - Assign Configuration Profiles to a User Group
 - Remove a User Group
 - Run Procedure on Group Devices
- Configure Role Based Access Control for Users
 - Create a New Role
 - Manage Role Rermissions and Assign to Users
 - Remove a Role
 - Manage Roles Assigned to a User

Devices and Device Groups

- Manage Device Groups
 - Create Device Groups
 - Edit a Device Group
 - Assign Configuration Profiles to a Device Group
 - Remove a Device Group
 - Run Procedures on Customer Groups
- Manage Devices
 - Add New Devices
 - Manage Windows Devices
 - Manage Mac OS Devices
 - Manage Linux Devices
 - Manage Android Devices
 - Manage iOS Devices
 - View User Information
 - Remove a Device
 - Remote Management of Windows and Mac OS Devices
 - Remotely Manage Folders and Files on Windows Devices
 - Manage Processes on Remote Windows Devices
 - Manage Services on Remote Windows Devices
 - Use Command Prompts on Remote Windows Devices
 - Apply Procedures to Windows Devices
 - Remotely Install and Update Packages on Windows Devices
 - Remotely Install Packages on Mac OS Devices
 - Remotely Install Packages on Linux Devices
 - Send Enrollment Link to iOS Devices
 - Install Apps on Android / iOS Devices
 - Generate an Alarm on Android Devices
 - Remotely Lock Mobile and Mac OS Devices
 - Wipe Selected Mobile and Mac Devices
 - Assign Configuration Profile to Devices



- Set / Reset Screen Lock Password for Mobile Devices
- Update Device Information
- Send Text Messages to Mobile Devices
- Restart Selected Windows Devices
- Change a Device's Owner
- Change Device Ownership Status
- Generate Device List Report
- Bulk Enrollment of Devices
 - Enroll Windows, Mac OS and Linux Devices by Installing the EM Communication Client Package
 - Enroll the Android and iOS Devices of Active Directory Users
 - Download and Install the Remote Control Tool

Configuration Templates

- Create Configuration Profiles
 - Profiles for Android Devices
 - Profiles for iOS Devices
 - Profiles for Windows Device
 - Profiles for Mac OS Devices
 - Profiles for Linux Devices
- View and Manage Profiles
 - Export and Import Configuration Profiles
 - Clone a Profile
- Edit Configuration Profiles
- Manage Default Profiles
- Manage Alerts
 - Create a New Alert
 - Edit / Delete an Alert
- Manage Procedures
 - View and Manage Procedures
 - Create a Custom Procedure
 - Combine Procedures to Build Broader Procedures
 - Review / Approve / Decline New Procedures
 - Add a Procedure to a Profile / Procedure Schedules
 - Import / Export / Clone Procedures
 - Change Alert Settings
 - Apply Procedures to Devices
 - Edit / Delete Procedures
 - View Procedure Results
- Manage Monitors
 - Create Monitors and Add them to Profiles
 - View and Edit Monitors
- Data Loss Prevention Rules
 - Create DLP Discovery Rules and Add them to Profiles



- View and Edit DLP Discovery Rules
- Network Management
 - Create, Manage and Run Network Discovery Tasks
- Applications
- View Applications on Android and iOS Devices
 - Blacklist and Whitelist Applications
- Patch Management
 - Manage OS Patches on Windows Endpoints
 - Install 3rd Party Application Patches on Windows Endpoints
- View and Manage Applications Installed on Windows Devices
 - Uninstall a Windows Application from Selected Devices
 - Uninstall a Windows Application from All Devices
- Vulnerability Management

Application Store

- iOS Apps
 - Add iOS Apps and Installing them on Devices
 - Manage iOS Apps
- Android Apps
 - Add Android Apps and Install them on Devices
 - Manage Android Apps
- Windows Apps
 - Install Windows Apps on Devices

Security Sub-Systems

- Security Dashboards
 - View Security Events by Time
 - View Events by File
 - View Security Events by Device
- View Contained Applications
- Manage File Trust Ratings on Windows Devices
- View list of Valkyrie Analyzed Files
- Antivirus and File Rating Scans
 - Run Antivirus and/or File Rating Scans on Devices
 - Handle Malware on Scanned Devices
 - Update Virus Signature Database on Windows, Mac OS and Linux Devices
- View and Manage Identified Malware
- View and Manage Quarantined Items
- View Android Threat History
- View and Manage Autorun Items
- View History of External Device Connection Attempts
- Data Loss Prevention Scans
 - DLP Logs
 - DLP Quarantined Files



Configure Endpoint Manager

- Email Notifications, Templates and Custom Variables
 - Configure Email Templates
 - Configure Email Notifications
 - Create and Manage Custom Variables
 - Create and Manage Registry Groups
 - Create and Manage COM Groups
 - Create and Manage File Groups
 - View and Mange Pattern Variables
 - View and Manage Keyword Groups
- Endpoint Manager Portal Configuration
 - Import User Groups from LDAP
 - Communication and Security Client Settings
 - Configure the Android Client
 - Android General Settings
 - Android Client Antivirus Settings
 - Add Google Cloud Messaging (GCM) Token
 - Add Apple Push Notification Certificate
 - Configure Windows Client
 - Communication Client Settings
 - Security Client Settings
 - Manage Endpoint Manager Extensions
 - Endpoint Manager Reports
 - Device Removal Settings
 - Account Security Settings
 - Set-up Administrator's Time Zone and Language
 - Configure Audit Log Settings
- Integrate Apple DEP with Endpoint Manager
 - Link Endpoint Manager with Apple DEP
 - Manage Apple DEP Devices
 - Manage Apple DEP Profiles
 - Configure Apple DEP Notifications
 - View Version and Support Information

License Management

- Manage your Licenses
- Manage License Allocation
- Bill Forecast

Appendix 1a: Endpoint Manager Services - IP Nos, Host Names and Port Details - EU Customers

Appendix 1b: Endpoint Manager Services - IP Nos, Host Names and Port Details - US Customers

Appendix 2: Pre-configured Profiles

Appendix 3: Pre-configured Profiles



1.1. Key Concepts

Mobile Device - For the purposes of this guide, a mobile device is any Android or iOS smart phone or tablet that is allowed to connect to the enterprise network. Endpoint Manager allows network administrators to remotely configure device access rights, security settings, general preferences and to monitor and manage the device. Mobile devices may be employee or company owned.

User - An employee or guest of the enterprise whose device(s) are managed by the EM console. Users must be created before their devices can be added. Users can be added manually or by importing user groups from an AD server.

Device Group - An admin-defined grouping of Android, iOS, Linux, MAC or Windows devices. Configuration profiles applied to a device group will be deployed to all devices in the group.

Quarantine - Malware found on managed networks can either be deleted or isolated in a secure environment known as 'quarantine'. Files moved to quarantine are encrypted so they cannot be executed. Admins can review quarantined items and delete or release the files. Quarantined files can also be added to the local whitelist and submitted to Comodo as a potential false-positive.

Configuration Profile - A configuration profile is a collection of settings applied to managed devices which determines their network access rights, overall security policy, antivirus scan schedule, and other preferences. Profiles are operating system specific and can be applied to individual devices, device groups, users or user groups. Endpoint Manager ships with a 'default' profile for each supported operating system (iOS, Android, MAC, Linux and Windows). The default profile is automatically applied to a user/device *if* no custom profile exists.

Comodo Client Security - Comodo Client Security (CCS) is the remotely managed endpoint security software installed on managed Windows devices. It offers complete protection against internal and external threats by combining a powerful antivirus, an enterprise class packet filtering firewall, an advanced host intrusion prevention system (HIPS) and Containment feature that runs unknown and unrecognized applications in an isolated environment at the endpoints. Each component of CCS can be configured to offer desired security level by applying configuration profiles.

• CCS can be white-labelled with your own company branding and UI texts. You can customize the company name, company logo, product logo and more.

Default Profile - Default profiles are immediately applied to a device when it is first enrolled into Endpoint Manager. Default profiles are split into four types - iOS default profiles, Mac OS default profiles, Android default profiles and Windows default profiles. Multiple default profiles can be created and applied to a device or group of devices.

Communication Client (a.k.a EM Agent) - The communication client (CC) is an agent which needs to be installed on all devices so they can be managed by Endpoint Manager. The client is responsible for receiving and executing tasks. Tasks include implementing configuration profiles, fetching device details, running antivirus scans, adding or removing apps and wiping the device.

• CC can be white-labeled with your own company branding and UI texts. You can customize the company name, company logo, product logo and more. You can also specify your support email, support website and support email in the CC 'About' dialog.

Notifications - Notifications are generated if a threat is found on a device, or if an app is installed or removed. You can choose to send notifications to admins only, to a mailing list, or to specific users. Threat notifications are also shown in the Endpoint Manager dashboard.

Patch Management - The patch management module lets you monitor and install updates for Windows and 3rd party software on Windows devices.

Valkyrie - Valkyrie is a cloud-based file verdicting service that tests unknown files with a range of static and behavioral checks in order to identify those that are malicious. CCS on managed Windows computers can automatically submit unknown files to Valkyrie for analysis. The results of these tests produce a trust verdict on the file which can be viewed from the EM interface.

Data Loss Prevention - A DLP discovery scan locates files containing sensitive information on managed Windows devices. For example, the scans find credit card numbers, social security numbers, bank account numbers, etc. You can then take actions to secure that data where required.



Active Directory - Endpoint Manager allows administrators to add multiple Lightweight Directory Access Protocol (LDAP) accounts for the purpose of importing user groups and users.

1.2. Best Practices

1. 'Default' profiles are automatically applied to a device if no custom profile exists for the device. Endpoint Manager ships with default profiles for each supported operating system, but you can also mark any custom profile as 'default' if you wish.

See Manage Default Profiles for more information.

2. Though it is possible to save all settings in a single profile, an option worth considering is to create separate profiles dedicated to the implementation of a single setting group. You can apply multiple profiles at once to a device or group. For example, you could name a profile 'Android_passcode_profile' and configure only the passcode rules. You could create another called 'Android_VPN_settings' and so on. Adding or removing a profile from a device would let you quickly troubleshoot if a particular setting is causing issues.

See Create Configuration Profiles for more details.

3. Each license allows you to enroll one mobile device or one Windows / Mac / Linux endpoint for a single user. You will need additional licenses for each device you add for a user. We encourage admins to evaluate the average number of devices per user and to set max. enrollments accordingly.

See Enroll Users' Devices for Management for more details.

4. Creating a group of devices is a great time-saver if the policies applied to them are going to be the same.

See Manage Device Groups for more details.

- 5. The first level of defense on any device is to set a complex passcode policy. Endpoint Manager allows you specify passwords which are a combination of numbers, letters, special symbols and of a minimum length set by you. You can also set passcode lifetimes, reuse policy and define whether data should be automatically wiped after a certain number of failed logins.
- 6. Decide what restrictions are required for *your* company and *your* users. For example, disabling cell-phone cameras might be expected and mandatory in certain corporate environments but could be seen as a savage affront to liberties in more relaxed offices. Endpoint Manager offers flexible restrictions for Android devices over items such as Wi-Fi, packet data, bluetooth connectivity and use of camera. iOS restrictions are much more granular and also include App purchases, game center, voice dialing and more.

See Profiles for Android Devices and Profiles for iOS Devices for more details.

7. Keeps an eye on the apps you allow in your organization. Apps can be useful and productive to your employees but some may pose a malware or data-leak risk for your organization. EM provides you the ability to blacklist and whitelist apps, to govern how apps behave and to determine whether users are allowed to install apps from 3rd party vendors. You can also remotely uninstall unwanted applications from Windows devices.

See **Applications** for more details.

- 8. Keeping enrolled devices free from malware is vital to your organization's security. It is advisable to run antivirus scans on devices regularly per your company's needs. EM allows you to create a scheduled antivirus scan profile that automates the process of AV scans. If needed, AV scans can also be run instantly for selected devices or all enrolled devices.
- 9. You can create custom roles for users which determine their permissions within Endpoint Manager. See Configure the Role-Based Access Control for Users for more details.
- 10. Keep on top of your devices. Check device status regularly for compliance with deployed profiles, and take advantage of Endpoint Manager's detailed reporting system. See The Dashboard and Manage Devices and Security Dashboards or more details.



1.3. Quick Start

Click here to view the Endpoint Manager quick-start guide.

1.4. Login into the Admin Console

After sign-up, you will receive an email containing your username and an account activation link. Click the link to activate your account and set your password. Once activated, you can login to Endpoint Manager using any browser.

- ITarian customers:
 - Login to your ITarian account
 - Click 'Applications' > 'Endpoint Manager'.

Note. Endpoint Manager admins created in Endpoint Manager itself can login directly to the EM console:


- MSP account Login at https://<your company name>-msp.cmdm.comodo.com/user/site/login
- Enterprise account Login at https://<your company name>.cmdm.comodo.com/user/site/login

Endpoint Manager standalone customers:

- Login at: https://<your company name>.cmdm.comodo.com/user/site/login
 - Where <your company name> is your Endpoint Manager company name.
- We sent you this URL in your account confirmation email.


Usernames and passwords are case sensitive. Please make sure that you use the correct case and caps lock is OFF.

Click 'I forgot my password' if you can't recall your password. A mail will be sent to your registered email with a link to reset your password.




The EM welcome screen is shown:





- · Select the products that you want help with and click 'Submit'
- Interactive guides Click the help icon at bottom-right to view walk-through tutorials on common tasks:




Note - You need to configure your firewall to allow Endpoint Manager to communicate with our servers and your managed devices. IPs, host-names and ports are detailed in **Appendix 1**.



2. The Admin Console

The admin console is the nerve center of Endpoint Manager (EM), allowing you to add users, enroll devices, apply configuration profiles, run virus scans and more.



Once logged-in, admins can access different areas of the console using the menu on the left.

Dashboard - Contains charts and graphs which show the structure and security status of devices in your network. See **The Dashboard** for more details.

Devices - Manage and control enrolled devices, remotely install applications, generate sirens, wipe, lock and power off enrolled devices, remotely install and manage apps on devices, manage device groups and more. See **Devices** and **Device Groups** for more details.



Users - Create and manage users and user groups, enroll of their devices and assign configuration profiles to devices. See **Users and User Groups** for more details.

Configuration Templates - Profiles govern a device's network access rights, scan schedule and other system settings. You can create and manage profiles for iOS, Android Windows, Mac OS and Linux devices. See **Configuration Templates** for more details.

Network Management - Run device discovery scans on your networks. Discovery scans help you identity what endpoints are connected to a network. You can then enroll these devices to Endpoint Manager. See **Network Management** for more details.

Application Store - Repository of applications which can be pushed to iOS/Android/Windows devices directly from EM. See **Application Store** for more details.


Applications - View and manage applications installed on Android, iOS and Windows devices. Manage patches on Windows devices. See **Applications** for more details.

Security Sub-Systems - View event logs, run AV scans and database updates. View and manage malware, quarantined items and contained applications. See **Security Sub-Systems** for more details.

License Management - Manage your subscriptions, distribute seats from a single license to different customers, and assign seats from multiple licenses to the same customer. See **License Management** for more information.

Settings - Configure email notifications, active directory, Google Cloud Messaging (GCM) and Apple Push Notification (APN) certificates and more. See **Configure Endpoint Manager** for more details.

The buttons on the top of the interface allows to view the EM notifications, create users and enroll devices, expand/collapse the left side tabs and logout.





Endpoint Manager	Click the logo to open the 'Welcome' screen. See Login into the Admin Console for more details.
& Logout (coyoteewile@yahoo.com)	The username of the person currently logged in. • Click this to log out of EM console.
License Options	Allows you to upgrade to the 'Premium' or 'Managed' version of EM.

3. The Dashboard

Click 'Dashboard' in the left menu to open this page.

The dashboard shows real-time data about the operating system, connection status and security posture of all devices enrolled to Endpoint Manager (EM). It contains pie charts showing device types, platforms, ownership, scan status and compliance status. The dashboard also lets you view Valkyrie results, view notifications, and generate reports.


The dashboard is divided into six sections:

- Audit Charts which show the operating systems and client versions installed on devices on your network.
 Also contains charts which show the types of devices in your network, and whether the devices are personal or corporate. See the Audit section for more details.
- Compliance Statistics which detail how compliant your devices are with EM security policies. For
 example, device connection status, devices with viruses, devices with blacklisted applications, rooted and
 jailbroken devices, and device scan status. See Compliance for more details.
- Valkyrie A summary of verdicts on unknown files submitted to the Valkyrie file analysis system. See
 Valkyrie for more details.
- Reports A list of all reports generated by Endpoint Manager. You can also create new reports from here.
 See Reports section for more information.
- Notifications A list of notifications sent to the administrator by EM. See Notifications for more details.
- Audit Logs A list of actions taken on managed devices by admins and staff. Example actions include
 applying profiles, remote installation of packages and more. See Audit Logs for more details.

Audit


Click 'Dashboard' on the left then 'Audit'





· Click 'Customize' at top-right if you want to change which charts are shown on the page





- Use the 'On/Off' switches to add or remove charts from the dashboard
- Click the 'Customize' icon

 Click the 'Customize' icon

 to view the number of charts removed from the default view
- Click and hold the icon at top right of a tile to move it around the page.




Operating System

Shows enrolled devices by operating system. Place your mouse cursor over a sector or the legend to see further details.

• Click on an item in the legend to view the respective 'Device List' page.

For example, clicking on 'Android' in the legend will open the 'Device List' page displaying the list of Android devices. See 'Devices' for more details.



Security Client Version (Windows) 1 10.7.0.6977 1 10.7.0.6975 1 10.7.0.6857 1 Latest version: 10.7.0.6981

Security Client Version (Windows)

The versions of Comodo Client Security installed on Windows devices on your network. Comodo Client Security is the antivirus/security software on an endpoint.

- The number of devices using each version is shown to the right of the version number.
- Click the number to view all devices using that version.
- The latest version of the client is shown underneath the chart.

Update to the latest version - Click the number, select the target devices, then click 'Install or Manage Packages'.

See Remotely Install and Update Packages on Windows Devices for more details.


Communication Client Version (Windows) O 6.22.16531.18090 O 6.22.16061.18090 O 6.20.13290.18070 Latest version: 6.22.16533.18090

Communication Client Version (Windows)

The versions of Communication Client installed on Windows devices on your network. This is the agent which sends updates to the EM console.

- The number of devices using each version is shown to the right of the version number.
- Click the number to view all devices using that version.
- The latest version of the client is shown underneath the chart.
- Update to the latest version Click the number, select the target devices, then click 'Install or Manage Packages'.

See Remotely Install and Update Packages on Windows Devices for more details.



Security Client Version (Mac OS)

The versions of the security client installed on MAC OS devices on your network. The security client is the Comodo Client Security for MAC (CCS for Mac) software on an endpoint.


- The number of devices using each version is shown to the right of the version number.
- Click the number to view all devices using that version.
- The latest version of the client is shown underneath the chart.
- Update to the latest version Click the number, select the target devices, then click 'Install or Manage Packages'.


See Remotely Install Packages on Mac OS Devices for more details.

Mobile Agent Version (Android)

The versions of the mobile agent installed on Android device in your network.

- The number of devices using each version is shown to the right of the version number.
- Click the number to view all devices using that version.
- The latest version of the client is shown underneath the chart.





Device Types

Shows the composition of your device fleet by device type. Place your mouse cursor over a sector see further details.

• Click an item in the legend to view the respective 'Device List' page.

For example, clicking on 'Tablet' in the legend will open the 'Device List' page displaying the list of tablet devices. See 'Devices' for more details.

Ownership Types

Ownership types can be 'Corporate', 'Personal' or 'Not Specified'.

• Click an item in the legend to view the respective 'Device List' page.


For example, clicking on 'Personal' in the legend will



show all devices in that category. See 'Devices' for more details.

Change ownership type:


 Click 'Devices' > 'Device List' > click a device name > Click 'Owner' button > 'Change ownership'.



Compliance

The compliance dashboard monitors the status of managed devices with regards to various security and activity criteria. Charts shown include, devices with viruses, devices with blacklisted applications, device requiring database updates, rooted and jail-broken devices, devices which are unresponsive and more.

• To view the compliance status of devices, click 'Dashboard' in the left navigation then 'Compliance'.






- To customize the charts shown in the interface, click the 'Customize' button
- To update the data in a tile, click the 'Refresh' icon at top right
- To move tiles around, click and hold the grid icon in the top right corner and drag the tile to the desired position.

Top 5 Vulnerability by Device Counts


Shows the top five weaknesses detected by EM on the enrolled devices. Placing the mouse cursor over a sector or the legend displays further details. See 'Vulnerability Management' for details about viewing the vulnerabilities and running security patches on the devices.



Click a vulnerability identifier (CVE code) to view the devices that require the security patch. See 'Run a
Security Patch on Devices' to know how to deploy the security patch.

Top 5 Vulnerable Devices by Vulnerability Counts

Shows the top five devices that require security patches. Placing the mouse cursor over a sector or the legend displays further details. See 'Vulnerability Management' for details about viewing vulnerabilities and running security patches on the devices.




 Click a device name to view the details of the required patches. See 'View and Manage Patches for Windows and 3rd Party Applications' for deploying patches on devices.



Endpoint Patching Status

Shows the patch statuses on your enrolled devices. Placing the mouse cursor over a sector or the legend displays further details. See **Patch Management** for details about deploying patches.




Click an item in the legend to view the respective 'Device List' page.

For example, clicking 'Missing Critical Patches' will open the 'Device Management' page displaying devices that require the critical patches. See 'Devices and Device Groups' for more details.

Devices With Viruses

Shows how many enrolled devices are affected by viruses and how many are clean. Placing the mouse cursor over a sector or the legend displays further details. See **Antivirus Scans** for details about scanning for viruses on enrolled devices.




• Click an item in the legend to view the respective 'Device List' page.

For example, clicking on 'With virus(es)' will open the 'Device List' page displaying devices that contain viruses. See 'Devices and Device Groups' for more details.

Active and Inactive Devices Last 24 Hours


Shows the connectivity status of enrolled devices. Devices which have not contacted EM for more than 24 hours are marked as 'inactive'. Placing the mouse cursor over a sector or the legend displays the further details.



For example, clicking on 'Active Devices' will open the 'Device List' page displaying the list of active devices. Similarly clicking on the 'Inactive Device' legend will open the 'Device List' page displaying the list of inactive devices. The devices screens allow you to manage the enrolled devices. See "Devices and Device Groups' for more details.

Devices with Blacklisted Applications

Displays how many devices contain blacklisted apps versus those that are free of blacklisted apps. Placing the mouse cursor over a sector or the legend displays further details. See **Applications** for details about adding and removing apps from blacklist.




Click an item in the legend to view the respective 'Device List' page.

For example, clicking on 'With Blacklisted Applications' legend will open the 'Device List' page displaying the list of devices that have blacklisted applications on them. See "**Devices and Device Groups**' for more details.

Devices Responses for Virus Scan

Shows how many devices have responded to virus scan requests. Placing the mouse cursor over a sector or the legend displays the further details. See **Antivirus Scans** for details about scanning for viruses on enrolled devices.




For example, clicking on 'With response on virus scan' legend will open the 'Antivirus Device List' page displaying the list of devices that are responding to scan command.

The 'Antivirus Device List' page allows you to run antivirus scans on selected devices. See **Antivirus Scans** for more details.

Rooted And Jail-broken Devices

Shows how many devices in your fleet are are rooted or jail-broken. Placing the mouse cursor over a sector or the legend displays the further details.



Click an item in the legend to view the respective 'Device List' page.

For example, clicking on 'Normal' in the legend will open the 'Device List' page displaying the list of devices that are normal, that is, not rooted or jail-broken. See 'Manage Devices' for more details.

Devices With Device Management Apps

Shows how many devices have the communication client. Android, Windows. Mac OS and Linux devices can only be enrolled with the EM app/communication Client (CC). iOS devices communicate with EM via the EM profile that was installed during enrollment and do not require the app. However, installing the app will provide enhanced functionality such as device location and the ability to send messages to the device from the admin panel.


Placing the mouse cursor over a sector or the legend displays the further details.



For example, clicking on 'With device management App' will open the 'Device List' page displaying the list of devices that have the EM app installed. See 'Manage Devices' for more details.

Device Online

Shows enrolled devices by online/offline status. Devices will shown as offline if they are turned-off, are not communicating with EM for other reasons, or if Communication Client is not running. Placing the mouse cursor over a sector or the legend displays the further details.




Click an item in the legend to view the respective 'Device List' page.

For example, clicking on 'Online' will open the 'Device List' page displaying the list of devices that are online. See 'Manage Devices' for more details.

Scan Status


Shows the progress and results of antivirus scans on enrolled devices. Placing the mouse cursor over a sector or the legend displays the further details.



For example, clicking on 'Virus Found' in the legend will open the 'Antivirus Device List' page displaying the list of devices in which the malware were detected. See 'Antivirus Scans' for more details.

Antivirus DB Update

Shows the progress and results of AV database updates on enrolled devices. Place your mouse cursor over a sector to view extra details.



Click an item in the legend to view the respective 'Device List' page.


For example, clicking on 'Complete' in the legend will show devices which have the latest virus database. See **Antivirus Scans**' for more details.

Security Product Configuration

Shows how many of your enrolled devices have 'Safe' or 'Not Protected' statuses. 'Not Protected' means:

- Comodo Client Security (CCS) is not installed on the devices
- CCS is installed but Anti-virus is not enabled in the deployed profiles on the devices







Click an item in the legend to view the respective 'Device List' page.


For example, clicking on 'Safe' will open the 'Device List' page displaying the list of devices that have Antivirus installed. See 'Devices and Device Groups' for more details.

Valkyrie

- Valkyrie is a cloud-based file analysis service that tests unknown files with a range of static and behavioral checks in order to identify those that are malicious.
- To use the service, apply a profile to CCS that contains the 'Valkyrie' component.
 - Click 'Configuration Templates' > 'Profiles'
 - Click the name of the profile you want to edit, or click 'Create' to make a new profile
 - Click the 'Add Profile Section' button > 'Valkyrie'
 - Click 'Save'
- All results will be displayed in the Valkyrie dashboard. See Valkyrie Settings in Create Windows Profile for more details.

Note: The version of Valkyrie that comes with the free version of EM is limited to the online testing service. The Premium/Managed version also includes manual file testing by ITarian research labs, helping enterprises quickly create definitive whitelists of trusted files. Valkyrie is also available as a standalone service. Contact your ITarian account manager for further details.






Unparalleled Protection by Comodo (Last Week)

Shows the number of threats identified by Valkyrie over the past week versus the user's previous vendor and the antivirus industry as a whole.

Place the mouse cursor over a sector or the legend to see the percentage of number of files in a particular category.

See Manage File Trust Ratings on Windows Devices for more details on Windows File List screen.





Unparalleled Protection By Comodo (All Time)

Shows the number of threats identified by Valkyrie since installation versus the user's previous vendor and the antivirus industry as a whole.

Place the mouse cursor over a sector or the legend to see the percentage of number of files in a particular category.

See Manage File Trust Ratings on Windows Devices for more details on Windows File List screen.



Globally blocked

C) III

162

53

File Statistics (Windows Devices)

Shows the trust rating and status of files on your network.

See Manage File Trust Ratings on Windows

Devices, for more details on Windows File List screen

 Click any item in the legend will to open the respective 'File List' page.

For example, clicking on 'Unrecognized' will open the 'Application Control' > 'Unrecognized' page displaying the list of unrecognized files detected from enrolled devices. See 'Manage File Trust Ratings on Windows Devices' for more details



uploaded

Valkyrie File Verdicts (Last Week)


71.4%

Displays Valkyrie trust verdicts on unknown files for the previous 7 days. This includes the number of unknown files identified as malicious, those that remain unknown, and those that were white-listed (trusted). The total amount of unknown files analyzed is shown at the bottom.

File Statistics (Windows Devices)

Place your mouse cursor over a sector or the legend to view the percentage of files in that category.

See Manage File Trust Ratings on Windows Devices, for more details on Windows File List screen.



Valkyrie File Verdicts (All Time)

Displays Valkyrie trust verdicts on unknown files for the lifetime of your account. This includes the number of unknown files identified as malicious, those that remain unknown, and those that were white-listed (trusted). The total amount of unknown files analyzed is shown at the bottom.

Place your mouse cursor over a sector or the legend to view the percentage of files in that category.

See Manage File Trust Ratings on Windows


Devices, for more details on Windows File List screen.

Reports

Endpoint Manager can create a wide variety of reports on system and malware activity on your fleet of devices.

- Click 'Dashboard' on the left then 'Reports'
- The reports interface lets you generate and download many different report types:





Column Header	Description
Name	The subject of the report. • Click the name to view report details and download the report.
Туре	The file format of the report.
Status	Whether or not the report has been downloaded by any user.
Created By	The admin who generated the report. • Click the admin name to view their details. See View User Details if you need help with this.
Created At	The date and time the report was generated

- Click any column header to sort items in ascending/descending order of items in that column.
- Click the funnel icon at top-right to filter and search reports

You can generate reports from the reports interface or from individual product areas:

- 1. **'Dashboard' > 'Reports' interface** Lets you generate following report types:
 - Android Antivirus
 - Windows Antivirus
 - Windows Malware List
 - Windows Top Malware
 - Windows Quarantine
 - Hardware Inventory

These reports are generated in spreadsheet (.xls) file format.



2. From specific interfaces:

- 'Users' menu
 - User List Click 'Users' > 'User Groups' > 'Export'. Click here for more details.
 - User Groups Click 'Users' > 'User List' > 'Export'. Click here for more details.
 - Role Management:
 - Roles Click 'Users' > 'Role Management' > 'Roles' > 'Export'. Click here for more details.
 - Users Click 'Users' > 'Role Management' > 'Users' > 'Export'. Click here for more details.
- 'Devices' main menu
 - Device List Click 'Devices' > 'Device List' > 'Export'. Click here for more details.
 - Device Details > File List Click 'Devices' > 'Device List' > Any Windows Device > 'File List' > 'Export'.
 Click here for more details.
- 'Configuration Templates' menu
 - Profiles Click 'Configuration Templates' > 'Profiles' > 'Export'. Click here for more details.
 - Alerts Click 'Configuration Templates' > 'Alerts' > 'Export'. Click here for more details.
 - 'Procedures' main menu
 - Procedures List Click 'Configuration Templates' > 'Procedures' > 'Export'. Click here for more details.
 - Procedure Execution Logs Click 'Configuration Templates' > 'Procedures' > 'any scrip procedure'
 > 'Execution Log' sub-tab > 'Export'. Click here for more details.
- Network Management menu
 - Discoveries Click 'Network Management' > 'Discoveries' > 'Export'. Click here for more details.
 - Managed Devices List Click 'Network Management' > 'Devices' > 'Managed Devices' tab > 'Export'. Click here for more details.
 - Discovered Devices List Click 'Network Management' > 'Devices' > 'Discovered Devices' tab > 'Export'. Click here for more details.
- 'Application Store' menu
 - iOS Store Click 'Application Store' > 'iOS Store' > 'Export'. Click here for more details.
 - Android Store Click 'Application Store' > 'iOS Store' > 'Export'. Click here for more details.
- 'Applications' menu
 - Mobile Applications Click 'Applications' > 'Mobile Applications' > 'Export'. Click here for more details.
 - Patch Management Click 'Applications' > 'Patch Management' > 'Operating System' tab > 'Export'.
 Click here for more details.
- 'Security Subsystems' menu
 - Containment Click 'Security Sub-Systems' > 'Containment' > 'Export'. Click here for more details.
 - Application Control Click 'Security Sub-Systems' > 'Application Control' > 'Export'. Click here for more details.
 - Valkyrie Click 'Security Sub-Systems' > 'Valkyrie' > 'Export'. Click here for more details.
 - Device Control Click 'Security Sub-Systems' > 'Device Control' > 'Export'. Click here for more details.
 - Antivirus:
 - Device List Click 'Security Sub-Systems' > 'Antivirus' > 'Device List' tab > 'Export'. Click here for more details.
 - Current Malware List Click 'Security Sub-Systems' > 'Antivirus' > 'Current Malware List' tab > 'Export'. Click here for more details.




- Quarantined Files Click 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files' tab > 'Export'. Click here for more details.
- Android Threat History Click 'Security Sub-Systems' > 'Antivirus' > 'Android Threat History' tab > 'Export'. Click here for more details.
- Autoruns Items Click 'Security Sub-Systems' > 'Antivirus' > 'Autoruns Items' tab > 'Export'.
 Click here for more details.
- Data Loss Prevention Click 'Security Sub-Systems' > 'Data Loss Prevention' > 'Quarantined Files' tab > 'Export'. Click here for more details.
- License Management menu
 - Licenses Click 'License Management' > 'License Management' > 'Licenses' tab > 'Export'.
 Click here for more details
 - Customers Click 'License Management' > 'License Management' > 'Licenses' tab > select a license > 'Details' > 'Customers' tab > 'Export'. Click here for more details

These reports are generated in comma separated values (.csv) format.

Generate a report from the 'Reports' interface

• Click 'Generate Report' from the top and then click on the report type from the drop-down.




A new report will be generated for the selected report type.

To download a report, select it and click 'Download' at the top


ITarian Endpoint Manager - Administrator Guide





Click a report name to view report details.






• To remove a report from the list, select it and click 'Delete'.

Notifications



- The number of unread messages you have is shown on the notification icon:
- Click the icon to view the messages.





 Message titles also act as shortcuts to the relevant interface. For example, clicking on 'Malware Found on Windows device' message opens the 'Antivirus Current Malware List' screen.

Tip: You can also receive notifications as emails. Click 'Settings' > 'Email Notifications' to configure them. See **Configure Email Notifications** if you need help with this.

Audit Logs

Click 'Dashboard' > 'Audit Logs'


- Endpoint Manager logs actions implemented on managed devices by admins and staff. These logs can be useful when troubleshooting issues.
- You can forward logs to an external syslog server if required. See Configure EM Audit Log Settings for more on this.
- Example logged actions include:
 - Add or remove devices
 - Apply a security profile
 - Create or edit a profile
 - Package installations
 - Remote take-over sessions
 - Changes to containment settings
 - Remote file transfers
 - Auto-removal of old / duplicate devices
- Each log entry is accompanied with details such as the staff member who applied the action, the affected device, the action taken, and more.
- Logs are kept for up to one year for PCI-DSS compliance.
- You can generate a report containing logs for the past three months as a comma separated values (CSV) file.





	Audit Logs - Column Descriptions
Column Heading	Description
Staff	Username of the admin or staff member who executed the action. • Click the staff name to view their details. See View user details if you need help with the details interface.
Event Name	The action executed on the device. Examples include enrollment of devices, remote installation of Comodo and third party MSI packages, remote take-overs and device removals.
Affected Object	The device, device group, profile, procedure or file group on which the action was executed. • Click the name to view more details about the item • The details interface allows you to view and manage the respective item.
Old Value	The previous setting or value before the action was implemented. For example, if a Comodo package is remotely updated, the old version number of the package will be shown here.
New Value	The new setting or value after the action was implemented. For example, if a Comodo package is remotely updated, the version number of the new package will be shown here.
Extra Info	Additional details about the action. Additional details include devices on which the procedure was run, package installation parameters, profiles applied/removed, malware quarantined, antivirus scans run and so on. • Script or patch procedures - Click the 'Selected Devices' link to view devices on which the procedure was run. • Click a device name in the list to view its 'Device Details' interface
Session ID	String used to identify the connection session between the device and the EM server during the action.
Log Creation Date	Date and time of the event.
	Controls






Click the 'Refresh' icon to load the latest events.

Search and filter options


- Click any column header (except 'Event Name') to sort items in alphabetical order of items in that column
- To filter or search for a specific event, click the funnel icon at the top right.
- · You can filter items by various criteria or search for specific events.
- Click 'Apply' to run your filter.



Generate Audit Logs Reports

- Click 'Dashboard' > 'Audit Logs'.
- Click the funnel icon to filter which records are included in the report.
 - Click 'Export' above the table then choose 'Export to CSV'. You can export logs for up to the past 90 days (Day 1 - Day 90).





- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

4. Users and User Groups

- One of the first steps in setting up Endpoint Manager is to add users.
- Once you have added users, you can enroll the devices which belong to them. You can enroll iOS, Android, Windows, Mac OS and Linux devices.
- After enrolling a device, you can remotely manage and apply security policies to it. You can create user groups in order to apply policies to multiple devices.
- You can also assign users to a 'role'. A role determines what areas a user can access, and what tasks they can perform. You can assign users one of the built-in roles, or create a custom role with custom privileges.

There are two places you can add users to Endpoint Manager:

- The ITarian console (preferred)
- The Endpoint Manager interface


Users added via ITarian will also be available in other modules like Service Desk and Quote Manager. Users added via Endpoint Manager will only be available in Endpoint Manager.

• ITarian customers - See https://community.itarian.com/help/topic-452-1-946-13054-Manage-Admins,-Staff-and-Roles.html for details on how to add users via ITarian console.

The following sections describe how to add users via the EM interface.

The 'Users' menu at the left allows you to add, view and manage users/user groups and to manage roles:





The following sections explain more about each area:

- Manage Users
 - Create New User Accounts
 - Manually Add Users
 - Import Users from a CSV file
 - Enroll Users' Devices for Management
 - View the Details of a User
 - Assign Configuration Profile(s) to a Users' Devices
 - Remove a User
- Manage User Groups
 - Create a New User Group
 - Edit a User Group
 - Assign Configuration Profile to a User Group
 - Remove a User Group
- Configure Role Based Access Control for Users
 - Create a New Role
 - Manage Permissions and Users Assigned to a Role
 - Remove a Role
 - Manage Roles Assigned to a User

4.1. Manage Users

Click 'Users' > 'User List'


- You can enroll users to EM and assign them roles with different privilege levels (as 'administrators', 'technicians', 'users', or a custom role).
- Devices belonging to users can only be enrolled after adding them to EM.
- Users can be added using any of the following methods:
 - · Manually add user accounts
 - Import users from a comma separated values (.csv) file
 - Bulk enroll users and Windows endpoints from Active Directory (AD)



ITarian customers - Staff added in the ITarian console are automatically added as users in EM.

See https://community.itarian.com/help/topic-452-1-946-13054-Manage-Admins,-Staff-and-Roles.html if you need help to add staff/ manage roles in ITarian.

- The 'Users List' shows all user accounts that have been added to EM. Admins can add/manage users, enroll user devices, manage device configuration profiles and more.
- Click 'Users' > 'User List'



Column Heading	Description	
Name	 The login username of the user. Click the username to view and edit user details. See 'View the Details of a User' for more info. 	
Email	The registered email address of the user. Account activation and device enrollment mails are sent to this address.	
Phone Number	The registered phone number of the user.	
Number of Devices	The total number of devices enrolled for the user.	
2FA Status	 Indicates whether two-factor authentication (2FA) is enabled or not. Active - Indicates 2FA is activated by the user Not active - Indicates 2FA is not yet configured by the user for the first time Not configured - Indicates 2FA was reset by admin and user is yet to reconfigure it again. Not available - Indicates the user is added via ITarian portal. For these users, 2FA is done in the portal. 	
Last Login	Date and time that the user most recently accessed EM.	
	Controls	
Enroll Device	Add user devices for management by EM. You can enroll Android, iOS, Mac, Windows and Linux devices. See Enroll User Devices for Management for more details.	
Create User	Manually add user accounts to EM.	




	 You can only add devices for users after you have enrolled the users themselves. 	
	Users can also be designated as administrators.	
	See Manually Add Users for more details.	
Manage Profiles	A profile determines the security configuration and network access rights of a device. See Apply configuration profiles to devices for more details.	
Send Password Recovery Email	Reset the password of users who have admin privileges. The password allows them to login to the EM console. See Send password recovery emails for users to access the EM console for more details.	
Change Password	Generate new password for a user. See Generate New Password for a User for more details.	
Delete User	Terminate selected user accounts. See Remove a User for more details.	
Import User	Add new users by importing them from a comma separated values (CSV) file. See Import Users from a CSV File for more help.	
Export	Save a copy of the current user list as a comma separated values (CSV) file. The exported .csv is available in 'Dashboard' > 'Reports' See Export the List of Users for more details.	
Reset 2FA Token	Force users to configure new two-factor authentication codes. See Reset Two Factor Authentication Token for a User for more details.	
Run Procedure	Execute stand-alone instruction scripts and patches on managed devices. See Run Procedures on User Devices for more help with this.	

- · Click any column header to sort items in ascending/descending order
- Click the funnel button Υ at the right end to open the filter options.
- To display all items again, clear all filter fields and click 'OK'.
- By default, 20 search results are shown per page. Click the arrow next to 'Results per page' to increase the number up to a max of 200.

Export the List of Users

- Click 'Users' > 'User List'.
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button above the table then choose 'Export to CSV':





- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Please use the following links to find out more:

- Create New User Accounts
 - Manually Add Users
 - Import Users from a CSV File
- Enroll User Devices for Management
 - Enroll Android Devices
 - Enroll iOS Devices
 - Enroll Windows Endpoints
 - Enroll Mac OS Endpoints
 - Enroll Linux OS Endpoints
- View User Details
 - Update the Details of a User
- Assign Configuration Profile(s) to a User's Devices
- Remove a User
- Generate New Password for a User
- Reset Two Factor Authentication Token for a User
- Run Procedures on User Devices

4.1.1. Create New User Accounts

- You can add new accounts using any of the following methods:
 - Manually add users. Add individual users to EM
 - Click 'Users' > 'User List' > 'Create User' to start this process.
 - You need to specify their name, email address, the company they belong to, and their EM role.
 - See Manually Add Users if you need help with this.
 - Import users from .csv file. Import a list of users from a comma separated values file.
 - Click 'Users' > 'User Import' to start this process
 - The file should contain the following, separated values: 'Username' (mandatory), 'Email address' (mandatory) and 'Phone number' (optional).
 - The file should not contain column headers and each line should contain a single user.
 - Users are assigned the role you specify in the import dialog.
 - See Import Users from a CSV File if you need help with this



- New users will receive an enrollment mail which requests they activate their account and set their password.
- You can also bulk enroll users and Windows endpoints from Active Directory (AD) group policy. See Bulk
 Enrollment of Devices and 'Import User Groups from LDAP' for more details.

ITarian customers - Staff added in the ITarian console are automatically added as users in EM.

See https://community.itarian.com/help/topic-452-1-946-13054-Manage-Admins,-Staff-and-Roles.html if you need help to add staff/ manage roles in ITarian.

Device licenses: User devices can only be enrolled after the user has been added to the system.

- Each device license covers one device per user
- You need an additional license for each mobile device or endpoint you add for the same user. You can
 purchase additional licenses from the ITarian website if required. See View and Manage Licenses for
 more details.

The following sections explain how to:

- · Manually add users
- Import users from a CSV file

4.1.1.1. Manually Add Users


- Click 'Users' > 'User List' > 'Create User' button
- You can add new users by specifying their name, email address and other details.
- Once added, you can enroll Windows, Android, iOS, Mac OS and Linux devices for the user.
- New users with admin roles will receive an account activation email. They can login to Endpoint Manager after activating their account.


Add a new user

- Click 'Users' > 'User List'
- Click the 'Create User' button

or


Click the 'Add' button at the menu bar and choose 'Create User'.








The 'Create New User' appears:



'Create new user' Form - Table of Parameters		
Form Element	Туре	Description
Username	Text Field	Enter the login username for the user.
Email	Text Field	The email address of the user for registration to EM. Account and device enrollment mails will be sent to this address. Please ensure users respond to the device enrollment mail from the device(s) you intend to enroll.
Phone Number (Optional)	Text Field	The contact number of the user.
Company	Drop-down	Choose the company to which the user belongs.
		 MSP customers can add users from any company they have added to their account.
		Enterprise and EM stand-alone customers can only add users to the default company.
Assign role	Drop-down	Select the role to be assigned to the new user from the 'Assign role' drop-down.





EM ships with four default roles:

- Account Admin Can login to EM and access all management interfaces. You cannot assign account admin to a user. The role is automatically assigned to the person who opened the ITarian account. This role is not editable.
- Administrators Can login to EM and access all management interfaces. This role can be edited as required.
- Technician Can login to EM and access all management interfaces. The technician role has fewer privileges than the administrator role. This role can be edited as required.
- Users Cannot login to EM. If required, you can change role permissions to have access to the admin console. See Configure Role Based Access Control for Users for more details.


You can create custom roles which grant access to selected areas of EM. These roles can be assigned to users as required. All roles created in EM and ITarian will appear in the 'Assign Role' drop-down when adding a new user. See **Configure Role Based Access Control for Users** for more details.

• Enter the details, select the role for the new user and click the 'Submit' button.

Tip: User roles can be changed at any time in the 'Role Management' interface ('Users' > 'Role Management'). See **Managing Permissions and Assigned Users of a Role** if you need help with this.



A confirmation will be displayed:



Repeat the process to add more users.

Successfully added users will be listed in the 'Users' interface. The user's devices can now be enrolled to EM.

Endpoint Manager will send account activation mails to the newly added administrators. They can activate their account and set their login password by clicking the link in the email. An example mail is shown below:

Dear Grey Pelican,

Congratulations, your Endpoint Manager account has been successfully created. Please click the following link to activate your account and set up your password:

https://herculespopular-msp.cmdm.comodo.com/user/site/activate/username/Grey+Pelican/key/499cdc1039e5fd03080347b55a776adc658c5c77

Sincerely, Endpoint Manager team.

- User clicks the link and activates his EM account.
- Upon activation, the user will be able to login to EM with his user-name and password. Login at: https://<your company name>-msp.cmdm.comodo.com/ as shown in the mail link.
- Users added via EM can login to EM console only and cannot login to Itarian portal.
- If the portal administrator has configured two-factor authentication, then the user has to follow the onscreen instructions to setup this during login.

Note: By default, enrolled users with the role 'Users' do not receive an account activation mail nor gain console

ITarian Endpoint Manager - Administrator Guide



login rights. Only personnel with the default roles 'Administrator', 'Technician', or a custom role with access to the administrative console, will receive an activation email.

Should you wish, you can change role permissions to allow the default 'User' role to have access to the admin console. See **Configure Role Based Access Control for Users** for more details.

4.1.1.2. Import Users from a CSV File

- Click 'Users' > 'User List' > 'Import User'
- You can load a list of new users by importing them from a comma separated values (CSV) file
- You can also specify the role to be assigned to all users in the list
- After adding a user, you can enroll Windows, Android, iOS, Mac OS and Linux devices for them

Process in brief

- Create a CSV file containing the list of users using spreadsheet applications like Microsoft Excel or OpenOffice Calc and save it on your admin computer
- The file should contain the following, separated values: 'Username' (mandatory), 'Email address' (mandatory) and 'Phone number' (optional).
- The file should not contain column headers and each line should contain a single user.
- In the EM admin console, click 'Users' > 'User List' > 'Import User'
- Browse to and select the CSV file you want to import
- Select a company and a role for the imported users
- · Upload the file
- The users will be imported and enrolled to EM

Requirements for .csv file

There are two mandatory fields and one optional field per user account:

- Username (mandatory)
- Email address (mandatory)
- Phone number (optional)
- Each line in the CSV file should contain one user entry
- The CSV file should not contain column headers


Example:

"james", "james@ditherscons.com", "9876543210"

To import users from a list

- Click 'Users' > 'User List'
- Click 'Import User' on the top






'User Import' Form - Table of Parameters		
Parameter	Description	
CSV File	Click 'Browse' navigate to the location of the CSV file and select the file	
Company	The company to which the users belongs.	
	 ITarian MSP customers can add users from Companies/Organizations enrolled in their account. 	
	Start entering first few letters of the company name and select the company from the options	
	 ITarian Enterprise and EM stand-alone customers can only add users to the default company. 	
	Enter 'Default Company' in the Company field	
Role	The role to be assigned to all users in the list.	
	Start entering first few letters of the name of the role and select the role from the options	



	EM ships with four default roles:
	Account Admin - Can login to EM and access all management interfaces. You cannot assign account admin to a user. The role is automatically assigned to the person who opened the ITarian account. This role is not editable.
	 Administrators - Can login to EM and access all management interfaces. This role can be edited as required.
	 Technician - Can login to EM and access all management interfaces. The technician role has fewer privileges than the administrator role. This role can be edited as required.
	 Users - Cannot login to EM. If required, you can change role permissions to have access to the admin console. See Configure Role Based Access Control for Users for more details.
	You can create custom roles which grant access to selected areas of EM. These roles can be assigned to users as required. All roles created in EM and ITarian will appear in the 'Role' drop-down when importing new users. See Configure Role Based Access Control for Users for more details.
Do not send any enrollment notifications	Select whether or not the account creation notification mail or account activation mail is to be sent to the imported users.
	Note: The notification mails will not be sent if you select 'Users' role for the new users.

Configure the parameters and click 'Import users from List'




The progress will be displayed.

- If you want to stop the import process, click 'Discard Import'
- Once the users have been imported, you can enroll devices for them.
- Users will receive an account activation mail if they are assigned a role that has access to the admin console. This includes the standard 'Administrator' and 'Technician' roles.
 - Tip Enable 'Do not send any enrollment notifications' in the import screen if you do not want to send these mails.



- Users click the link in the mail to activate their account and configure their password.
- You will receive an error report if the import fails. See the following screenshot:



- The report can help pinpoint errors so you can rectify them.
 - · Click 'Export' to download the error report in .csv format
 - Click 'Clear errors report' to remove the report and retry the import.

4.1.2. Enroll User Devices for Management

You need to enroll devices to Endpoint Manager in order to manage those devices going forward. Reminder - you must first have **added users** before you can add their devices.

Click 'Users' > 'User List' > select users > click 'Enroll Device'.

ITarian Endpoint Manager - Administrator Guide



- Complete the wizard to send device enrollment mail to your users. Users must open the mail on the device itself. See the tutorial below.
- The mail contains an enrollment token. Multiple devices can be enrolled with the same token by the user simply responding to the mail from each device. Each token is valid for 90 days.
- Each license covers one device per user. You will need additional licenses for each device you add for a
 user. See Manage Licenses if you need help with this.
- You can also bulk enroll users and Windows endpoints by creating a software installation policy in Active Directory (AD). See Enroll Windows Devices Via AD Group Policy and 'Import User Groups from LDAP' for more details.
- You can also enroll iOS devices using your Apple DEP account. See 'Integrate Apple DEP with Endpoint Manager'
- This section explains how to enroll devices for multiple users

Tutorial


- Click 'Users' > 'User List' on the left
- Select the users for whom you want to add devices
 Or
- Click the 'Add' button on the menu bar then 'Enroll Device'.

This starts step 1 of the device enrollment wizard:

Step 1 - Device Options

- **Current device** Enrolls the device you are currently using. You may disregard this option at this stage as we are adding multiple devices with the 'Other device' option.
- Other device Add devices owned by the users you selected previously. Those users should already be listed in the 'Specify User' box:






- You can add additional, existing users by simply typing their email address in the box. Endpoint Manager will auto-suggest users that have already been created.
- Create New User Click if you want to add a new user to Endpoint Manager. You cannot add devices unless you have first added the users that own them. The add-user process is explained here.
- Click 'Next' to proceed to step 2.

Step 2 - Enrollment Options





TLDR -

- Click 'Not Specified' if you only want to install the communication client on target devices. The wizard will
 detect the target operating system and send the appropriate client to the device user.
- Click one of the operating system tiles if you also want to install the security client. Make sure the target devices use the operating system you selected.

There are two broad ways you can enroll devices:

Option 1 - Enroll + Protect - Single Operating System

- Click one of the operating system boxes to enroll devices of that type. Please make sure all your target devices use this operating system.
- The wizard will send enrollment mails that only provision the OS you choose. For example If you select
 the 'Windows' box, then the wizard will send enrollment mails which only contain download links for the
 Windows clients.
- Once you have chosen the OS, you can customize enrollment options as required. You can configure items such as enrollment type, reboot policy, client version, configuration profile and device name.

Option 2 - Enroll Only - Multiple Operating Systems

- Click the 'Not Specified' box. This option installs only the communication client, and doesn't install the security client.
- Your target devices can be a mix of operating systems rather than a single OS. This option auto-detects the OS of the device and emails the appropriate client link to the user.
- The latest version of the communication client is installed on each device. The MDM profile is installed on MAC devices



 Note - You can use this option to quickly connect devices to Endpoint Manager, then go back later and install the security client if required.

Enrollment Type

Applies to Windows, Mac and Linux devices.

- Enroll and Protect Installs both the communication client and the security client.
- · Just Enroll Installs only the communication client

Background. There are two types of client:

- Communication Client Connects the device to Endpoint Manager for central management. It is mandatory to install this client.
- **Security Client** This is the security software. Depending on the operating system, it includes antivirus, firewall, threat-containment, web-filtering, and more. It is optional to install this client.

Click 'Next' to skip to step 3 if you are happy with your choices on this page.

OR

Use the following links to read more about the various settings per OS:

- Windows
- Linux
- Mac OS
- iOS / Android

Windows

Setting	Description
Choose platform	Select Window OS version. 64 bit, 32 bit, or hybrid.
	The hybrid package will auto-detect and install the correct version.
Use default Communication Client	This client enrolls the endpoint for central management.
version	You can only change the CCC version if enabled in portal settings . If the option is not enabled then the 'Default version' is deployed.
Use default Communication Client Security version	This client installs security software such as antivirus, firewall and autocontainment.
	You can only change the CCS version if enabled in portal settings . If the option is not enabled then the 'Default version' is deployed.
Additional options	AV Database - Choose whether to include the latest virus database with the installation package. This increases the size of the package.
	If disabled, the client will download the latest database anyway when you run the first virus scan.
Configuration Profile	A configuration profile is a collection of settings which specify a device's network access rights, security settings, antivirus scan schedule, and more.
	The default is 'Windows - Security Level 1' profile. Choose a different profile if required.
	The default profile is recommended for most users and can always be changed later if required.



	 If you want to change it, type the first few characters of a profile name and choose from the suggestions that appear.
	 You can view the settings in a profile at 'Configuration Templates' > 'Profiles'.
Set Reboot Options	Endpoints need to be restarted to complete CCS installation. You have the following restart options:
	 Force the reboot in Restart the endpoint a certain length of time after installation. Select the delay period from the drop-down. A warning message is shown to the user prior to the restart.
	 Suppress reboot - Endpoint is not auto-restarted. The installation is finalized when the user next restarts the endpoint.
	Warn about reboot and let users postpone it - Shows a message to the user which tells them that the endpoint needs to be restarted. The user can choose when the restart happens.
	Optional. Type a custom message in the 'Reboot Message' field.
Device Name Options	Do Not Change - The device's existing name is used to identify the device in Endpoint Manager.
	 Change - Enter a new device name. Note - You can restore the original name from the device list screen if required.

• Click 'Next' to proceed to step 3

Linux

Setting	Description
Choose platform	Select Linux OS version
	Ubuntu / Debian (Hybrid Package)
	RHEL / CentOS (Hybrid Package)
	'Hybrid' just means the package is suitable for both types of OS.
Device Name Options	 Do Not Change - The device's existing name is used to identify the device in Endpoint Manager.
	 Change - Enter a new device name. Note - You can restore the original name from the device list screen if required.

• Click 'Next' to proceed to step 3

MacOS

Setting	Description
Select Method	With MDM profile (recommended) - Installs both the communication client and the Endpoint manager configuration profile. You can use the full suite of Endpoint Manager tools on your devices
	Without MDM profile - Installs only the communication client for



	connection to EM. 'Profile-less' enrollment lets you use Endpoint Manager to manage security while using another platform for general Mac management.
Device Name Options	Do Not Change - The device's existing name is used to identify the device in Endpoint Manager.
	Change - Enter a new device name. Note - You can restore the original name from the device list screen if required.

Click 'Next' to proceed to step 3


iOS / Android

- Device Name Options
 - **Do Not Change** The device's existing name is used to identify the device in Endpoint Manager.
 - Change Enter a new device name. Note You can restore the original name from the device list screen if required.
- Click 'Next' to proceed to step 3

Step 3 - Installation Summary

Review your choices so far.

The summary you see depends on the operating system and enrollment type:




- Click 'Back' or 'Change Configuration' (top-right) to revise your choices.
- Click 'Next' to proceed to step 4




Step 4 - Installation Instructions

The final step is to send out the enrollment emails to the device owners:



• Send - Click this to send enrollment mails to users with the settings you choose in steps 1, 2 and 3.



- Enroll Another Device Takes you back to step 1
- Go to Bulk Installation Package Takes you to bulk installation package screen to configure and enroll users in bulk. See 'Bulk Enrollment of Devices'
- Click 'Finish' to close the window.

Note - If you chose 'Current Device' in step 1, then you can enroll your device in two ways:

- 1. Download the client in the final step. Follow the instructions and complete the enrollment procedure.
- 2. Click 'Enrollment Instructions' at top-right, click the appropriate enrollment link to your device and complete the procedure.

An example mail that is sent to users is shown below:





Welcome to Endpoint Manager!

You are receiving this mail because your administrator wishes to enroll your smartphone, tablet, macOS, Linux or Windows device into the Endpoint Manager system. Doing so will make it easier and more secure to connect your personal devices to company networks. This mail explains how you can complete the enrollment process in a few short steps.

Note:

Make sure that you selected the operating system of the device that you want to enroll.
 This product allows the system administrator to collect device and application data,
 add/remove accounts and restrictions, list, install and manage apps, and remotely erase data on your device.

Device Enrollment:

Click this link to enroll your device

Sincerely, Endpoint Manager team.

 Clicking the link will take the user to a page which lets them download the appropriate communication client/profile:

Tip: Here's two other ways you can enroll devices for users:

- Click 'Users' > 'User List' > click the name of a user to open their details screen > click 'Enroll Device'
- Click 'Devices' > 'Device List' > 'Enroll Device'

The following sections contain help per device operating system:

- Enroll Android Devices
- Enroll iOS Devices
- Enroll Windows Endpoints
- Enroll Mac OS Endpoints
- Enroll Linux OS Endpoints

Note - See Appendix 1 for a list of ports that Endpoint Manager uses to communicate with endpoints and Comodo servers.

4.1.2.1. Enroll Android Devices

- After you have completed the setup process, Endpoint Manager will send an email to your users containing device enrollment instructions.
- Users should open the mail on the device itself.




Android device enrollment involves two steps:

- Step 1 Download and Install the communication client
- Step 2 Configure the client

Step 1 - Download and Install the communication client

- Open the mail on the device you want to enroll
- Tap the link in the mail to start the enrollment wizard
- Tap the 'Get it on Google Play' button:



· Download and install the client software from Google Play

Step 2 - Configure the communication client


The next step is to configure the client to connect to Endpoint Manager. There are two ways to do this:

- Automatic Configuration
- Manual Configuration

Automatic Configuration


After installation in step 1, go back to the device enrollment page and tap the 'Enroll' button under 'Step 2':





The client is automatically configured and the **End User License Agreement** screen appears. **Manual Configuration**

Users can manually configure the communication client to connect to Endpoint Manager by entering the server settings and token string (aka PIN). You can find these items on the enrollment page:






Manually configure the client

- Open the client by tapping the client icon on your device.
- This starts the client configuration wizard. Enroll the device by entering the server settings and unique token.

Server Settings



- Server URL The server URL is listed on the enrollment page as described above.
- Server port The server port is also listed on the enrollment page. Default = 443.
- · Tap the 'Connect' button. The 'Login' screen will open

Login to the Console

There are two ways to login to the console:


- Enter the token from the enrollment page in the 'PIN Code' tab OR
- Enter your domain username and password

Enter the token from the enrollment page

· Open the communication client



Open the 'Pin Code' tab:



- Enter the token from the enrollment page as the PIN
- Tap 'Login' then agree to the EULA.

Domain username and password


- Open the communication client
- Open the 'AD Credentials' tab

Prerequisite: Enrollment of user devices using their Active Directory (AD) credentials requires:

- The AD server to be integrated with EM
- The users to be imported from AD to EM.

See Import User Groups from LDAP for more details on this process.





- Enter the username and password you use to login to your network domain.
- Tap the 'Login' button

End User License Agreement



ITARIAN END USER LICENSE AGREEMENT AND TERMS OF SERVICE

ENDPOINT MANAGER

THIS AGREEMENT CONTAINS A BINDING ARBITRATION CLAUSE.

IMPORTANT - PLEASE READ THESE TERMS CAREFULLY BEFORE USING ITARIAN ENDPOINT MANAGER (THE "PRODUCT"). THE PRODUCT MEANS ALL OF THE ELECTRONIC FILES PROVIDED BY DOWNLOAD OR ACCESSED OR INSTALLED WITH THIS LICENSE AGREEMENT. BY USING THE PRODUCT, OR BY CLICKING ON "I ACCEPT" BELOW, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, THAT YOU UNDERSTAND IT, AND

I ACCEPT DENY

Scroll down then click the 'I Accept' button

This starts the client activation screen. Activation requires the client is given some privileges:





← Device administrator



Mobile Device Management..

Activating administrator will allow Mobile Device Management Client to perform the following operations:

Erase all data

Erase the phone's data without warning by performing a factory data reset.

Change the screen lock Change the screen lock

Change the screen lock.

Set password rules

Control the length and the characters allowed in screen lock passwords and PINs.

Monitor screen-unlock attempts

Monitor the number of incorrect passwords typed when unlocking the screen and lock the phone or erase all the phone's data if too many incorrect passwords are typed.

Lock the screen

Control how and when the screen locks.

Set screen lock password expiry


Change how frequently the screen lock

CANCEL

ACTIVATE

Tap 'Activate'.

The communication client home screen opens:



The device is now enrolled to EM. A security profile will be applied to the device as follows:

- If the user is already associated with a configuration profile in EM then those profiles will be applied to the
 device. See Assign Configuration Profile(s) to User Devices and Assign Configuration Profiles to a
 User Group for more details.
- If no profiles are defined for the user then the default Android profile(s) will be applied to the device. See Manage Default Profiles for more details.

The device can now be remotely managed from the EM console.

4.1.2.2. Enroll iOS Devices

- After you have completed the setup process, Endpoint Manager will send an email to your users containing device enrollment instructions.
- Users should open the mail on the device itself.

Note: Users must keep their iOS device switched on at all times during enrollment. Enrollment may fail if the device auto-locks or enters standby mode.

Enroll an iOS device

- Complete the steps in 4.1.2.Enroll User Devices for Management if you haven't done so already. Those
 steps will send an enrollment email to the device owners.
- Device owners should open the mail on the device itself and tap the enrollment link. This will take them to the device enrollment wizard.





Welcome to Enrollment Wizard

In order to complete the connection of your device, follow the instruction below

Installation Instruction



Step 1

Download the Profile to enroll your device. When your profile has been enrolled, you will be requested to install Communication Client application.

Download MDM Profile


Step 2

Upon completion of the installation, there will be a green icon labeled "Run after installation" shown just like a new application. Tap the green icon and follow on-screen instructions to complete enrollment process.


• Click 'Download MDM Profile' in 'Step 1':

A confirmation is shown:






• Click 'Allow'. The 'Install Profile' wizard starts:




Tap 'Install'...






· ...then 'Install' again.

The profile and certificate installation processes will start:




When that has finished, read the privacy information then click 'Install' to continue:






• Click 'Trust' at the remote management screen to continue installation:








- Tap 'Done' to finish profile installation.
- After installing the profile, the communication client installation process will begin. The client is essential to connect the device to Endpoint Manager:




- The app is downloaded from the Apple store using the user's account.
- After installation, tap the green 'Run After Install' icon on the home screen:




Tip: You can resend the 'Run after install' shortcut, if the user misses to tap that after the agent installation and accidentally removes it. See **Send Enrollment Link to iOS Devices** for help to do this.

• Next, select 'Open' to begin the installation process:





• The client requires access to device location to continue the setup process:



- Tap 'Always Allow'.
- Read and accept the EULA:





END USER LICENSE AGREEMENT AND TERMS OF SERVICE

COMODO ENDPOINT MANAGER

THIS AGREEMENT CONTAINS A BINDING ARBITRATION CLAUSE.

IMPORTANT - PLEASE READ THESE TERMS CAREFULLY BEFORE USING THE COMODO ENDPOINT MANAGER SOFTWARE (THE "PRODUCT"). THE PRODUCT MEANS ALL OF THE ELECTRONIC FILES PROVIDED BY DOWNLOAD WITH THIS AGREEMENT. BY USING THE PRODUCT, OR BY CLICKING ON "I ACCEPT" BELOW, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, THAT YOU UNDERSTAND IT, AND THAT YOU AGREE TO BE BOUND BY ITS TERMS. IF YOU DO NOT AGREE TO THE TERMS HEREIN, DO NOT USE THE SOFTWARE, SUBSCRIBE TO OR USE THE SERVICES, OR CLICK ON "I ACCEPT".


Product Functionality

Comodo Endpoint Manager (EM) allows administrators to manage, monitor and secure mobile devices which connect to enterprise wireless networks. Once a device has been enrolled, administrators can remotely apply configuration profiles which determine that device's network access rights, security settings and general preferences. EM also allows administrators to monitor the location of the

Accept Decline

• The device will be successfully enrolled to Endpoint Manager once the client is installed:





App Catalog - View installed apps, required apps and available apps.

An Endpoint Manager security profile will be applied to the device as follows:

- If a custom profile is assigned to the user in EM then those profiles are applied to the device. See **Assign Configuration Profiles to User Devices** and **Assign Configuration Profiles to a User Group** for more.
- If no profiles are defined for the user then all 'default' iOS profiles are applied to the device. See **Manage Default Profiles** for more on this.

The device can now be remotely managed from the EM console.

4.1.2.3. Enroll Windows Endpoints

- After you have completed the setup process, Endpoint Manager will send an email to your users containing device enrollment instructions.
- Users should open the email on the Windows endpoint you want to enroll. After installation, the communication client will automatically connect to the EM server.

Enroll a Windows device

Open the email on the device you want to enroll.



EM

Endpoint Manager

Welcome to Endpoint Manager!

You are receiving this mail because your administrator wishes to enroll your smartphone, tablet, macOS, Linux or Windows device into the Endpoint Manager system. Doing so will make it easier and more secure to connect your personal devices to company networks. This mail explains how you can complete the enrollment process in a few short steps.

Note

Make sure you select the procedure appropriate for your device type i.e. macOS, Windows, Linux, iOS or Android and complete the necessary steps from the phone, tablet or desktop machine.
 This product allows the system administrator to collect device and application data, add/remove accounts and restrictions, list, install and manage apps, and remotely erase data on your device.


Device Enrollment:

Click this link to annual your device

Sincerely, Endpoint Manager team

- Click the enrollment link in the email to open the device enrollment page
- The device enrollment wizard starts.
- Click the 'Download Windows Installer' button:





The EM client setup file gets downloaded.

Double-click on the file to install the communication client.

The device automatically gets added to Endpoint Manager once installation is complete. The EM communication client icon papears at the bottom-right of the endpoint screen.

- If the client is not automatically enrolled after installation, you can manually enroll the device at a later time. This might happen, for example, if there are connectivity issues.
- You will need to enter the host, port and token ID to manually enroll. You can find these items at the end of the device enrollment page.



complete

Manual Enrollment Credentials

These credentials can be used for manual device enrollment via Endpoint Manager portal or via Communication Client

Host

Server Url

herculespopular-herculespopular-msp.cmdm.comodo.com

Port

Server Port

443


Token

29014e9f995b3d8762126bb53cf99dcd


Manually enroll your device

· Right-click on the communication client tray icon and select 'Activation'





- Enter the host, port number and token in the respective fields. You can find these items in the device enrollment page.
- The client communicates with the EM server and enrolls the device.



After device enrollment, the next step is to install Comodo Client Security (CCS) onto the endpoint. See **Remotely Install and Update Packages on Windows Devices** for help with this.

A security profile will be applied to the device when CCS is installed. Profile deployment is as follows:

- If the user is already associated with a configuration profile in EM then those profiles will be applied to the device. See Assign Configuration Profiles to User Devices and Assign Configuration Profiles to a User Group for more details.
- If no profiles are defined for the user then the default Windows profile(s) will be applied to the device. See Manage Default Profiles for more details.

The device can now be remotely managed from the EM console.

Endpoint Manager allows you to rebrand the communication client (CC) and CCS applications to change the appearance and interface texts in their GUI. This is especially useful for customers who wish to white-label the CC/CCS interfaces for their clients.

- The 'UI Settings' component of a configuration profile applied to the device can be configured to:
 - Show your company name, support website, phone number and email.
 - Display your company logo, header logo, product icons and product logo in various interfaces of the applications.
 - See CC and CCS Application UI Settings under Create Windows Profiles for more details.

4.1.2.4. Enroll Mac OS Endpoints

You can enroll MAC devices either with or without installing the Endpoint Manager profile.

- Apple only allows one portal to use the protocol which manages devices. This causes issues with customers who want to use Endpoint Manager in conjunction with another management platform.
- 'Profile-less' enrollment lets you use Endpoint Manager to manage security while using another platform for general Mac management.
- However, you cannot manage the following items if you choose 'profile-less' enrollment:
 - Certificates

ITarian Endpoint Manager - Administrator Guide




- Restrictions
- VPN
- Wi-F
- You can configure whether or not EM profile is to be installed along with the communication client while enrolling user's device.
 - See the **settings for Mac OS devices** in the section **Enroll User Devices for Management** for help with this.

Enroll a Mac OS device

- Open the email on the device you want to enroll.
- Click the enrollment link in the email.
- The device enrollment wizard starts.
- Click the 'Download mac OS Installer' button:







The EM client setup package file gets downloaded.

Open the file to install the communication client.






Click 'Continue' and follow the installation wizard





• If you have configured the package to install the EM profile, the device profiles screen appears when installation is complete:



The device automatically gets added to Endpoint Manager. The EM communication client icon appears at the top-right of the endpoint screen.

If Comodo Client Security (CCS) is included in the **setup process**, then it is installed automatically. Else you can install CCS manually after device enrollment is complete. See **Remotely Install Packages on Mac OS Devices** for help to do this.

- Endpoint Manager will apply any user-specific profiles to the device. See Assign Configuration Profiles to
 User Devices and Assign Configuration Profiles to a User Group for more details.

4.1.2.5. Enroll Linux OS Endpoints

- After you complete the setup process described in 4.1.2, Endpoint Manager will send an email to your users containing device enrollment instructions.
- The email contains instructions on how to install the EM communication client on their device.
 - Users should open the email and complete the installation on the actual endpoint you want to enroll.
- After installing the communication client, the endpoint will automatically connect to the EM server.

Supported distributions


- Ubuntu 18
- Ubuntu 16.04.2
- Cent OS 7
- Debian 8.8



Red Hat Enterprise 7

Enroll a Linux device

- Open the mail on the target device and click the enrollment link. This will start the setup wizard.
- Click the 'Download Linux Installer' button and save the file:



You can install the communication client on the Linux device by completing the following:

- 1. Change installer mode to executable enter the following command:
 - \$ chmod +x {\$installation file\$}
- 2. Run installer with root privileges enter the following command:
 - \$ sudo ./{\$installation file\$}

For example:

chmod +x itsm_cTjlw6gG_installer.run sudo./itsm_cTjlw6gG_installer.run



```
© c1@c1-VirtualBox: ~/Downloads
c1@c1-VirtualBox:~$ ls
Desktop
           Downloads
                                km-0409.ini
                                              Pictures
                                                         Templates
Documents examples.desktop Music
                                              Public
                                                          Videos
c1@c1-VirtualBox:~$ cd Downloads/
c1@c1-VirtualBox:~/Downloads$ ls
itsm_cTjIw6gG_installer.run
c1@c1-VirtualBox:~/Downloads$ chmod +x itsm_cTjIw6gG_installer.run
c1@c1-VirtualBox:~/Downloads$ sudo ./itsm_cTjIw6gG_installer.run
[sudo] password for c1:
Verifying archive integrity... All good.
Uncompressing Linux ITSM Agent 100%
systemd system
cTjIw6gG
Created symlink from /etc/systemd/system/multi-user.target.wants/itsm.service to
/etc/systemd/system/itsm.service.
Your device is now enrolled!
Service started
c1@c1-VirtualBox:~/Downloads$
```

- After installation, the communication client will connect to the Endpoint Manager and enroll the device.
- If Comodo Client Security (CCS) is included in the **setup process**, then it is installed automatically. Else you can install CCS manually after device enrollment is complete. See **Remotely Install Packages on Linux Devices** for more details.
- After installing CCS, any EM configuration profiles associated with the user will be applied to the device.
 See Assign Configuration Profile(s) to a Users' Devices and Assign Configuration Profiles to a User Group for more details.
- If no profiles are defined for the user then the default profiles for Linux are applied. See Manage Default
 Profiles for more details.

The device can now be remotely managed from the EM console.

4.1.3. View User Details

Click 'Users' > 'User List'


The 'User List' interface lets you view and edit user account details at anytime.

View user details

- Click 'Users' > 'User List'
- Click the name of a user

The user details screen opens:





- Click the 'Edit' button if you want to modify the user's details. See **Update the Details of a User** if you want more help with these settings.
- This area only lets you edit users who were added directly to Endpoint Manager. You cannot edit users that were added via the ITarian portal.

The user details screen also lets you:

- · Add new devices for a user
- Apply configuration profiles to devices
- Send password recovery emails for users to access the EM console
- Generate new password for a user
- · Reset two-factor authentication token for a user
- View and manage user devices
- View device enrollment tokens generated for users
- · View and manage groups to which a user is a member
- Run procedure on user devices

Add new devices for users

- Click 'Users' > 'User List'
- Click the name of a user



Click 'Enroll Device' at the top of the details interface

The 'Enroll Devices' dialog will open with the user pre-populated. See **Enroll User Devices for Management** if you need help to complete this process.

Apply Configuration Profiles to user devices

- Click 'Users' > 'User List'
- Click the name of a user
- Click the 'Manage Profiles' button

This will open a list of profiles added to the user's devices. You can add new profiles which will be applied to their devices. See **Assign Configuration Profiles to a User Devices** for more details.

Send a password recovery email to users

- Click 'Users' > 'User List'
- Click the name of a user
- Click the 'Send Password Recovery Email' button to start the process.
 - Note you can only send password emails to users added to Endpoint Manager. This option is not available for users added via the ITarian management portal.

The email contains a link which lets the user reset their password:



Endpoint Manager

Dear Dyanora,

We recently received a password reset request for your Endpoint Manager account.

Date of request: Thu, 25 Oct 2018 05:00:44 +0000

If you requested this change, please confirm and complete the reset process by clicking the following link (available only once): https://frontfork-msp.dmdemo.comodo.com/user/site/change-password/username/Dyanora/key/1b11dea0b03b12b26e6bd81266a604
9ac44d464b

If you did not request this change, please contact us immediately by sending an email to support@itarian.com

Sincerely, Endpoint Manager team.

Tip: Alternatively, you can send the password reset mail from the 'User List' interface. Select the user from the list and click 'Send password Recovery Email' at the top.

Generate password for a user

Click 'Users' > 'User List'



- Click the name of a user
- Click 'Change Password' at the top of the details interface

The change password dialog opens. You can generate a new password for the user. The process is explained in more detail in 'Generate New Password for a User' section.

Reset two-factor authentication token for a user


- Click 'Users' > 'User List'
- Click the name of a user
- Click 'Reset 2FA Token' above

This will start the reset procedure. See 'Reset Two Factor Authentication Token for a User for more details.

View devices associated with a user

- Click 'Users' > 'User List'
- · Click the name of a user
- Click the 'Associated Devices' link

This tab shows all devices enrolled for the user:



Associated Devices - Column Descriptions		
Column Header	Description	
OS	The operating system of the device.	
Name	The label of the device as assigned by the user.	
	 If no name is assigned, the model number of the device will be used as the name of the device. 	
	Click the name of the device to open the 'Summary' screen of the Device Details interface.	




	See 'View Summary Information' for more details.
Active Components	The endpoint security components running on the device. For example, Antivirus, Firewall, Containment etc.
Patch Status	How many OS patches and updates are ready for installation on the endpoint. Patch status is only available for Windows endpoints.
	 Click the number to open the 'Patch Management' tab of the 'Device Details' interface. It allows you to initiate installation of the missing patches.
	 See View and Manage Patches for Windows and 3rd Party Applications for more details.
Company	The customer organization to which the device was registered.
Last Activity	The date and time at which the device last communicated with the EM server.

View User Tokens

Endpoint Manager generates a unique token for each user when you enroll a device for them. This token is used by the communication client on the device to authenticate the enrollment request to Endpoint Manager. A single token can be used to enroll any number of devices for the same user. A token is valid for 90 days.

The 'User Tokens' interface displays a list of generated user tokens. You can use these tokens to manually enroll device for specific users

- Click 'Users' > 'User List'
- Click the name of a user
- Click the 'User Tokens' link




User Tokens - Column Descriptions	
Column Heading	Description



Token	The unique serial number of each enrollment token.
Expiration Date	Date till which the token is valid. Users can enroll devices using the same token until expiry.
Days left	How many days remain until the token expires.

To view and manage user groups to which the user belongs

- Click 'Users' > 'User List'
- · Click the name of a user
- Click the 'Groups' tab to view all groups to which the user belongs:



Groups - Column Descriptions		
Column Header	Description	
Group Name	The label of the user group Click the group name to open the 'Group Details' interface. See Edit a User Group for more details.	
Number of Users	The total count of users in the group.	
Created By	The administrator who added the group. • Click the name to open the 'User Details' interface of the administrator.	
Created	The date and time at which the group was created.	



4.1.3.1. Update the Details of a User

- Click 'Users' > 'User List'
- · Click the name of a user
- Click the 'Edit' button

The 'User Details' pane lets you update the username, email address and phone number of a user. You can also view devices associated with the user and send them a password recovery email.

Note: The 'Edit' option is only available for users added in the Endpoint Manager interface. It is not available for users that were added via the ITarian portals. Those users must be edited in the ITarian portal. All changes will be reflected in the EM interface.


To update the details of a user

- Click 'Users' > 'User List'
- Click on the user whose details you want to update.

The user details screen will open.

Click the 'User Info' tab and then the 'Edit' button





- Update the username, email address of the user and the phone number as required.
- Click 'Save' at the top for your changes to take effect

The role assigned to the user is displayed under 'Roles'.

- Click the role name to change the role if required.
- See 'Manage Roles Assigned to a User' for more details.


4.1.4. Assign Configuration Profiles to User Devices

- Click 'Users' > 'User List'
- Profiles assigned to a user will apply to all devices owned by the user.
- You can apply multiple profiles for different operating systems to a user. Endpoint Manager will apply the appropriate profile to a device depending on its OS.



Manage configuration profiles assigned to a user

- Click 'Users' > 'User List'
- Select the user for whom you want to assign/remove profile(s)
- Click 'Manage Profiles'




The list shows all profiles assigned to a user. You can add, remove or edit profiles as required.

Tip: Alternatively, click 'Users' > 'User List' > click on a username > 'Manage Profiles'.

To add a new profile to a user


- Click 'Users' > 'User List'
- Select the target user
- · Click 'Manage Profiles'
- Click 'Add Profiles':





- The next screen shows all profiles that you can add to the user. The list excludes profiles which are already assigned to the user.
- Select the profiles you want to add and click 'Save'
 - Click the funnel icon on the right if you want to search for a particular profile

The new profiles will be automatically deployed to the user's devices.




To remove a profile

- Click 'Users' > 'User List'
- Select the target user
- Click 'Manage Profiles'



Select the profiles you want to disassociate and click 'Remove Profiles'



The selected profiles will be immediately removed from devices belonging to the user. See note below:

Note: There are 4 ways you can assign a profile to a device:

- 1. Assign the profile the device owner, aka the 'user'.
 - Click 'Users' > 'User List' > click a username > 'Manage Profiles' > 'Add Profiles'
- 2. Assign the profile to the device itself.
 - Click 'Devices' > 'Device List' > click a device name > 'Manage Profiles' > 'Add Profiles'
- 3. Assign a profile to a device group. Make the device a member of the group.
 - Click 'Devices' > 'Device List' > 'Group Management' tab > click a group name > 'Manage Profiles'
- 4. Assign a profile to a user group. Make the user (device owner) a member of the group
- Click 'Users' > 'User Groups' > click a group name > 'Manage Profiles' / 'Associated Devices'
 Removing a profile as described in this section will only remove profiles which arrived on the device via method # 1 above

The profile may remain on the device if it was (also) deployed via methods 2, 3 or 4 above.


4.1.5. Remove a User

You can remove users if they no longer have devices which need to be managed by Endpoint Manager.

• Click 'Users' > 'User List'



Select the target user and click 'Delete User':



- Alternatively, click on the name of the user
- Click 'Delete User' in the 'User Details' screen.
- · Click 'Confirm' in the confirmation dialog




Note 1: Users added via the ITarian portal cannot be removed via the EM interface. They can only be removed at the portal through which they were added. Once removed they are automatically deleted from EM.

Note 2: Users cannot be removed if they still have devices. Ensure all devices associated with a user are removed or reassigned to another user. See **Remove a Device** and **Change Device's Owner** for more details.

4.1.6. Generate New Password for a User

- Click 'Users' > 'User List' > select a user > click 'Change Password'
- This area lets you manually set a new password for a user, instead of letting them reset their own password.






Note - This interface only applies to users that were created in Endpoint Manager itself. It does not change the passwords of users who were created in the ITarian portal.

There are two possible ways to change user passwords:

- Send a password recovery email Let the user reset their own password. Click here for more details.
- Generate a new password Create a new password on behalf of the user. This section explains this
 method.

Generate a new password.

- Click 'Users' > 'User List'
- Select the user and click 'Change Password'
- This opens the reset dialog:





Type a new password for the user in the box provided. Alternatively, click 'Generate New Password' to have Endpoint Manager create a random password.

Ask for a password change at the next Sign-in - After logging in with the new password you provide, users will be forced to change their password again. This improves privacy by ensuing only the user knows their own password.

Notify user about changing password on email - Will send an email to users that informs them their password has been reset.

Click 'Change'


The following confirmation is shown:

The New Password successfully saved

4.1.7. Reset Two Factor Authentication Token for a User


Click 'Users' > 'User List' > select a user > Click 'Reset 2FA token'

- This feature lets you force admins whose use two-factor authentication (2FA) to reset it at their next login.
 - Click here if you want to know how to setup 2FA in Endpoint Manager.
- Note: This action does not reset 2FA on ITarian logins. It only affects 2FA for admins who were created in Endpoint Manager itself.



- Click 'Users' > 'User List'
- Select the user and click 'Reset 2FA Token' above
 - Alternatively click the name of the user then click 'Reset 2FA Token'






· Click 'Confirm'

A success message is shown:

Two-Factor Authentication Configuration successfully reset

The admin will go through the 2FA setup process after their next login.



The tutorial to configure 2FA is explained in detail **here**.


4.1.8. Run Procedures on User Devices

Procedures are standalone instruction scripts and patches for Windows devices. There are various ways you can execute procedures on devices. This section explains how to run procedures on devices based on user name.


• See Manage Procedures to know more about creating procedures.

Click 'Users' > 'User List'





- Select the target users then click 'Run Procedure'
- Alternatively, click on a user's name then click 'Run Procedure' in their details screen.
- Next, choose the script you want to run and other options:



- Procedure Name Type the name of the procedure that you want to add in the first field (make sure you have approved the procedure)
- Run as Local System User / Run as Logged in user Choose the user account under which the
 procedure should run. This option is not available for patch procedures.
- Send the resulting logs by email Script procedures only.
 - Send to current user Procedure results are sent to the admin who is currently logged into Endpoint Manager.



- Send to the following email addresses Add email addresses to whom log results should be sent.
- Click 'Run'

Endpoint Manager runs the procedure on the users' devices.


4.2. Manage User Groups

Click 'Users' > 'User Groups'

- You can create groups of users to simplify and streamline management. For example, you can group users
 according to existing corporate units ('Sales Dept.', 'Accounts Dept.') and/or by type of user.
- Once created, you can apply specific profiles to each group as required. See Configuration Profiles for more help with profiles.
- You can also import users and user groups from Active Directory using LDAP. EM will periodically
 synchronize with AD to ensure any user updates are mirrored in the EM database. See Import User
 Groups from LDAP for more details.

The 'User Groups' interface lists all existing groups and allows you to add and edit groups. You can also assign profiles to groups from this interface.

Click 'Users' > 'User Groups' to open the groups interface.



Column Heading	Description
Name	The user group label. • Click the name of a group to view and manage its members, assign
	configuration profiles and more. See Edit a User Group for more details.
Number of Users	Shows how many users are in the group.
Created By	The administrator who created the group.
	 Click the admin name to view their details. See View User Details if you need help with this.
Created	Date and time at which the group was created.




Controls		
Create Group	Add a new user group to EM and include users into it. See Create a New User Group for more details.	
Run Procedure	Execute stand-alone instruction scripts and patches on group devices. See Run Procedures on User Groups for more help with this.	
Export	Save the list of user groups as a comma separated values (CSV) file.	
	The exported .csv is available in 'Dashboard' > 'Reports'	
	See Export the List of User Groups for more details.	

- Click any column header to sort groups in alphabetic or ascending/descending order of the entries in the column.
- Click the funnel button at the right end to open the filter options.

Export the List of User Groups

- Click 'Users' > 'User Groups'.
- Click the 'Export' button above the table then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

The 'User Groups' interface allows you to:

- Create a New User Group
- Edit a User Group
- Assign Configuration Profile(s) to a User Groups
- Remove a User Group
- Run Procedures on Group Devices



4.2.1. Create a New User Group


Click 'Users' > 'User Groups'

The 'User Groups' interface lets you add and populate new user groups. Configuration profiles applied to the group will then be pushed to all devices owned by users in the group.

Create a new user group

- Click 'Users' > 'User Groups'
- Click 'Create Group' above the table.


The 'Create User Group' dialog will open:



- Name Type a label for the user group.
- Choose User(s) Add users to the group.
 - Start typing the first few letters of a username and select from the suggestions.
 - Repeat the process to add more users.
 - Note: You can skip this step and add users later if required. See Edit a User Group for more details.
- The group will be saved and the group details screen will open.
- Profiles can now be applied to the group. See Assign Configuration Policy to a User Group for more details.
- Users can be added or removed from the group at anytime. See Edit a User Group for more details.

ITarian Endpoint Manager - Administrator Guide






Note: A single user can be a member of more than one group. Profiles from every group of which the user is a member will be applied to the user's device. If the settings in one profile clash with another profile, EM will implement the most restrictive setting. For example, if one profile allows the use of the camera but another profile blocks it, then the device will not be able to use the camera.

4.2.2. Edit a User Group

- The group details screen lets you manage group members, rename the group, or delete the group.
- Click 'Users' > 'User Groups'.
- Click the name of the group you want to edit:






The group details screen allows you to:

- Add new users to the group
- Rename the group
- Assign Configuration profiles to the group
- · Remove the group

Add new users to the group

- · Click 'Add Users To Group'.
- · Select the users you want to add then click 'Save'.
- All group profiles will be applied to the new user's devices. These profiles will be removed from the device if you remove the user from the group.






Rename a group

- Click 'Users' > 'User Groups'.
- Click the name of the group you want to re-name.
- · Click the 'Rename User Group' button
- Enter the new label in the 'Name' text box and click 'Save':





4.2.3. Assign Configuration Profiles to a User Group

Click 'Users' > 'User Groups' > click on the name of a group

- The group details pane lets you manage the profiles currently applied to the group.
- Any profile changes are instantly applied to the devices of group members. Endpoint Manager detects the
 device operating system and only installs the profiles appropriate for that OS.

For more details on profiles, See Create Configuration Profiles.


View and manage group profiles

- Click 'Users' > 'User Groups'.
- Click on the name of the group whose profiles you wish to manage.

The group details interface opens with a list of all users in the group.

Click 'Manage Profiles' at the top:






The profiles screen lists all profiles assigned to the group.

Add a profile

- Click 'Users' > 'User Groups'.
- Click on the name of the group whose profiles you wish to manage.
- Click 'Manage Profiles' at the top of the group details screen
- · Click the 'Add Profiles' button
- This open a list of all available profiles, excluding those that are already applied to the group:






• Select the profiles you want to add to the group then click 'Save'.

Remove a profile from a group

- Click 'Users' > 'User Groups'.
- Click on the name of the group whose profiles you wish to manage.
- Click 'Manage Profiles' at the top of the group details screen
- Select the profile you want to remove then click 'Remove Profiles'





The profiles will be removed from all devices belonging to group members.

Note - A profile you removed from the group might remain on a device if it was also applied through some other source. For example, you can apply profiles to devices directly at 'Devices' > 'Device List' > click on a device name > 'Manage Profiles' > 'Add Profiles'.

4.2.4. Remove a User Group

• Click 'Users' > 'User Groups'

The 'User Groups' interface lets you remove unwanted groups.

Note: You can only remove groups that have no users in them. Please empty the group of users before attempting to remove it. See **Edit a User Group** if you need help to do this.


Remove a user group

- Click 'Users' > 'User Groups'
- Click the name of the group to be removed.

The group details interface will be displayed with the list of users in the group.

Click 'Delete User Group' at the top.






• Click 'Confirm' in the confirmation dialog. The user group will be removed from Endpoint Manager.


4.2.5. Run Procedures on Group Devices

Procedures are standalone instruction scripts and patches for Windows devices. This section explains how to run procedures on all devices which belong to users in a user group. See **procedures** if you want to learn more about procedures in general.

- Click 'Users' > 'User Groups'
- Select the target groups then click 'Run Procedure':







- Procedure Name Type the name of the procedure that you want to add in the first field (make sure you have approved the procedure)
- Run as Local System User / Run as Logged in user Choose the user account under which the
 procedure should run. This option is not available for patch procedures.
- Send the resulting logs by email Script procedures only.
 - Send to current user Procedure results are sent to the admin who is currently logged into Endpoint Manager.
 - Send to the following email addresses Add email addresses to whom log results should be sent.
- Click 'Run'

The procedure command is sent to the devices belonging to the users in the user groups.



4.3. Configure Role Based Access Control for Users


- Click 'Users' > 'Role Management'
- User privileges depend on the roles assigned to them. Admins can create roles with different access privileges and assign them to users as required. A single user can be assigned to any number of roles.
- Staff created in ITarain can be added to any role for any company. This allows you to assign different roles to the same staff member for different companies.
- You can restrict a role to specific companies/groups. Staff can only manage the devices of companies/groups allowed by their role.
- You can also create roles with read-only privileges. These allow staff to view assigned interfaces but not make changes.

The role management area has two tabs:

- Roles View and edit each role's permissions. You can also create custom roles here.
- Users View users and assign them to roles

Roles

- The 'Roles' interface allows you to create and manage user roles.
- Each role defines a staff member's rights to access EM modules and to manage users/devices belonging to different companies. You can restrict a role to manage specific companies and specific device groups.
- Endpoint Manager ships with four roles, 'Account Admin', 'Administrators', 'Technician' and 'Users'.
- The 'Account Admin' role can be viewed but not edited. The permissions in the other three roles can be modified. You can also create custom roles according to your requirements.



- Custom roles and built-in roles are available for selection when adding a new user.
- Admins can add or remove roles at any time. You can also change the role of any user at any time.
- New users are assigned the 'User' role by default. However, you have the option to make any role the
 default.

Roles - Column Descriptions		
Column Heading	Description	
Name	Role label. Click a role name to open the 'Role Management' > 'Role Permissions' screen. You can view and manage permissions assigned to the role.	



	See 'Manage Permissions and Assign Users of a Role' for more details.	
Description	A short description of the role.	
Number of Users	Shows how many users are assigned to the role.	
	 Click the number to open the 'Assign Users' screen, which lets you manage users assigned to the role. See 'View users assigned to a role' for more details. 	
Controls		
Add Role	Create new roles and assign them to users. See Create a New Role for more details.	
	ordate new roles and assign them to users. See Greate a new Role for more details.	
Export	Save the list of user roles as a comma separated values (CSV) file.	
Export		

- Click a column header to sort the table according to the items in the column.
- Click the funnel on the right to implement more filters.

The roles interface allows you to:

- Create a new role
- Manage Roles
 - Edit a role name and description of a role
 - Manage the permissions assigned to a role
 - Manage the users assigned with a role
- Remove a Role

Export the List of Roles

- Click 'Users' > 'Role Management'.
- Select the 'Roles' tab
- Click the 'Export' button above the table then choose 'Export to CSV':




- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Users

- The 'Users' interface lets you view users added to EM and the roles assigned to them.
- You can also edit the roles assigned to each user from this interface.



• Click the 'Users' tab to switch to the 'Users' interface:




Users - Column Descriptions			
Column Heading	Description		
Name	The login username of the user.		
	 Click a username to view and manage roles assigned to the user. See Manage Roles assigned to a User for more details. 		
Email	The registered email address of the user.		
Roles	The user roles assigned to the user.		
	Click a role name to view and manage permissions assigned to the role. See 'Manage Permissions and Assigned Users to a Role' for more details.		
	Controls		
Reset to Default Role	Revert the user's role to the ITarian system default role.		
	Applies only to users imported from ITarian console. It doesn't apply to users added via EM.		
	See Restore user role in Manage Roles Assigned to a User for more.		
Export	Save the list of users as a comma separated values (CSV) file.		
	The exported .csv is available in 'Dashboard' > 'Reports'.		
	See Export the List of Users for more details.		

- Click a column header to sort the table according to the items in the column.
- Click the funnel on the right to implement more filters.



Export the List of Users

- Click 'Users' > 'Role Management'.
- · Select the 'Users' tab
- Click the 'Export' button above the table then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.


The 'Users' interface allows administrators to:

Manage Roles Assigned to a User

4.3.1. Create a New Role

- Click 'Users' > 'Role Management'
- Click the 'Roles' tab
- Click 'Add Role':






Create a name and description for the role then click 'Ok'.

The new role is added to the list in the 'Roles' screen.

 Click on the new role to edit its permissions, assign users, and specify which entities the role is allowed to manage.






The edit screen has three tabs:

- Role Permissions Define access rights and privileges for the role
- Assign Users Select users who should have the role.
- Access Scope Select which companies and groups can be accessed by role members.

Select access rights and privileges for the role

Click the 'Role Permissions' tab if it is not open








- Read Only Portal Role-members can view areas to which you assign them permission, but cannot make changes.
 - The read-only switch applies to *every* permission you enable in the list below.
- **Users.allow-portal-login** Role-members can login to Endpoint Manager (EM). EM sends an account activation mail to users assigned to the role. The user can login to EM and manage as per the permissions you assign below.

Each item in the list lets you choose permissions for a specific area.

- Click the down arrow next to a module name to view its permissions
 OR
- Click 'Expand' at the top to view all permissions




- Use the switches on the right to enable or disable specific permissions
- · Use the 'Apply to all' switch to enable or disable all permissions
- Click 'Save' for your settings to take effect

Assign the new role to selected users

Click the 'Assign Users' tab.

This opens a list of all enrolled users:





• Assign to Role - Click to place the user in a particular role.


Tip: You can search for specific users by clicking the funnel icon at top-right.

Select which companies and device groups can be accessed by the role

Click the 'Access Scope' tab.

This opens a list of all companies added to Endpoint Manager. **Device groups** in each company are listed below the company name.






Configure the access scope of the role as follows:

- Use the green 'master' switch next to a company name to enable/disable the ability to manage groups under the company.
- Use the switch next to a device group to control access to a specific group.
- Apply to All Enable or disable access to all companies and groups on the page.
- · Click 'Save' for your settings to take effect
- Click the edit button Edit to modify the role's name and description. Please note that you cannot modify the built-in roles, Account Admin, Administrators and Technician.
- Click 'Make Default' if you want this to be the role that is initially assigned to new users.

4.3.2. Manage Permissions and Users Assigned to a Role

- Click 'Users' > 'Role Management' on the left.
- · Click the 'Roles' tab.
- Click a role name to view its details





The role management area lets you:


- Edit the name and description of a role
- Add or remove permissions assigned to a role
- Manage the permissions assigned to a role
- View users assigned to a role
- Assign / remove a role to / from users



- Select companies and device groups accessible to a role
- Set a role as the default role

Edit the name and description of the role

Click the 'Edit' button Edit at the top




- · Modify the name and / or description as required
- Click 'Ok' for your changes to take effect.

Add or remove permissions assigned to a role

- · Click the name of the role to open the 'Role Details' interface
- · Click the 'Role Permissions' tab if it is not open






Adding or removing the permissions is similar to assigning permissions while creating a role. See the
 explanation of assigning permissions in the previous section Create a New Role for help on this.

View users assigned to a role

- · Click the name of the role to open the 'Role Details' interface
- Click the 'Assign Users' tab





The links in the 'Action' column indicate which users are assigned the role.

- Click the 'Assign to Role' links to place a user in the role.
- Click the 'Remove from Role' link to unassign a user from the role.


Tip: You can search for specific user(s) by clicking the funnel icon at the top right.

• Click a username to open a list of all roles assigned to that user. You can to add or remove roles from the user as required. See Manage Roles assigned to a User for more details.

Select which companies and device groups can be accessed by the role

- Click the name of the role to open the 'Role Details' interface
- Click the 'Access Scope' tab





- Use the green 'master' switch beside a company name to enable or disable the ability to manage groups belonging to the company. Please note you should have provided appropriate devices **role permission**.
- Use the switch beside a device group to enable or disable access to the specific group within a company.
- Use the 'Apply to All' switch to enable or disable access to all companies and groups on the page.
- · Click 'Save' for your settings to take effect


Set a role as the default role

- The default role is automatically applied to any new user unless the admin specifies a different role when adding the user
- The default role is automatically applied to users if their current role is removed


Set the default role:

- Click 'Users' > 'Role Management' > 'Roles'
- Click the name of the role you wish to make default.
- Click 'Make Default' under the name of the role:





The role is set as default. This is indicated as follows:



4.3.3. Remove a Role


Administrators can delete roles that are no longer deemed necessary.

- You cannot remove roles that are currently assigned to users. You need to remove all users from any role you want to delete.
- The current 'Default' role cannot be deleted. You should make another role the default first.
- The built-in roles ('Account Admin', 'Administrators' and 'Technicians') cannot be removed either.

To remove a role



- Click 'Users' on the left and select 'Role Management'.
- Click the 'Roles' tab.
- Click the 'Role' name to open the 'Role Management' interface
- · Click 'Delete Role' at the top



· Click 'Confirm' to remove the role.


4.3.4. Manage Roles Assigned to a User

- The 'Users' tab lets you view the roles assigned to each user. A role governs a users permissions and access rights within Endpoint Manager.
- You can add new roles to a user, or remove roles from a user.
 - Note you cannot assign or remove the 'Account Admin' role. This is automatically assigned to the
 person that created the ITarian account.
- ITarian customers All staff created in ITarian will be available for selection in all roles, and for all
 companies. This lets you assign different roles to the same staff member for different companies.
- You can specify which companies a role can access in the role's 'Access scope':
 - Click 'Users' > 'Role Management'
 - · Click the 'Roles' tab
 - Click on a role name to open its details page
 - Open the 'Access Scope' tab
 - Enable or disable access to specific companies as required.

View the list of users with roles assigned to them



- Click 'Users' > 'Role Management'.
- Select the 'Users' tab.




The 'Users' interface lets you to:

- Add or remove roles assigned to a user
- Revert a user's role to the ITarian system default role

Manage roles assigned to a user

- Click on the name of a user whose roles you want to manage.
- The interface will show all roles you can assign to the user.
- · Click 'Assign to Role' to delegate a new role to the user .
- Click 'Remove from Role' to withdraw membership of a role from a user.






Reset the roles to ITarian default


The following only applies to users added via the ITarian portal. It does not apply to users added via the Endpoint Manager interface.

- Click 'Users' > 'Role Management'.
- · Click the 'Users' tab.



 Select the user and click 'Reset to Default Role'. Use the filter option at top-right if you need to search for users.






Click 'Confirm' to restore the user with ITarian default role.

5. Devices and Device Groups

The 'Devices' area allows you to:

- View, manage, and take actions on enrolled devices and device groups.
- Download the packages required for endpoint enrollment (including via Active Directory).
- Download the Remote Control tool, which allows staff to access Windows and Mac endpoints



The area is split into two sections - 'Device Management' and 'Group Management'. A list of companies and company groups are shown in the middle column.

• **Device Management** - Shows all devices added to Endpoint Manager. Use the links in the middle column to view devices which belong to a specific company or group.

This area lets you add and manage devices, manage device profiles, install CCS, take remote control of Windows and Mac OS devices, remotely lock devices and more. See 'Manage Devices' for more details.

Note: See Enroll User Devices if you need help add new devices.



- **Group Management** Create new device groups, view and manage membership of existing groups, apply profiles to groups and more. You can choose the group you want to manage from the list in the middle column. See 'Manage Device Groups' for more details.
- **Bulk Installation Package** Download the communication client packages required to manually enroll devices from Active Directory. You can also download the Remote Control tool which allows you to interact with remote Windows and Mac OS endpoints. See **Bulk Enrollment of Devices** for more details.

Note: Mobile devices – You need to install an APN certificate (iOS) and/or Google GCM token (Android) before you can enroll mobile devices. See **step 2** of the quick start guide if you have not yet installed an APN certificate and/or GCM token.

Process in short:

- Step 1 Enroll users (if you haven't done so already)
- Step 2 Enroll devices (if you haven't done so already). Note you also can use bulk enrollment to import Windows and MAC devices en masse.
- Step 3 Create Device Groups.
- Step 4 Import Devices into Groups.
- Step 5 Apply Configuration Profiles to Groups.
- Step 6 View Details of and Manage Individual Devices.

Please use the following links to find out more:

- Manage Device Groups
 - Create Device Groups
 - Edit Device Groups
 - Assign Configuration Profile to Groups
 - Remove a Device Group
- Manage Devices
 - Add New Devices
 - Manage Windows Devices
 - Manage Mac OS Devices
 - Manage Linux Devices
 - Manage Android Devices
 - Manage iOS Devices
 - View User Information
 - Remove a Device
 - Remote Management of Windows and Mac OS Devices
 - Remotely Manage Folders and Files on Windows Devices
 - Manage Processes on Remote Windows Devices
 - Manage Services on Remote Windows Devices
 - Use Command Prompts on Windows Devices
 - Apply Procedures to Windows Devices
 - Remotely Install and Manage Packages on Windows Devices
 - Remotely Install Packages on Mac OS Devices
 - Remotely Install Packages on Linux Devices
 - Send Enrollment Link to iOS Devices
 - Install Apps on Android / iOS Devices



- Generate an Alarm on Android Devices
- Remotely Lock Mobile and Mac OS Devices
- Wipe Selected Mobile and Mac Devices
- Assign Configuration Profile to Devices
- Set / Reset Screen Lock Password for Mobile Devices
- Update Device Information
- Send Text Messages to Mobile Devices
- Restart Selected Windows Devices
- Change a Device's Owner
- Change Device Ownership Status
- Generate Device List Report
- Bulk Enrollment of Devices
 - Enroll Windows and Mac OS Devices by Installing the EM Communication Client Package
 - Enroll the Android and iOS Devices of Active Directory Users
 - Download and Install the Remote Control Tool

5.1. Manage Device Groups


Click 'Devices' > 'Device List > 'Group Management'

- Device groups make it easy to manage large numbers of Android, iOS, Mac, Windows or Linux devices.
- The group management area lets you view and create groups, import devices into groups, assign profiles to groups, and more.
- The ability to create device groups depends on your product/account type. See the table below for details:

ITarian MSP account	Can create device groups for every customer on their account. All customers and groups are listed to the left of the main pane.
ITarian Enterprise account	Can only create groups under the 'Default Customer'.
Endpoint Manager stand-alone account	Can only create groups under the 'Default Customer'.

 After opening the device list, click a customer or group name in the middle column to view devices belonging to that entity:





View and manage device groups

- Click 'Devices' > 'Device List'
- Click the 'Group Management' tab
 - Click a customer name to view groups under that customer Or
 - Select 'Show All' to view every device group added to EM

Device Groups - Column Descriptions		
Column Heading	Description	
Name	The label of the device group. Click a group name to view all devices in that group. You can add or remove group devices, manage group profiles, export the	
Number of Devices	device list to .csv, and more. See Edit a Device Group for more details. How many devices are in the group.	
Created By	The admin who created the group. • Click the name to view the admin's details. See View User Information if you need more explanation of the details window	
Created	The date and time at which the group was created.	

- · Click any column header to sort items in alphabetical or numerical order
- Click the funnel icon to configure filters
- Use the search box to find a specific group
- · Click the number below to navigate to different pages, or click previous / next
- Select how many records to view from the results per-page drop-down

Group profiles

You can apply configuration profiles with specific settings to any device group. If a device belongs to multiple groups, then all group profiles are applied to the device. If the settings in one profile clash with those of another then EM



applies the more restrictive of the two settings. For example, if one profile allows the use of the camera and another blocks it, then the device cannot use the camera.

See **Configuration Templates** if you want to learn more about profiles.

See the following sections for help with device groups:


- Create Device Groups
- Edit a Device Group
- Assign Configuration Profiles to a Device Group
- Remove a Device Group
- Run Procedures on Customer Groups

5.1.1. Create Device Groups

- Placing devices into a group lets you run actions and apply profiles to multiple devices at once.
- OS-specific profiles will be automatically applied to relevant devices.


Add a new device group

- Click 'Devices' > 'Device List'
- Click the 'Group Management 'tab
- Select a company/department on the left (ITarian MSP customers only)
- · Click the 'Create Group' button
 - MSP customers can also place their mouse over the company name and click the '+' sign that appears:



The 'Add Group' interface will open.






'Add Group' dialog - Table of Parameters		
Form Element	Description	
Name	Create a label to identify the group.	
Company	The parent company of the group. The company to which the group belongs.	
	 If you already selected a company on the left then this field is pre-populated. You cannot edit this field. 	
	If you selected 'Show All' then you need to choose a parent company for the group.	
	 Type first few letters of the company name and select the company from the options. 	
Devices	Choose devices which will be members of the group.	
	Type the first few letters of the device name and select from the suggestions.	
	Repeat the process to add more devices.	
	 Note - You can only add devices which are enrolled to the parent company. 	
	Tip: You can add devices at a later stage too.	

• Fill the details and click 'Add'.

The new group will be created under the company. You can add or remove devices and manage profiles applied to the devices in the group at any time. See **Edit a Device Group** for more details.





- Repeat the process to add more groups.
- The new groups will be listed for the selected company/department. The added groups will also be listed in the hierarchical structure on the left for the company/department.
- Appropriate configuration profiles can now be applied to each new group. See Assign Configuration Profiles to a Device Group for more details.

5.1.2. Edit a Device Group


The 'Group Management' interface lets you view/add/remove devices, rename the group and manage group policies.

- View or edit a device group
- Add new devices to a group
- Remove devices from a group
- Rename a group
- Assign Configuration profiles to a device group
- Export the list of devices in a group
- Remove a group

View or edit a device group

- Click 'Devices' > 'Device List'
- ITarian MSP customers should choose the company/department whose group is to be edited
- Click the name of the group to be edited from the left menu
- · Click the 'Group Management' tab on the right

The group management interface for the selected group will open.



The list of devices included in the group will be displayed, with their details.

Device Group Details - Column Descriptions	
Column Heading	Description
OS	The operating system of the device.
Name	The label assigned to the device by the user.
	Grey text color indicates the device has been offline for the past 24 hours.
	If no name is assigned, the model number of the device will be used as the name. You can assign a new name as required.
	Click the device name to view device details.
	 See Manage Windows Devices, Manage Mac OS Devices, Manage Linux Devices and Managing Android / iOS Devices for more details.
Logged in User	The name of the user currently signed-in to the device.
	The user name is prefixed with the active directory (AD) domain or workgroup that the user is currently logged-in to:
	Active Directory - Name is shown as <ad domain="" name="">\<user name=""></user></ad>
	Workgroup - Name is shown as <workgroup name="">\<user name=""></user></workgroup>
	No network - Name is shown as <device name="">\<user name=""></user></device>
	Click the icon to copy the username to the clipboard.
Active Components	Comodo Client Security modules which are enabled on the device
	Examples include 'Antivirus', 'Firewall', 'Containment' and 'Agent Only'
	The possible components for each OS are as follows:
	Android - Antivirus and agent (EM communication client)
	iOS - Agent
	Windows - Antivirus, agent, firewall and containment.
	Mac OS - Antivirus and agent



	Linux - Antivirus and agent
Patch status	The number of patches available for Windows endpoints. Patch statuses are as follows: One of patches available for Windows endpoints. Patch statuses are as follows:
Customer	Critical patches are available. The number to the right shows how many are pending. Click the number to view and manage the patches. See View and Install Windows and 3rd Party Application Patches for more details. Optional patches are available. Click the number to the right to view and manage the patches. The name of the company to which the device is enrolled.
	 ITarian customers can enroll devices to any of the companies they have created in ITarian. ITarian Enterprise / EM standalone customers can only use the 'Default company'.
Last Activity	The date and time at which the device last communicated with the EM server.
	Controls
Add Devices to Group	Add devices of any operating system to the group. See Add new devices to a group for more details.
Manage Profiles	View and apply configuration profiles to all member devices in the group at once. See Assign Configuration Profiles to a Device Group for more details.
Rename Group	Change the label of the group.
Delete Device Group	Remove unwanted device groups from EM. Note - You cannot delete a device group unless it is empty. Remove all member devices before deleting. See Remove a Device Group for more details.
Remove from Group	Remove unwanted devices from the group. See Remove devices from a group for more details.
Run Procedure	Execute script and patch procedure on devices. See 'Apply Procedures to Windows Devices' for more help with this.
Export	Save a list of devices in the group in .csv format. The exported .csv is available in 'Dashboard' > 'Reports' See Export the List of Devices in a Group for more details.

• Click column headers to sort the items in ascending/descending order of entries in that column.

Search and Filter Options

- Click the funnel button \mathbf{Y} at the right end to open the filter options.
 - To filter the items or search for a device based on its OS, online status, name, patch status, company, currently logged-in user and/or a period of last activity, enter the search criteria in part or full in the text box and click 'Apply'.
- To display all the items again, remove / deselect the search key from filter and click 'OK'.

ITarian Endpoint Manager - Administrator Guide



• EM returns 20 results per page when you perform a search. To increase the number of results displayed per page up to 200, click the arrow next to 'Results per page' drop-down.


Add New Devices to a Group

- Click 'Devices' > 'Device List'
- · ITarian MSP customers choose the parent company on the left
- Click the name of the group you want to edit
- Click the 'Group Management' tab
- Click 'Add Devices to Group' at the top right.

Note: You can only add devices which belong to the same company as the group.

The interface will list all devices enrolled to the company that are not already in the target group:






Select the devices to be added to the group and click 'Add Selected Devices'.

Tip: You can filter or search for specific devices using the filter options that appear on clicking the funnel icon at the top right.

A confirmation dialog will appear.



Click 'Confirm'. The devices will be added to the group.


Once the device(s) are added to the group, the configuration profiles, associated with the group, will be applied to the device, in addition to the profiles, which are already in effect on the device.

Tip: You can add a device to a group from the 'Device Details' interface too. For more details, see **View and Manage Device Group Membership**.



Remove Devices from a Group

- Click 'Devices' > 'Device List'
- ITarian MSP customers choose the parent company on the left
- · Click the name of the group you want to edit
- Click the 'Group Management' tab
- Choose the devices you want to remove
- · Click 'Remove from Group'



Click 'Confirm' in the confirmation dialog.

If a device is removed from a group, any group profiles will also be removed from the device.

Tip: You can remove the membership of a device to a group, from the 'Device Details' interface too. For more details, see **View and Manage Device Group Membership**.


Rename a Group

- Click 'Devices' > 'Device List'
- ITarian MSP customers choose the parent company on the left
- Click the name of the group you want to edit
- Click the 'Group Management' tab
- Click 'Rename Group'
 - Alternatively, move your mouse over the group name and click the pencil icon





The 'Rename Group' dialog will open.




• Enter a new name for the group in the 'Name' text box and click 'Rename'.

The group will be updated with the new name.

Export the List of Devices in a Group

- Click 'Devices' > 'Device List'
- ITarian MSP customers choose the parent company on the left
- Click the name of the group you want to edit
- · Click the 'Group Management' tab
- Click the 'Export' button above the table then choose 'Export to CSV':





- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

5.1.3. Assign Configuration Profiles to a Device Group


You can view profiles currently assigned to a device group, add new profiles or remove existing profiles.

See Configuration Profiles if you need help to create a profile.

View and manage the profiles applied to a group

- Click 'Devices' > 'Device List'
- ITarian MSP customers choose the parent company on the left
- · Click the name of the group you want to edit
- Click the 'Group Management' tab
- Click 'Manage Profiles' from the options at the top
- This will show a list of all profiles associated with the device:






Add a new profile

- · Click 'Add Profiles' at the top.
- Select the profiles you want to apply to the group then click 'Save'.






EM applies all profiles which are appropriate for a device's operating system.

Remove a profile from a group

• Select the profile(s) to be removed, from the 'Manage Profiles' interface and click 'Remove Profiles'






The profile(s) will be removed from member devices of the group, where applied, according to their operating system(s).

Note: Disassociating a profile from a device group will remove the profile from devices only if it is applied because the device is a member of that group. If the same profile is applied to a member device through some other source, (like the profile is applied to the user of the device or a group to which the user belongs), then the profile will not be removed.

5.1.4. Remove a Device Group

- Note you cannot delete a device group unless it is empty. Remove all member devices first.
- Click 'Devices' > 'Device List'
- ITarian MSP customers choose the parent company on the left
- · Click the name of the group you want to edit
- · Click the 'Group Management' tab
- Ensure there are no devices in the group. See Remove all devices from the group if required.
- Click 'Delete Device Group'.





Click 'Confirm' to apply your changes

The device group will be removed from EM.


5.1.5. Run Procedures on Customer Groups

Procedures are standalone instruction scripts and patches for Windows devices. Each script allows you to accomplish a specific task. Endpoint Manager ships with a range of pre-defined scripts for you to use, and provides a python editor so you can create your own.


This section explains how to run procedures on all devices in a customer group. See **procedures** if you want to learn more about procedures in general.

- Click 'Devices' > 'Device List'
- Select the customer in the middle pane then 'Group Management'
- Select the target groups of the customer then click 'Run Procedure':





Next, choose the script you want to run and other options:



- Procedure Name Type the name of the procedure that you want to add in the first field (make sure you
 have approved the procedure)
- Run as Local System User / Run as Logged in user Choose the user account under which the
 procedure should run. This option is not available for patch procedures.
- Send the resulting logs by email Script procedures only.
 - Send to current user Procedure results are sent to the admin who is currently logged into Endpoint Manager.
 - Send to the following email addresses Add email addresses to whom log results should be sent.
- Click 'Run'.

Endpoint Manager runs the procedure on the customer groups' devices.




5.2. Manage Devices

Click 'Devices' > 'Device List' > 'Device Management'

Note: If you haven't done so already, you should first enroll users then enroll their devices.

- The 'Device Management' screen is an inventory of all mobile devices and endpoints for a company.
- It shows each device's connection and patch status, which security components are enabled, recent activity, and more.



From this area you can:

- Enroll new devices for management (Windows, Mac, Linux, iOS and Android)
- · Add or remove profiles on any selected device
- Install Comodo Client Security and other packages on Windows, Mac OS and Linux endpoint
- Take remote control of Windows and Mac OS devices
- Browse folders and files on Windows endpoints
- View and manage currently running processes on Windows endpoints
- View applications installed on Windows endpoints
- Remotely uninstall applications from Windows endpoints
- · Remotely run procedures on Windows endpoints
- Remotely install OS and third-party application patches on Windows endpoints
- Remotely restart Windows endpoints
- Sound an alarm on mobile devices
- Send custom text messages to mobile devices
- Remotely wipe mobile devices
- Remotely lock mobile and Mac OS devices
- Reset lock-screen passcodes
- View detailed information about any device by simply clicking the device name



- View and edit device owner information by clicking the owner name
- View and manage device group memberships of a device
- · Generate a device details reports

Open the 'Device Management' interface


- Click the 'Devices' > 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane

The interface shows devices belonging to the company or group selected on the left.

Select 'Show All' to view every device enrolled to EM.

Column Heading	Description
OS	The operating system of the device.
Name	The label assigned to the device by the user. If no name is assigned, the model number of the device will be used as the name.
	The device icon to the left of the name shows the device's connection status:
	Device is not reachable. The connection might be down or the endpoint is switched off.
	 Slow connection. The device is connected but commands and messages may take some time to execute since the endpoint is busy.
	Good connection. Commands should be executed in real time.
	- A device is marked as 'Old' if it does not connect to EM for a certain number of days.
	You can set how many consecutive days of inactivity must pass before EM marks a device as 'Old'.
	You can also tell EM to remove devices that do not reconnect for a certain number of days after being marked 'Old'.
	See Configure Device Removal Settings to read more.
	- The device is a duplicate. Applies to Windows devices only.
	A duplicate device is one that has the same name and / or MAC address as one or more other devices. This could be because the same device was enrolled more than once, or because the same name was given to multiple devices.
	You can tell EM to auto-remove duplicate devices or to selectively uninstall the clients.
	Alternatively, you could simply rename a device to remove the 'Duplicate' flag.
	See Device Removal Settings to read more.
	Windows endpoints also have a shield icon to the right of their name. The shield has a colored circle on it which indicates the status of Comodo Client Security (CCS):
	Yellow - CCS is not installed on the endpoint.
	 Click the shield icon to remotely install CCS on the endpoint.
	The 'Install Additional Comodo Packages' dialog will appear.







	- Communication with CCS on the endpoint has been lost.
	 Click the device name to open the device details interface. See Manage Windows Devices, Manage Mac OS Devices and Manage Android / iOS Devices for more details.
Active Components	Indicates which modules are installed on the device. Possible components are 'Agent', 'Antivirus' (AV), 'Firewall' (FW) and 'Containment'.
	 Android devices - The agent will automatically install the AV (antivirus) component.
	iOS devices - Only the agent (EM client) will be installed
	 Windows endpoints - Available components are - Agent, AV, FW (firewall) and Containment. These components are installed automatically when a profile featuring the components is installed.
	Mac OS endpoints - Available components are EM Agent and AV
	The color of the icon shows the status of the component:
	Green - Installed and active
	Gray - Installed but disabled by profile setting
	 Blue (only applies to the 'Containment' module) - The containment module is baselining the device. During the baseline period, unknown files are auto- submitted to Valkyrie for analysis, but are not placed in containment. See Baseline Settings in Containment Settings for help to configure baseline settings.
	Blank - Component is not installed.
Patch status	Indicates the number of patches available for Windows endpoints. Patch status icons are as follows:
	No patches required. All patches are up-to-date.
	 Critical patches are available.
	The number to the right shows how many are pending. Click the number to view and manage the patches. See View and Manage Patches for Windows and 3rd Party Applications for more details.
	 Optional patches are available. Click the number to the right to view and manage the patches.
Customer	The name of the company to which the device is enrolled.
	 ITarian MSP customers can enroll devices to any of the companies they have created in ITarian.
	 ITarian Enterprise customers / EM standalone customers can only use the 'default company'.
Logged in User	The name of the user currently signed-in to the device.
	 The user name is prefixed with the active directory (AD) domain or workgroup that the user is currently logged-in to:
	 Active Directory - Name is shown as <ad domain="" name="">\<user name=""></user></ad>
	 Workgroup - Name is shown as <workgroup name="">\<user name=""></user></workgroup>

ITarian Endpoint Manager - Administrator Guide



	 No network - Name is shown as <device name="">\<user name=""></user></device> Click the icon to copy the username to the clipboard.
Last Activity	The date and time at which the device last communicated with the EM agent.

Click a column header to sort items in ascending/descending order of entries in that column.

Search and Filter Options

- The search box at the top allows you filter devices based on any parameter in the table.
- Alternatively, you can click the funnel button \(\cdot \) on the right to open filter options.




- · Click the info-box at right of the search field to view hints about search methods
- Enter your search criteria and click the magnifying glass to view devices matching the criteria.

You can search using the following criteria:

- OS Enter the operating system of the devices you wish to view.
- Online/Offline status Type 'Online' or 'Offline'
- Name Enter the name of the device in part or full
- Logged in User Enter the name of the end-user who is currently logged-in to the device.
- CSS Status Type one of the following values as required:
 - Not installed
 - Not supported
 - Secure
 - · Silent mode
 - Need attention
 - At risk
- Customer Enter the customer company name. Start typing to view auto-complete suggestions.
- Owner Enter the name/email address of the device owner in part or full
- Last Activity Enter a date in YYYY/MM/DD format to filter devices by the time of their last connection with EM.
 - You can use operators such as '<, '>', '<=' and '>=' to view devices before or after the date.
 - To view devices within a range, enter start and end dates as follows: YYYY/MM/DD YYYY/MM/DD
- Clear any search terms and click the magnifying glass to view all devices again.

You can also access filters by clicking the funnel button \textsup on the right:





- EM shows 20 results per page by default. Click the arrow next to 'Results per page' to increase this to a max. of 200.
- Use the left and right arrows and the page numbers to navigate to the page you want to view.

Please use the following links to find out more:

- Add New Devices
- Manage Windows Devices
 - View and Edit Device Name
 - View Summary Information
 - View Hardware Information
 - View Network Information
 - View and Manage Profiles Associated with Windows Device
 - View and Manage Applications Installed on a Device
 - View List of Files on the Device
 - View CCS Configuration Exported from the Device



- View MSI Files Installed on the Device through Endpoint Manager
- View and Install Windows and Third Party Application Patches
- View Antivirus Scan History
- View and Manage Device Group Memberships
- View Device Logs
- Manage Mac OS Devices
 - View and Edit Mac OS Device Name
 - View Summary Information
 - Manage Installed Applications
 - View and Manage Profiles Associated with the Device
 - View Mac OS Packages Installed on the Device through Endpoint Manager
 - View and Manage Device Group Memberships
 - View Mac Device Logs
- Manage Linux Devices
 - View and Edit Linux Device Name
 - View Summary Information of Linux Device
 - View Network Information of a Linux Device
 - View and Manage Profiles Associated with a Linux Device
 - View Linux Packages Installed on a Device through Endpoint Manager
 - View and Manage Device Group Memberships
- Manage Android Devices
 - View and Edit Device Name
 - View Summary Information
 - Manage Installed Applications
 - View and Managing Profiles Associated with the Device
 - View Sneak Peek Pictures to Locate Lost Device
 - View the Location of the Device
 - View and Manage Device Group Memberships
- Manage iOS Devices
 - View and Edit Device Name of an iOS device
 - View Summary Information of an iOS device
 - View Applications installed on an iOS Device
 - View and Manage Profiles Associated with an iOS Device
 - View the Location of an iOS Device
 - View and Manage Group Memberships of an iOS device

5.2.1. Add New Devices

Device enrollment is covered in the users section of this guide.

• See Enroll User Devices for help to add new devices.

5.2.2. Manage Windows Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Windows device




The device details page contains granular information about the device's hardware and software. This
includes device profiles, network connections, installed applications, patches and device group
membership.

Note: If you haven't done so already, you should first enroll users then enroll their devices.

View and manage a Windows device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the main configuration pane
 - Select a company or group to view devices in that group
 - Or
 - Select 'Show all' to view every device enrolled to Endpoint Manager
- Click the name of any Windows device to open its details pane:



The details screen contains a maximum of thirteen tabs:

- Device Name The device label. You can change this as per your preference. See View and Edit Device
 Name for more details.
- **Summary** General details about the device. This includes hardware and OS information, resource usage data, and an overview of CCS configuration. See **View Summary Information** for more details.
- Hardware Hardware configuration of the selected device. This tab is only available if legacy Comodo RMM agent is installed. See View Hardware Information for more details.
- Networks Information about the device's network card, MAC address, IP address, and more. See View Network Information for more details.

ITarian Endpoint Manager - Administrator Guide



- Maintenance Windows Details of maintenance periods of the device as applied by the profiles active on the device. See View Maintenance Windows Associated with Device for more details.
- Associated Profiles Details of the profiles deployed on the device. See View and Manage Profiles
 Associated with the Device for more details.
- Software Inventory Applications installed on the device. See View and Manage Applications Installed
 on a Device for more details.
- File List Inventory of files on the device along with their file rating ('Unrecognized', 'Trusted' or 'Malicious').
 See View the Files on a Device for more details. Note the 'File List' tab is only available if Comodo Client Security is installed on the device. See Remotely Install and Manage Packages on Windows Devices for more details.
- Exported Configurations Saved Comodo Client Security configuration files. These files let you export
 CCS settings to different endpoints. See View CCS Configurations Exported from the Device for more
 details. Note the 'Exported Configurations' tab is only available for devices with Comodo Client Security
 installed. See Remotely Install and Manage Packages on Windows Devices for more details.
- MSI Installation State MSI packages that have been installed on the device via Endpoint Manager. See
 View MSI Files Installed on the Device through Endpoint Manager for more details.
- Patch Management A list of available patches for the device. See View and Install Windows and 3rd
 Party Application Patches for more details.
- Antivirus Scan History A list of all threats identified on the device over time, and the actions taken by Endpoint Manager in response. See View Antivirus Scan History for more details. Note - the 'Antivirus Scan History' tab is only available if Comodo Client Security is installed on the device. See Remotely Install and Manage Packages on Windows Devices for more details.
- **Groups** A list of device groups to which the endpoint belongs. You can also manage group membership from here. See **View and Manage Device Group Membership** for more details.
- Logs View event logs from activities recorded on the device. See View Device Logs for more details.
 - Alert Logs Alerts generated because of a breach of monitoring conditions or because of a
 procedure deployment.
 - Monitoring Logs Monitoring rules can be added to an EM policy to observe resource usage on a
 device. For example, you may wish to create a log entry if CPU usage goes above 75% for a
 certain period of time.
 - Script Logs Script procedures that were run on the Windows device. Scripts can be run manually or automatically via a profile schedule.
 - Patch Logs A record of operating system patch installations. Patches can be installed manually
 or automatically via a profile schedule.
 - Third Party Patch Logs A record of patch installations for non-Comodo applications.
 - Installation Logs Apps installed on the device from the Windows Application store (Application Store > Windows Application Store). See Install Windows Apps on Devices for more details.
 - Uninstallation Logs Apps uninstalled from the device through Endpoint Manager. You can remotely uninstall unwanted apps from Windows devices in two ways:
 - 'Device Details' > 'Software Inventory' interface See View and Manage Applications Installed on a Device for more details.
 - 'Applications' > 'Global Software Inventory' interface See Uninstall a Windows Application from Selected Devices
 - Discovery Logs Shows results of any network discovery scans run using the device as probe.
 Network discovery scans are used to identify managed and unmanaged devices, including SNMP devices connected to the network. See Create and Run Network Discovery Tasks if you want to learn more about discovery scans and probe devices.

ITarian Endpoint Manager - Administrator Guide



You can remotely perform various tasks on the device using the buttons above the table:



- Manage Profiles Add/remove configuration profiles to/from the device. These profiles are in addition to any group profiles applied to the device. See Assign Configuration Profiles to Selected Devices for more details.
- Remote Control Take-over managed endpoints over a remote desktop connection and transfer files between the remote device and your management computer. See Remote Management of Windows and Mac OS Devices for more details.
- File Transfer Use the remote control tool to transfer files between the remote device and your management computer. See Transfer Items to / from the Remote Computer for more details..
- Remote tools Explore and manage files and folders on a remote device, view and manage currently
 running processes and services and remotely run command line commands and Power Shell scripts, on a
 managed Windows device. See the following sections for help on the respective task:
 - Remotely Manage Folders and Files on Windows Devices
 - Manage Processes on Remote Windows Devices
 - Manage Services on remote Windows Devices
 - Use the command prompt on remote Windows Devices
- Run Procedure Execute script, patch and third-party application patch procedures on the device. See Apply Procedures to Windows Devices for more details.
- Install or Manage MSI Packages Remotely install Comodo endpoint security software and third party Windows packages. See Remotely Install and Manage Packages on Windows Devices for more details.
- Refresh Device Information Contacts the device and updates system information. See Update Device Information for more details.
- Reboot Remotely restart the device. See Restart Selected Windows Devices for more details.
- Export Security Configurations Save the device's current CCS configuration as a profile. Exported
 profiles can be viewed under the Exported CCS Configurations tab. These can then be imported later as
 a Windows profile, potentially for deployment to other devices. See Import Windows Profiles for more
 details.
- Delete Device Removes the device from Endpoint Manager. See Remove a Device for more details.
- Change Owner Change the user with whom the device is associated. You can also change the type of
 device to corporate or personal. See Change a Device's Owner and Change the Ownership Status of a
 Device for more details.


5.2.2.1. View and Edit Device Name

- Enrolled devices are listed by the name assigned to them by their owner. For example, 'Franks-PC'
- If no name was assigned then the manufacturer device name or model number is used.
- Custom Device Name You can change the label of the device according to your preference. The custom name will apply in Endpoint Manager but will not change the name on the endpoint itself.
- Allow Auto Rename of Device Custom Name If enabled, the custom name is replaced automatically by the
 actual device name during the next sync. Disable this option if you want to retain the custom name.


Change a device name



- Click the 'Devices' link on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view the list of devices in that group Or
 - Select 'Show all' to view every device enrolled to EM
- · Click on any Windows device then select the 'Device Name' tab



- Custom device name The current name of the device.
- Allow auto rename of device custom name Indicates whether the actual device name will automatically replace any custom name during the next sync.
- To change the name of the device, click the 'Edit' button at the right.



- Enter the new name in the 'Custom Device Name' field
- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name
 in the list. If this is enabled, the custom name will be automatically replaced with the device's name
 or model number during the next sync with the EM communication client on the device.
- Click 'Save' for your changes to take effect.

The device will be listed with its new name.




To restore the name of the device as it was at the time of enrollment, click 'Edit' from the 'Device Name' interface, click 'Restore' at the right and click 'Save'.

5.2.2.2. View Summary Information

The 'Summary' tab contains general device information, including operating system details, hardware details, last activity, CCS configuration and resource usage.

To view the device summary

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab
 - Select a company or a group to view devices in that group Or
 - Select 'Show all' to view every device enrolled to EM
- Click on the name of a Windows device then open the 'Summary' tab:



- Device Summary Basic hardware, software, user and connection information. Includes device name, user, operating system, active directory domain, ownership type, IP address, local time zone and more.
- OS Summary Detailed information about the device operating system. Includes OS build, service pack availability, last restart time, reason for last reboot and more.
- Security Products Info Details about the Comodo security client installed on the endpoint. The security
 client provides the antivirus, firewall and containment services required to protect the device. Information in
 this section includes active security components, database update status, the amount of time remaining in
 baseline mode, and more.
- Performance Metrics Current hardware resource usage on the device. Includes CPU, RAM, network and disk. The details are refreshed every 30 seconds.

5.2.2.3. View Hardware Information


Note: This section is only available for devices that have the legacy Comodo RMM agent installed.



This screen contains basic details about a device's motherboard and hardware setup (RAM slots, processor type etc).

To view a device's hardware details

- Click the 'Devices' link on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view the list of devices in that group Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows device then select the 'Hardware' tab




5.2.2.4. View Network Information

The 'Networks' screen shows details about the networks to which an endpoint is connected.

View a device's network details

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab
 - Select a company or a group to view devices in that group
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows device then select the 'Networks' tab





5.2.2.5. View Maintenance Windows Associated with Device

The maintenance windows tab lists all maintenance windows to which the device is assigned.


- A maintenance window is a scheduled time-slot when your Endpoint Manager procedures will run. A
 procedure is a task you want to run on your devices. For example, to patch all Windows endpoints.
- You create a maintenance window by adding a 'Maintenance Window' section to a Windows profile. You can then assign any procedures in the profile to the maintenance window.
- The procedures will run on all devices to which the profile is applied at the time set in the maintenance window.
- See Maintenance Window Settings for more help on this topic.

View maintenance windows associated with a device

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab
 - Select a company or a group to view the list of devices in that group Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows device then select the 'Maintenance Windows' tab

ITarian Endpoint Manager - Administrator Guide





- A green 'On' icon means that the device is in at least one active maintenance window.
- As mentioned earlier, a maintenance window is a section in a configuration profile. The 'Profile' column shows you which profile(s) have maintenance windows which include this device.
- The 'Current Status' column shows you whether the maintenance window is active or not.

Maintenance Windows - Column Descriptions	
Column Heading	Description
Name	The label of the maintenance window. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Period	How often the maintenance window runs.
Profile	The profile to which the maintenance window belongs. Click profile name to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Maintenance Time	The time slot defined in the maintenance window • Click the time slot to view the details of the maintenance window. An example is shown below:



	Maintenance Window ×
	Name Run system cleanup Scheduled Weekly Start time 06:00 AM End time 07:30 AM Days of Week Sunday
Current Status	Whether or not the maintenance window is active.
Created by	The administrator who created the profile. • Click the name of an administrator to view their user details. See View the details of the User for more details.
Created on	The date and time at which the profile was created.

 Click any column header except 'Maintenance Time' and 'Current Status' to sort items in alphabetical or ascending/descending order.

5.2.2.6. View and Manage Profiles Associated with a Device

The 'Associated Profiles' tab lists all active configuration profiles on an endpoint. A profile may be applied to a device for any of the following reasons:


- · Because it is a default profile
- It was specifically applied to the device
- It was specifically applied to the user
- The device belongs to a device group which has a group profile
- · The user belongs to a user group which has a group profile

For more details on configuration profiles, see **Profiles for Windows Devices**.

View and manage the profiles associated with a device

- · Click the 'Devices' link on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view the list of devices in that group Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows device then select the 'Associated Profiles' tab





Associated Profiles - Column Descriptions	
Column Heading	Description
Name	The profile label. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Source Associated	The source through which the profile was applied to the device. Configuration profiles can be applied to a device in different ways:
	 Profiles can be directly applied to the device. See Assign Configuration Profiles to Selected Devices for more details
	 Profiles applied to a user are deployed to all devices belonging to them. See Assign Configuration Profiles to User Devices for more details
	 Profiles applied to a user group are deployed to all devices owned by group members. See Assign Configuration Profile to a User Group for more details
	 Profiles applied to a device group are deployed to all member devices in the group. See Assign Configuration Profile to a Device Groups for more details
	Click a source to view its details interface.
Information about Association	The status of profile application to the device.

Click the 'Name' column header to sort the items in the alphabetical order of the names of the items

Add or Remove Profiles

Profiles can be added or removed from the device clicking 'Manage Profiles' option at the top. See **Configuration Profiles to Selected Devices** for more details.


5.2.2.7. View and Manage Applications Installed on a Device

- The software inventory area is a list of all applications installed on a device.
- The interface also lets you remotely uninstall applications.



View applications installed on a device

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view devices in the group
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click the name of a Windows device then select the 'Software Inventory' tab:



Column Heading	Description
Software	The name of the application.
Vendor	The publisher of the application.
Version	The version number of the application.
Installation Date	The date at which the application was installed on the device.


Endpoint Manager periodically synchronizes with devices to get an up-to-date list of their installed applications. Click 'Update Software Inventory' to manually synchronize.

Remotely uninstall applications

Supported 3rd party applications can be remotely uninstalled from the Endpoint Manager. See **EM Supported 3rd Party Applications** for a full list.

- Select an application in the list
- Click 'Uninstall Selected Application'
- An uninstall command will be sent to the device.
- You will see the following message if the software cannot be uninstalled without notifying the device user:





Click 'Proceed' to continue with the uninstall.

Tip:

- You can uninstall an application from selected or all Windows devices from the 'Global Software Inventory'.
- Click 'Applications' > 'Global Software Inventory' to access this area.
- See View and Manage Applications Installed on Windows Devices if you need more help with this.
- · Click the column headers to sort items in alphabetical or ascending/descending order
- Click the funnel button on the right to use the filter


5.2.2.8. View the Files on a Device

• The 'File List' tab shows executable files found on a device along with their trust rating.

View files on a Windows device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click the name of a Windows device then select the 'File List' tab:





File List - Table of Column Descriptions	
Column Heading	Description
File Name	The label of the executable file or application.
File Path	The installation location of the application at the endpoint. • Click the icon to copy the path to the clipboard.
File Hash	The SHA1 hash value of the executable file. • Click the iii icon to copy the hash value to the clipboard.
Size	The size of the executable file.
Comodo Rating	The trust rating of the file as per the Comodo File Look-up service, reported by the CCS installations at the endpoints
Admin Rating	The trust rating of the file as manually set by the administrator, if any.

Comodo Client Security monitors all file activity on a Windows endpoint. New executables are scanned against the Comodo files database and rated as 'Unrecognized', 'Trusted' or 'Malicious'. You can configure this behavior in the 'File Rating settings' section of the configuration profile applied to the device. See **File Rating settings** in **Creating a Windows Profile** for more details.

Unrecognized Files

Files that could not be identified as 'Trusted' or 'Malicious' by Comodo Client Security (CCS) are reported as 'Unrecognized' to Endpoint Manager. You can review these files and manually rate them as 'Trusted' or 'Malicious' if required.

- The rating you set is purely a local trust rating for the file. It does not affect the global rating set by Comodo.
- The 'Valkyrie' section of a profile lets you auto-upload unknown files to the cloud for behavior analysis.
 See Valkyrie Settings for more details

Background Note: Valkyrie is a file verdicting service that tests unknown files with a range of static and dynamic checks. The results of these tests produce a trust verdict on the file. This verdict can be viewed in the 'Windows File List' > 'Valkyrie Processed Files' tab. See **View List of Valkyrie Analyzed Files** for more details.



Trusted Files

Files are identified as trusted in the following ways:

Cloud-based file lookup service (FLS) - Whenever a file is accessed, Comodo Client Security (CCS) checks the file's reputation on Comodo's online file database. It also consults the local list of trusted vendors.

The file is classed as trusted if:

- The app is from a vendor with a 'Trusted' status in the local vendor list in CCS
- The app trusted is on Comodo's online file database (aka, it is whitelisted)
- Admin rating Admins can assign a 'Trusted' rating to files from the Application Control interface
- User Rating Users can assign a 'Trusted' rating to files at the local CCS installation in two ways:
 - In response to an alert. If an executable is unknown then it may generate a HIPS alert on the local endpoint. Users could choose 'Treat this as a Trusted Application' at the alert
 - The user can assign 'Trusted' rating to any file from the 'File List' interface.

CCS creates a hash of all files assigned 'Trusted' status by the user. In this way, even if the file name is changed later, the file will retain its trusted status as the hash remains same. This is particularly useful for developers who are creating new applications that, by their nature, are unknown to the Comodo safe list.

Malicious Files

Files identified as malicious by the File Look-Up Service (FLS) will not be allowed to run by default. These files are reported as malware to EM.

The File List screen

Possible file ratings are 'Unrecognized', 'Trusted' or 'Malicious'. Administrators can manually set the file rating at their discretion.

- Files rated as 'Trusted' are allowed to run.
- Files rated as 'Malicious' are guarantined and not allowed to run.
- Files rated as 'Unrecognized' are run inside the container an isolated operating environment. Contained applications are not permitted to access files or user data on the host machine.

Any ratings set by the administrator are propagated to all enrolled endpoints.

Admins can also view a history of purged files. Purged files are those which existed on devices at one point in time, but are not currently present on any device. To view these files, apply the filter named 'Show Purged Files'. See the explanation of **Filter Options** given below.

Tip: if you wish to see all files across all managed devices, please view the 'Applications' and 'Application Control' interfaces. See 'Applications > Mobile Applications' to view applications in mobile devices.

Sorting, Search and Filter Options

- · Click any column header to sort items in alphabetical order
- Click the funnel icon to open more filter options:
- Use the check-boxes to show or hide purged, non-executable, hidden or unrecognized files.
- Use the search fields to filter by file name, file path or SHA1 hash value. You can also filter by file size and the number of devices on which the file is present.
- Use the drop-down boxes to filter items by Comodo and/or admin rating



Clear any search filters and click 'OK' to display all items again.

You can use any combination of filters simultaneously to search for specific apps.

Manage Applications

The 'File List' interface allows you to:


- View the details of files in the list
- View Process Activities of a File
- Assign Admin rating to a file
- · Hide/Display selected files in the list
- Export the list of selected files to a CSV file
- · Remove files from the list

View file details

- Simply click on a file in the list or select a file and click 'File Details' at the top.
- The File Details screen contains two tabs:
 - **File info** Shows basic file details and the devices on which the file is present. You can also change the trust rating of the file in this area.
 - **Device List** Displays the list of managed Windows devices on which the file is discovered. The 'Device List' interface also allows you to view the process activities of the file in respective devices.


File info

• The file info screen shows file name, installation path, file type, version, size, hash values and the date the file was first encountered. The screen also shows the file's trust rating and the number of endpoints on which the file is present.




 The 'Change Rating' button allows you to manually set the file's rating as 'Trusted', 'Malicious' or 'Unrecognized':






The new rating will be sent to all endpoints.

• The 'Record' button lets you hide, display or remove the file from the 'File List' screen.



Device List Screen

The device list screen shows the list of endpoints on which the item was discovered. The screen also shows
the installation path, the installation date and the file rating assigned by Comodo Client Security. The
Viruscope column shows detailed info on processes started by the file. See the explanation under View
Process Activities of a File for more details.



You can remove the file from device(s) by selecting a device then clicking 'Delete'




View Process Activities of a File

Note: In order to fetch process activity data, VirusScope should be enabled in the profile in effect on the endpoint. See **Configuring Viruscope Settings** in **Creating a Windows Profile** for more details.

To view the activities of a file on the endpoint

- · Click the file name from the 'File List' screen to open the 'File Details' screen
- Click the 'Device List' tab
- Click the 'View Processes' link in the 'Viruscope' column in the row of the device name.
- This will open a list of processes executed by the file on the selected endpoint in chronological order:




- Click 'View Activity' to see detailed information about each process. The 'Process Activity' interface has two tabs:
 - Summary Displays the name of the device and the installation path of the executable
 - Activity Displays a chronological list of activities by the selected process, including details of files modified by the process.





The 'Activity' - Table of Column Descriptions	
Column Heading	Description
Date	The date and time of process execution.
Action	The task executed by the process on the target file.
Path	The location of the target file.
Details	A link to view more information about the action.

You can inspect a particular activity by clicking the 'Details' link:



Assign Admin Rating to a File


- Each file on an endpoint is automatically scanned and assigned a trust rating by Comodo Client Security.
- These ratings can be either 'Unrecognized', 'Trusted' or 'Malicious'. The rating for each file is shown in the 'Comodo Rating' column of the 'File List' screen.
- The file rating determines whether or how the file is allowed to run:
 - **Trusted** The file will be allowed to run normally. It will, of course, still be subject to the standard protection mechanisms of Comodo Client Security (behavior monitoring, host intrusion prevention etc).
 - **Malicious** The file will not be allowed to run. It will be automatically quarantined or deleted depending on admin preferences.



- **Unknown** The file will be run inside the container. The container is a virtual operating environment which is isolated from the rest of the endpoint. Files in the container write to a virtual file system, use a virtual registry and cannot access user or operating system data.
- Automatic file rating can be configured in the 'File Rating' section of the configuration profile active on the endpoint. See File Rating settings in Creating a Windows Profile for more details.
- Click 'Change Rating' in the 'File List' interface to manually set a rating for a selected file or files. The new rating will be propagated to all endpoints and will determine the file's run-time privileges. Admin assigned ratings will be shown in the 'Admin Rating' column of the interface:

To assign a file rating to a file


- Select the file(s) whose rating you want to change and click the 'Change Rating' button.
- Choose the rating you want to from the drop-down:



As mentioned, the new admin rating will be set and sent to all endpoints. The Admin Rating will determine the file's run-time privileges.

Hide/Display Selected Files

Select the file(s) you want to hide and click 'Record' at the top




Select 'Hide / Unhide / Delete Record' as required.

To view hidden files




- · Click the funnel icon at the top-right to open the filter options
- Select 'Show with hidden file(s)' and click 'Apply'



The hidden files will be added to the list in the 'File List' screen. The files will be highlighted with a gray stripe.

To restore hidden files

- · Click the funnel icon at the top-right to open the filter options
- Enable 'Show with hidden file(s)'
- · Select the hidden files you want to restore and click 'Unhide Record' from the drop-down




The files will be displayed in the permanently.



Export the List of Files

You can export the 'File List' to a comma-separated values (CSV) file as follows:

Click the 'Export' button above the table then choose 'Export to CSV':




- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Remove files from the list

You can remove items you no longer wish to see in 'File List' screen. Deleted files will only be removed from the list. They will remain on the endpoints themselves.

- Select the files you want to remove and click 'Record' at the top
- Choose 'Delete Record' from the drop-down



5.2.2.9. View Exported Configurations and Import Profiles

- You can create a new Windows profile out of the CCS configuration on an endpoint.
- This is useful if you want to copy the configuration of an endpoint to multiple other endpoints

To export a CCS configuration




- Click the 'Devices' tab on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view their devices
 - Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click on the Windows device whose configuration you wish to export to open its 'Device Details' interface
- Click the 'Export Security Configuration' button at the top.



The CCS configuration will be exported as an .xml file with date/time stamp suffix in the file name. The profile will be saved on the EM server and can be viewed by clicking the 'Exported Configurations' tab of the device details interface of the same device.

To view and manage exported profiles

- Click the 'Devices' tab on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click the name of a Windows device then select the 'Exported Configurations' tab:




The 'Exported Security Configuration' List - Table of Column Descriptions	
Column Heading	Description
File Name	The label of the exported file.
Created	Date and time at which the CCS configuration was exported

· Click any column header to sort items in alphabetic or ascending/descending order

To import and save the security configuration

Click on the file name that you want to import as a profile






The file will be imported as an .xml file.

To import the saved configuration file as a Windows profile, see 'Step 2 - Import the .xml file as a profile for application to required endpoints or endpoint group(s) in 'Importing Windows Profiles'.

- To remove a file from the list, select it and click 'Delete'
- Click 'Confirm' to remove the file from the list



5.2.2.10. View MSI Files Installed on a Device through Endpoint Manager

- You can remotely install Endpoint Manager packages onto managed endpoints.
- These may be ITarian applications or third-party MSI packages. See Remotely Install and Update
 Packages on Windows Devices if you want to know more about this process.

View MSI file installation list on the device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab then




- Select a company or a group to view only their devices
 Or
- Select 'Show all' to view every device added to EM
- Click on the name of a Windows device then select the 'MSI Installation State' tab:



MSI Installation State - Table of Column Descriptions	
Column Heading	Description
Name	The source URL/file name of the MSI file.
State	The installation status of the MSI file.
Created	The date and time the MSI file installation command was sent.

- · Click any column header to sort items in alphabetic or ascending/descending order
- To delete an entry from the list, select it and click 'Delete MSI Installation State(s)'.



Click 'Confirm' to remove the file from the list

Only the chosen entry will be removed from the list but the package will not be uninstalled from the endpoint.



5.2.2.11. View and Manage Patches for Windows and 3rd Party Applications


Click 'Devices' > 'Device List' > click on a Windows device > Click 'Patch Management

- Windows and 3rd party applications have to be kept up-to-date to protect them from vulnerabilities.
- The details page of each device has a patch management tab which lets you view and install available patches. You can install multiple patches on a device simultaneously.
- This section tells you how to patch individual devices via the 'Device Details' screen.
 - Alternatively, there is a full patch management interface at 'Applications' > 'Patch Management'.
 Go here if you want to manage patches on multiple devices. See 'Patch Management' in this guide for help with this area.

Note: Hidden OS patches are not visible in a device's patch management screen. You can hide/unhide them in the full patch management interface at 'Applications' > 'Patch Management' > 'Operating System' tab.

Process in brief

- Click 'Devices' > 'Device List'
- Click the name of a Windows device to open its details page
- Select the 'Patch Management' tab
- Choose the patches you want to install from the 'Operating System' and 'Third Party' tabs
- Click 'Install Patches'. Each tab has a separate install button.



- Operating System Shows all installed and pending OS patches for the device. Additional details are
 available for each patch, including classification, severity, release date, installation status and
 knowledgebase articles.
- Third Party Applications Shows applications on the device for which updates are available. The version
 numbers of the currently installed version and the latest available version are shown. The 'severity' column
 tells you the importance of the update.

View Windows patches available for a device


- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons



- Click the name of a Windows device to open its details page
- · Select the 'Patch Management' tab
- · Click the 'Operating System' tab

Note:

- The 'Operating System' tab only shows Windows patches which are relevant to a device.
- Any hidden patches are not shown. Hidden patches are configured in 'Application' > 'Patch Management'.
 For more details, see hide patches in Manage OS Patches on Windows Endpoints.
- Only approved and auto-approved patches are installed. See approve / decline patches in Manage OS
 Patches on Windows Endpoints for more details



Column Heading	Description
Title	The descriptive name of the patch.
	 Click the name to view patch details. See View Details of a Patch for more details.
KB	The Microsoft knowledgebase article for the patch.
	Click the number to view the article.
CVE	The common vulnerabilities and exposures (CVE) entry number. Click the number to view details such as summary, vulnerability type, published date, vendor, affected devices and more.
Bulletin	The Microsoft bulletin number that contains details about the patch.
	Click the number to view the bulletin page.
Classification	The category of the patch. The possible values are:
	 Update - Fixes a specific, non-critical problem. This type of patch does not address security-related bugs.
	 Definition update - Updates to a product's internal database. For example, an update to the virus signature database for Windows Defender.
	Critical Update - Fixes a specific, critical OS problem or a critical security-



	related bug
	Security update - Fixes a version specific, security related vulnerability
	 Update rollup - A collection of updates, hotfixes, security updates and critical updates packaged together for easy deployment. These updates generally target a specific Windows component.
	Driver - Adds software for controlling peripherals or add-on devices that could be connected to the endpoint
	Feature pack - Adds new functionality distributed after an OS release.
	 Service pack - Contains a collection of updates, hotfixes, security updates, critical updates and additional fixes.
	Tool - Installs a utility or feature for a specific task or a set of tasks.
	 Upgrades - Updates the Windows OS version on the endpoint to the latest build.
Severity	The criticality of the patch. The severity levels are:
	Critical
	Important
	• Low
	Moderate
	Unspecified
Reboot	Whether or not the endpoint requires a restart to complete the patch installation.
Release Date	The date on which the patch was released by Microsoft
Status	Whether the patch has been installed on the device or not. The possible values are:
	Available - The patch is yet to be installed on the device
	Installed - The patch is already installed
	Reboot pending - The patch is installed but the device needs to be restarted for the patch to take effect.
	Controls
Install Patch(es)	Deploy selected patches to the device. See Install missing patches on the device for more details.
Uninstall Patch(es)	Remove previously installed patches or updates from the device. See Uninstall patches from a device for more details.
Check Available Updates	Refresh patch inventory with the latest updates available for the device.
L	1

- · Click any column header to sort the items in ascending/descending order of entries in that column
- Click the funnel icon on the right to filter patches by various criteria, including by severity, by whether a patch is available, or by patch installation status.


Install missing patches on the device

Note – Make sure the missing patches are approved in 'Applications' > 'Patch Management' > 'Operating System'

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons



- Click the name of a Windows device to open its details page
- Select the 'Patch Management' tab
- Click the 'Operating System' tab
- · Identify patches with 'Available' status
 - Click the funnel icon on the right
 - Select 'Available' from the 'Status' drop-down
 - Click 'Apply'
- Select the patches you want to install
- Click 'Install Patch(es)':



- Maintenance window status Details of any maintenance windows in the device's profile.
 - Total number of devices outside of maintenance window The number of devices that are not part of a maintenance window. The patches can run on these devices.
 - Number of devices blocked by maintenance windows settings The number of devices on which you cannot run the patches because the admin has blocked patch installation outside the maintenance window.
 - Number of devices warned by maintenance window settings The number of devices that
 are part of a maintenance window and have warnings enabled. You can still run the patches
 on these devices.
 - Skip devices warned by maintenance windows settings A maintenance window is a
 time-slot reserved for running important tasks on target devices. Admins can enable a
 warning if somebody attempts to run a patch installation outside of the window. This
 setting will skip those devices which have been added to a maintenance window with
 warnings enabled.
- Click 'OK'.


Install command successfully added to install queue. The process may take a while to be completed.

A command will be sent to install the selected patches.



Uninstall patches and Windows updates from the device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
- Click the name of a Windows device to open its details page
- Select the 'Patch Management' tab
- · Click the 'Operating System' tab
- Identify patches and updates with 'Installed' status
 - · Click the funnel icon on the right
 - Select 'Installed' from the 'Status' drop-down
 - · Click 'Apply'
- Select the items you want to uninstall
- Click 'Uninstall Patch(es)':



Click 'OK' in the confirmation dialog

Uninstall command successfully added to uninstall queue. The process may take a while to be completed.


A command will be sent to remove the select patches/updates from the endpoint.

View 3rd party application patches available for a device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
- Click the name of a Windows device to open its details page



Click the 'Patch Management' tab then 'Third Party Applications':



Third Party Applications - Column Descriptions	
Column Heading	Description
Software Name	The label of the third party application. Click the name to view general application details and a list of devices on which the (outdated) application is installed. See View Details of an Application in Install 3rd Party Application Patches on Windows Endpoints for more details.
Vendor	The software publisher.
Software Category	The type of the application. Possible values include: Comodo Products Runtime applications Web Browsers Utilities Messaging File Compression utilities Developer Tools Documents Online Storage Other
Installed Version	The version number of the application currently installed on the endpoint.
Installation Date	The date on which the application was installed on the endpoint.
Latest Version Available	The version number of the latest version of the application that is available from the publisher
Severity	Indicates the level of severity of the update as determined by Microsoft. The severity levels are: Unspecified Critical Important Low Moderate




Release Date	The date at which the latest version of the application was released.	
Controls		
Install Patch(es)	Remotely install selected patches on the device. See Install 3rd party application patches on a device for more details.	

See EM Supported 3rd Party Applications to view a full list of applications that can be updated.

Install 3rd party application patches on a device

Only approved / auto-approved 3rd party application patches are installed. See **approve** in **Install 3rd Party Application Patches on Windows Endpoints** for more details.

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
- Click the name of a Windows device to open its details page
- Select the 'Patch Management' tab then open 'Third Party Applications'
- Choose the patches you want to install
- Click the 'Install Patch(es)' button
- Select 'Update to the latest version' or 'Update to specific version' as required



- · Click 'Send'
- Click OK in the confirmation dialog:





• A command will be sent to the endpoint to install the patch:

«Update to a Specific Version» command has been sent

- Once the command is received, the communication client (CC) on the endpoint will check whether
 the update is available on any other devices in the network.
- If available, CC downloads the patch from the other device over a peer-to-peer connection. This reduces bandwidth consumption and speeds up the deployment process.
- If the update is not available on the local network, CC downloads the update from the EM patch portal.

5.2.2.12. View Antivirus Scan History

The antivirus tab shows malware discovered on your managed endpoints. You can also see the malware installation path and quarantined items.

You can only view scan history on endpoints that have Comodo Client Security installed. The scan history covers manual scans and automatic scans which ran as part of a profile.

View Device Scan history

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab
 - Select a company or a group to view their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click on the name of a Windows device then click the 'Antivirus' tab


There are two tabs:

- Scan History Shows previous malware scans run on the device
- Quarantined Files Shows files placed in quarantine on the device

Scan History

Click the 'Scan History' tab if not already open:






Column Heading	Description
Malware Name	Label of the malicious item.
Path	The installation location of the malware.
Action Taken	The response taken by Comodo Client Security to the malware.
Action Status	The success or failure of the action.
Scan Identification Number	Unique identifier assigned to the scan which found the malware.
Date	Date and time at which the scan was performed.

Quarantined Files

- Open the 'Quarantined Files' tab
- Click 'Request quarantined files' on the right to manually refresh the list.



Column Header	Description
File Name	The file that was moved to quarantine.
File Path	The location of the identified file on the device



File Hash	The SHA1 hash value of the quarantined file
Date Quarantined	Date and time at which the malware was identified and moved to quarantine on the device.
Comodo Rating	The file's trust level as rated by CCS.
Admin Rating	The trust rating of the file as set by the administrator. Files can be rated as trusted, malicious or unrecognized.
User's last action	The response to the quarantined item by the EM admin.
User's last action status	The current status of the response. The possible statuses are: Operation failed. Try again. Command is queued Command has been sent

Click 'Request quarantined files' to import the list of most recently quarantined files from the device

The quarantine interface lets you:

- Restore False Positives from Quarantine
- Remove Malware files from the devices
- Rate files as 'Unrecognized', 'Trusted' or 'Malicious'

Restore False Positives from Quarantine

You can restore items from quarantine to their original location. This is useful if an identified item is a false positive, or a trustworthy file.

- Select the items from the list
- Click 'Restore file(s) on Device' on the top
- The items are restored to its original location on the device and removed from the list.

Remove Malware files from the devices

You can permanently delete items from the device, if identified items are genuine malware.

- Select the items from the list
- Click 'Delete file(s) from Device' on the top

The items are deleted permanently from the device and removed from the list.

Rate files as 'Unrecognized', 'Trusted' or 'Malicious'

You can set a trust rating for items in quarantine as 'Admin Rating'. The admin rating supersedes the Comodo rating for a file.

- Select the items from the list
- Click 'Rate as Unrecognized', 'Rate as Trusted' or 'Rate as Malicious' appropriate to the rating you want to assign to the items.

A confirmation is shown and the command is sent to the device.

- Files rated as 'Malicious' will stay in quarantine on the device.
- Files rated as 'Unrecognized' will be restored to their original locations on the device. Future AV scans may flag them as 'malicious' again.
- Files rated as 'Trusted' will be restored to their original locations in the device. These files will be whitelisted and skipped by future antivirus scans.



5.2.2.13. View and Manage Device Group Membership

The 'Groups' tab shows device groups to which the Windows endpoint belongs. You can remove the device from a group or add it to a new group.

View and manage device group membership

- · Click the 'Devices' tab on the left and choose 'Device List'
- Click the 'Device Management' tab at the top of the main configuration pane
 - Select a company or a group to view their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click the name of a Windows device then select the 'Groups' tab:



- The interface lists all groups of which the device is a member.
- Any group profiles will also be applied to the endpoint.


See Assign Configuration Profiles to a Device Group, for more details about applying configuration profiles to device groups.

Device Groups - Table of Column Descriptions	
Column Heading	Description
Group	The group label. Click the group name to view and edit group details. See Edit a Device Group for more details.
Customer	The name of the company for which the group was created.
Number of Devices	The total count of devices in the group. Click the number to view and edit group details. See Edit a Device Group for more details.
Created By	Name of the admin who created the group. Click the name to view the admin's details. See View the Details of a User for more details.
Created	The date and time at which the group was created.

Add the device to a new group



Click 'Add to Group'



The 'Add Device to Group' dialog will appear.


- **Choose Group(s)** Start typing the name of the group which you want the endpoint to join. Select the correct group from the list of suggestions.
- Repeat the process to add the device to other groups.
- · Click 'Add'.

The device will be added to the group or groups.

Remove the device from a group

• Select the group from the list and click 'Remove from Group'.





A confirmation dialog will appear.

Click 'Confirm' to remove the device from the group.

The device will be removed from the group. Group profiles will also be removed from the device.


5.2.2.14. View Device Logs

The 'Logs' tab shows all events that occurred on a specific device. This contrasts to 'Dashboard' > 'Audit Logs', which shows events on all devices.

View device logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices OR
 - Select 'Show all' to view every device enrolled to EM
- · Click the name of a Windows device
- Click the 'Logs' tab





There are eight types of logs, each shown on a different tab. Each row on these tabs is a specific event.

- The first column shows the template that caused the log to be generated. This is a named monitor, procedure or discovery task.
 - You can manage these templates in 'Configuration Templates' > 'Alerts' > 'Procedures' / 'Monitors'
 - The 'Alert Logs' tab has a slightly different layout. The template is shown in the 'Trigger Name' column
- The last column, 'Details', shows the contents of the log. Click this to view all steps that occurred in the
 event.
 - Again, this is slightly different in the 'Alert Logs' tab. 'Details' is replaced with 'Hit Count'.
- Each row represents a different event. For example, event logs are created when:
 - · A procedure fails
 - A condition is breached in a monitor
 - An alert is generated on the device
 - A script or patch procedure is executed
 - An app from the 'Windows Application Store' is installed
 - An OS update is installed or uninstalled
 - A network discovery scan is run

Click on the following for details about each type of log:

- Alert Logs
- Monitoring Logs
- Script Logs
- OS Patch Logs
- Third Party Patch Logs
- Installation Logs
- Uninstall Logs
- Discovery Logs

View Alert Logs

A record of all events where an alert was generated on the endpoint. For example, logs are generated after a failed procedure deployment or a breach of monitoring conditions.


View alert logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top menu
 - Select a company or a group to view just their devices



Or

- Select 'Show all' to view every device enrolled to EM
- · Click the name of the Windows device then select the 'Logs' tab
- · Select 'Alert Logs'



	Alert Logs - Table of Column Descriptions
Column Heading	Description
Alert Name	The alert template used in the event.
	 An alert template is just a collection of settings that determines alert recipients, information included, priority etc. The template does not specify the condition under which the alert is generated.
	The 'Trigger Name' is the actual procedure and monitor that generated the event.
	 In the standard workflow, all procedures and monitors have the 'Default Alert' template applied to them. Click 'Configuration' > 'Templates' > 'Alerts' > 'Default Alert' to view the settings in the default template.
	 You can also create your own alert templates. See 'Manage Alerts' for more details.
	 Click the alert name to view and configure its settings.
	Note - Discovery scan alert is not logged.
Trigger Name	The monitor or procedure that generated the alert.
	Procedures - An alert is created if a procedure fails
	Monitors - An alert is created when one or more of the monitor's conditions are met
	Click the trigger name to view and configure its settings
	See Manage Monitors and Manage Procedures for more details.
Trigger Type	Can be 'Monitor' or 'Procedure' as explained above.
Hits Count (24 H Period)	The number of time this condition was triggered in the past 24 hours.

View Monitoring Logs


The 'Monitoring Logs' tab



- Monitors are procedures which keep track of specific items on an endpoint. For example, you may set a monitor to track disk usage does not exceed a certain percentage.
- Monitors can be added to the 'Monitoring' section of a configuration profile
- Logs are shown for the past 24 hours.
 - See Manage Monitors for help to create monitors.
 - See Monitor Settings for help to add monitors to profiles

View monitoring logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click the name of the Windows device then select the 'Logs' tab
- Click 'Monitoring Logs'




Monitoring Logs - Table of Column Descriptions		
Column Heading	Description	
Monitor Name	The monitoring condition that was triggered to create the log. Click the name to view and manage the parameters of the monitor. See 'Monitor Settings' and 'Manage Monitors' for more details.	
Status	Whether or not the monitor is currently active on the device.	
Hit Count	The number of times the monitoring condition was breached during the last 24 hours.	
Last Hit Time	Date and time the monitoring rule was last broken.	
Last Update Time	Date and time when the information was last refreshed.	
Details	 Click the 'Details' link to view a log of the breach events. See View Details of Monitoring Logs (given below) for more information. 	

View Details of Monitoring Logs

Click the 'Details' link to view event information and the conditions of a monitor:





Details are shown under three tabs:

Logs - The date and time when the event occurred. Also shows details about the monitoring rule that detected the event.

Monitoring Log Details - 'Logs' tab - Table of Column Descriptions		
Column Heading	Description	
Time	Date and time of the event.	
Status	The current status of the monitored condition on the device.	
Additional Information	Details on the condition monitored and the breach	


Tickets - Shows any service desk tickets created by the events.



Second Monitor [Suspicious Files Folder for John] - Log Det	ails	← Back
ogs Tickets Statuses		
INK	STATUS	CREATED ON
ttps://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2019/01/03 10:14:05 AN
ttps://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2019/01/03 10:08:35 AN
ttps://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2019/01/03 10:03:35 AN
ttps://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2019/01/03 09:58:28 AN
ttps://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2019/01/03 09:52:05 AN

Monitoring Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	

Statuses - Shows the current status of all conditions monitored on the device.





Monitoring Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Condition Type	The observed parameter of the monitor. Click the condition to view the details of the monitored parameter and configured	
	thresholds. An example is shown below:	
	«CPU usage» Condition	
	Parameter CPU usage Condition Value During More than 5% 5 sec	
	Note The monitor checks the computer performance metrics. If the selected parameter meets the specified condition, the monitor triggers an alert. OK	
Value	The thresholds set for the parameter.	
Status	Current state of the monitored parameter.	
	 Green - The device is operating within the thresholds of the monitored condition. 	
	Grey - Unknown	
	Red - The device is exceeding the thresholds of the monitored condition.	
Status Changed at	The date and time of the most recent change to the monitor status.	


View Script Procedure Logs

- The 'Script Logs' tab shows script procedures that were manually run on Windows devices as well as those run automatically via a profile.
- For more details on creating and running script procedures, see Manage Procedures.

View script procedures logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - · Select 'Show all' to view every device enrolled to EM
- Click the name of the Windows device then select the 'Logs' tab
- Click 'Script Logs'






Script Procedure Logs - Table of Column Descriptions		
Column Heading	Description	
Procedure Name	The label of the script procedure that was run on the device. • Click the procedure name to view the configuration parameters of the script procedure. • See Manage Procedures for more details.	
Started At	The date and time when the procedure commenced.	
Started By	Who or what launched the procedure.	
	 A profile name will be shown here if the procedure was scheduled in a profile which is active on the device. 	
	 An admins name or email address will be shown if the procedure was run manually. 	
	Click the name/email address to view the details of the admin.	
Launch Type	Whether the procedure was scheduled or run manually.	
Executed By	The user account type used by Endpoint Manager to execute the procedure.	
Finished At	The date and time when the procedure was completed.	
Status	Whether the script successfully executed or not.	
	You can configure an alert if a procedure deployment fails. See 'Manage Procedures' for more details.	
Last Status Update	The date and time when the information was last updated.	
Details	 Click the 'Details' link to view a log of the procedure's execution. See the explanation of View Details of Script Procedure Logs given below. 	

View Script Procedure Log details

• Click the 'Details' link to view details about a procedure's execution:





The details are displayed under two tabs:


Statuses - The date and time at which successive stages in the procedure were run, their success status and results.

Script Procedure Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Time	The date and time of the procedure execution.	
Status	Whether the execution was successful or not.	
Additional Information	Provides details on the execution:	



If successful, displays the results of the procedure execution
 If failed, displays the reason for not running the procedure

Tickets - Displays tickets raised for any failed procedures.



Script Procedure Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	

View OS Patch Procedure Logs


- The 'Patch Logs' tab shows OS patch procedures that were manually run on Windows devices as well as those run automatically via a profile.
- For more details on creating and running patch procedures, see Manage Procedures.

View patch procedures logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click the name of the Windows device then select the 'Logs' tab
- Click 'Patch Logs'

ITarian Endpoint Manager - Administrator Guide






Column Heading	Description	
Procedure Name	The label of the patch procedure that was run on the device.	
	Click the procedure name to view and manage the configuration parameters of it.	
	See 'Manage Procedures' for more details.	
Started At	The date and time when the procedure commenced.	
Started By	Who or what launched the procedure.	
	 A profile name will be shown here if the procedure was scheduled in a profile which is active on the device. 	
	An admins name or email address will be shown if the procedure was run manually.	
	Click the name/email address to view the details of the admin	
Launch Type	Whether the procedure was scheduled or run manually.	
Finished At	The date and time when the procedure was completed.	
КВ	Microsoft knowledgebase articles for successfully deployed patches.	
	Click the number to view the article.	
Failed Patch KB	Microsoft knowledgebase articles for patches whose deployment failed.	
	Click the number to view the article.	
Status	Whether the OS patch procedure was successfully executed or not.	
	You can configure an alert if a procedure deployment fails. See 'Manage Procedures' for more details.	
Last Status Update	The date and time when the information was last updated.	
Targeted Patch Count	Total number of patches included in the procedure.	
Success Patch Count	Number of patches that were successfully installed.	



Details	•	Click the 'Details' link to view a log of the procedure's execution.
	•	See the explanation of View Details of OS Patch Procedure Logs given below.

View OS Patch Procedure Log details

• Click the 'Details' link to view details about a procedure's execution:



The details are displayed under two tabs:

Statuses - The date and time at which successive stages in the procedure were run, their success status and results.

OS Patch Procedure Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Time	Date and time of the procedure execution.	
Status	Whether the execution was successful or not.	
Additional Information	Provides details on the execution: If successful, displays the results of the procedure execution If failed, displays the reason for not running the procedure	



Tickets - Displays tickets raised for any failed procedures.




Column Heading	Description
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.
Status	Indicates whether the ticket is open or closed
Created On	The date and time at which the ticket was created.

View Third Party Patch Procedure Logs

- The third-party patch tab shows logs of patch deployments run on third party applications.
- This includes procedures that were run manually and those run automatically via a profile.
- If you need help to create patch procedures, see Manage Procedures.

To view third party patch procedures logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- · Click the name of the Windows device then select the 'Logs' tab
- Click 'Third Party Patch Logs'






Third Party Patch Logs - Table of Column Descriptions	
Column Heading	Description
Procedure Name	The label of the procedure that was run on the device.
	 Click the procedure name to view and manage the configuration parameters of the third party patch procedure.
	See 'Manage Procedures' for more details.
Started At	The date and time when the procedure commenced.
Started By	Who or what launched the procedure.
	 A profile name will be shown here if the procedure was scheduled in a profile which is active on the device.
	 An admins name or email address will be shown if the procedure was run manually.
	Click the name/email address to view the details of the admin
Launch Type	Indicates whether the procedure was scheduled or run manually.
Finished At	The date and time when the procedure was completed.
Status	Whether the third party patch procedure was successfully executed or not.
	 You can configure an alert if a procedure deployment fails. See 'Manage Procedures' for more details.
Last Status Update	Date and time when the information was last updated.
Details	Click the 'Details' link to view a log of the procedure's execution.
	 See explanation of View Details of Third Party Patch Procedure Logs given below.

View Third Party Patch Procedure Log details

• Click the 'Details' link to view details about a procedure's execution:






The details are displayed under two tabs:

Statuses - The date and time at which successive stages in the procedure were run, their success status and results.

Third Party Patch Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Time	Date and time of the procedure execution.	
Status	Whether the execution was successful or not.	
Additional Information	Provides details on the execution: • If successful, displays the results of the procedure execution • If failed, displays the reason for not running the procedure	

Tickets - Displays tickets raised for any failed procedures.






Third Party Patch Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	

View Installation Logs

- 'Installation Logs' tab shows installations of third party applications from the Windows application Store ('Application Store' > 'Windows Application Store').
- See Install Windows Apps on Devices for more details on remote installation

To view installation logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- · Click the name of the Windows device then select the 'Logs' tab
- Click 'Installation Logs'




Installation Logs - Table of Column Descriptions		
Column Heading	Description	
Procedure Name	The possible value is 'On-demand installation'. Install apps from 'Application Store' > 'Windows Application Store'.	
Started At	The date and time when the installation commenced.	
Started By	The administrator who started the remote installation. • Click the name/email address to view the details of the admin	
Launch Type	Indicates whether the procedure was scheduled or run manually. The possible value is 'On Demand'	



Finished At	The date and time when the installation was completed.
Status	Whether the remote installation was successful, in progress, or failed.
Last Status Update	The date and time when the information was last refreshed.
Details	 Click the 'Details' link to view a log of the procedure's execution. See explanation of View Details of Installation Logs given below.

View Details of Installation Logs

• Click the 'Details' link to view details about a procedure's execution:



The 'Log Details' pane shows the date and time at which successive stages in the installation were run, their success status and results.

Installation Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Time	Date and time each stage in the installation was run.	



Status	Whether the execution was successful or not.
Additional Information	Show current installation progress.
	If the install fails, this area shows the reason.


View Uninstall Logs

- The uninstallation tab contains logs about the removal of third party applications from devices.

 There are two ways in which you can remotely uninstall applications:
 - i. 'Device Details' interface You can uninstall selected application(s) from an individual device.
 - Click 'Devices' > 'Device List' > 'Device Management'
 - Click the name of a Windows device and select the 'Software Inventory' tab
 - Select the applications and click 'Uninstall Selected Application' on the top
 - See View and Manage Applications Installed on a Device for more details
 - ii. 'Global Software Inventory' interface You can uninstall selected application(s) from all managed devices on which the are currently installed.
 - Click 'Applications' > 'Global Software Inventory'
 - Select the application to be uninstalled
 - Click 'Uninstall' on the top
 - See View and Manage Applications Installed on Windows Devices for more details

To view uninstallation logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab
 - Select a company or a group to view just their devices
 Or
 - · Select 'Show all' to view every device enrolled to EM
- Click the name of the Windows device then select the 'Logs' tab
- Click 'Uninstallation Logs'




Uninstallation Logs - Table of Column Descriptions	
Column Heading	Description
Procedure Name	The possible value is 'On-demand Uninstallation'. You can uninstall apps from devices by two ways explained above.
Started At	The date and time when the uninstallation commenced.



Ctantad D.	The administrator who started the remote wainstallation
Started By	The administrator who started the remote uninstallation.
	Click the name/email address to view the details of the administrator.
Launch Type	Indicates whether the procedure was scheduled or run manually. The possible value is 'On Demand'
Finished At	The date and time when the uninstallation was completed.
Status	Whether the remote uninstallation was successful, in progress, or failed.
Last Status Update	The date and time when the information was last refreshed.
Details	Click the 'Details' link to view a log of the procedure's execution.
	See explanation of View Details of Uninstallation Logs given below.

View Details of Uninstallation Logs

Click the 'Details' link to view details about a remote uninstallation execution:



The 'Log Details' pane shows the date and time at which successive stages in the uninstallation were run, their success status and results.

Installation Log Details - 'Statuses' tab - Table of Column Descriptions	
Column Heading	Description
Time	Date and time each stage in the uninstallation was run.
Status	Whether the execution was successful or not.
Additional Information	Show current installation progress. • If the uninstallation failed, this area shows the reason.




View Discovery Logs

- A managed endpoint can be used as a probe device which runs discovery scans on a network.
- If a device has been used as a probe, then the discovery logs tab shows any scans run from it.
- See Create and Run Network Discovery Tasks if you want to learn more about discovery scans and probe devices.

View discovery logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click the name of the Windows device then select the 'Logs' tab
- Click 'Discovery Logs'




Installation Logs - Table of Column Descriptions	
Column Heading	Description
Discovery Name	The label of the discovery scan task. • Click the name to view task details
	See Create and Run Network Discovery Tasks to read more about discovery tasks and probe devices.
Status	Whether the scan is progress, queued or finished.
Started At	Date and time the scan commenced on the network.
Started By	The email address of the admin who launched the scan.
	 Click the email address to view the details of the admin. See View User Details if you need help with this.
Finished At	The date and time the scan ended.
Launch Type	How the scan was started. For example, 'On Demand' means it was manually started by an admin.
Type of Discovery	Can be SNMP scan or network (IP) scan.



Details	•	View more information about the scan. For example, this will tell you the number of devices found and their names.
	•	See View Details of a Discovery Scan below.

View Details of a Discovery Scan

Click 'Details' in the row of a scan to view additional information:



- 'Click here' link View devices found by the scan.
 - See Discovered Devices for more details

5.2.3. Manage Mac OS Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Mac OS device


- The MAC details page shows operating system and security information about the device.
- The screen also lets you manage device profiles, view quarantined files, remotely install packages, configure group membership, and view device logs.

Note: If you haven't done so already, you should first enroll users then enroll their devices.

View and manage Mac OS devices

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group in the middle column to view only their devices OR
 - · Select 'Show all' to view every device added to EM
- Click the name of any Mac OS device to open its details page:






Click the following links to read more about each tab:

- Device Name The device label. You can change this as per your preferences.
- **Summary** General information about the device, including operating system, network details and security configuration.
- Installed Apps A list of applications currently installed on the device, along with their versions.
- Antivirus Shows all quarantined files on the device over time, and the actions taken by the user/ Endpoint Manager in response.
- Associated Profiles Lists all profiles active on the device.
- Package Installation State Programs that have been installed on the device via Endpoint Manager.
- **Groups** Device groups to which the endpoint belongs. You can manage group membership from here.
- Logs View events recorded on the device.
 - Alert Logs Alerts generated because of a breach of monitoring conditions or because of a procedure deployment.
 - Monitoring Logs Monitoring rules can be added to an EM policy to observe resource usage on a
 device. For example, you may wish to create a log entry if CPU usage goes above 75% for a certain
 period of time.
 - Procedure Logs Results or procedures run manually or automatically by a profile active on the device

You can use the controls along the top to run remote tasks on the device:





- Manage Profiles Add or remove device configuration profiles.
- Remote Control Establish a remote desktop connection to an endpoint.
- Install Mac OS Packages Remotely install Comodo Client Security (CCS) for Mac package.
- Refresh Device Information Contacts the device and updates displayed information.
- Wipe / Corporate Delete data stored on the device if the device is lost or stolen.
- Lock/Unlock Mac OS Remotely lock or unlock the device if it is lost, misplaced or stolen.
- Delete Device Deletes the device from Endpoint Manager.
- Owner Change the user with whom the device is associated. You can also change the type of device to corporate or personal.


5.2.3.1. View and Edit Mac OS Device Name

- Enrolled devices are listed by the name assigned to them by their owner.
- If no name was assigned then the actual device name or model number will be used.
- Admins can change the device name as required. Name changes apply only in Endpoint Manager. The name will not change on the endpoint itself.
- 'Allow Auto Rename of Device Custom Name' if enabled then the custom name is replaced by the device name/model number at the next sync. Disable this option if you want to retain the custom name.


Change a device name

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click on any Mac OS device then select the 'Device Name' tab





- Custom device name The current device label.
- Allow auto rename of device custom name Enabled The device's real name will automatically replace the custom name in this list during the next sync.
 - Disabled the custom name is kept in EM
- Click the 'Edit' button at the right to change the name of the device.



- Enter the new name in the 'Custom Device Name' field
- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name
 in the list. If this is enabled, the custom name will be automatically replaced with the device's name
 or model number during the next sync with the EM communication client on the device.
- Click 'Save' for your changes to take effect.

The device is listed with its new name.

 To restore the name of the device as it was at the time of enrollment, click 'Edit' from the 'Device Name' interface, click 'Restore' at the right and click 'Save'.


5.2.3.2. Summary Information of Mac Device

The summary tab shows the device OS, network connection, security configuration and more.

View device summary

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group to view just their devices
 Or
 - Select 'Show all' to view every device add to EM
- Click on any Mac OS device then select the 'Summary' tab (if not already open).






- **Device Summary** Device name, user, type, model, last sync time wit the client, whether or not MDM profile is installed, device ownership status and more.
- OS Summary Details about the operating system of the device, including version and build.
- Network Summary MAC addresses of the device for connection through Bluetooth, WiFi and Ethernet.
- Security Products Info Details about Comodo Client Security (CCS) for Mac on the device, including version number, database version and update status.

5.2.3.3. View Installed Applications

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Mac OS device > 'Installed Apps'
The installed apps tab shows all applications installed on the device.

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any Mac OS device then select the 'Installed Apps' tab





Column Heading	Description
Application	 The name of the software. Click the name of the application to view all Mac devices on which the app is installed. See Manage Devices for more details.
Package	The source of the application. The Mac OS package from which the application was installed.
Version	The version number of the application.

- · Click any column header to sort the items in order of entries in that column.
- Click the funnel icon on the right to search for specific item(s).
- To display all the items again, remove / deselect the search key from filter and click 'OK'.

5.2.3.4. View Quarantined Files

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Mac OS device > 'Antivirus'

- The 'Antivirus' tab shows all files currently quarantined on the device.
- Endpoint Manager periodically synchronizes with managed devices to collect and show history of all files in different times on devices.
- You can view this at 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files'.

View quarantined items on a device


Click 'Devices' > 'Device List'



- Click the 'Device Management' tab
 - Select a company or a group to view their devices

Or

- · Select 'Show all' on the left to view every device enrolled to EM
- Click the name of a MAC device then click the 'Antivirus' tab



Click 'Request quarantined files' on the right to manually refresh the list.

The table columns and the options are similar to Quarantined Files interface of a Windows device details interface. See **Quarantined Files** in **View Antivirus Scan History** for description of this interface.

5.2.3.5. View and Manage Profiles Associated with a Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Mac device > 'Associated profiles'


- The 'Associated Profiles' tab displays a list of all currently active configuration profiles on the device. A
 profile may have been applied to a device because:
 - it is a default profile for the device's operating system.
 - the profile was specifically applied to the device
 - the profile was applied to the device's user. The profile is then applied to all devices that the user owns.
 - the device is a member of a device group. The device inherits all profiles applied to the device group.
 - the device owner is a member of a user group. The device inherits all profiles applied to the user group.

See Profiles for Mac OS Devices for more details on configuration profiles.

View and manage profiles associated with a device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any Mac OS device then select the 'Associated Profiles' tab





Associated Profiles - Column Descriptions	
Column Heading	Description
Name	The profile label. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Source Associated	 How the profile was applied to the device. Profiles can be applied to a device in different ways: Profile was directly applied to a device. See View and Manage Profiles Associated with a Device for more details Profile was applied to a user. These profiles are in-turn deployed to all devices belonging to the user. See Assign Configuration Profiles to User Devices for more details Profile was applied to a user group. These profiles are deployed to all devices owned by group members. See Assign Configuration Profile to a User Group for more details Profile was applied to a device group. These profiles are deployed to all devices in the group. See Assign Configuration Profile to a Device Group for more details Click the source to view and manage profiles associated with that source.
Information about Association	Whether the profile has been successfully applied to the device or is pending.

• Click the 'Name' column header to sort the items in the alphabetical order of the names of the items.

Add or Remove Profiles

Click 'Manage Profiles' to add or remove profiles. See View and Manage Profiles Associated with a
 Device for a full overview of this interface.




5.2.3.6. View Mac OS Packages Installed on a Device through Endpoint Manager

Endpoint Manager lets you remotely install packages on managed Mac devices.

Note: Currently only CCS can be remotely installed on Mac OS devices. Support for other packages is coming in future versions.


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any Mac OS device then select the 'Packages Installation State' tab



MSI Installation State - Table of Column Descriptions	
Column Heading	Description
Name	The label of the installation package.
State	Whether the installation was successful or not
Created	The date and time at which the installation command was sent.

- Click any column header to sort items in ascending/descending order of the entries in that column.
- Select an entry and click 'Delete mac OS Package Installation State' to remove it from the list.





· Click 'Confirm' to remove the entry from the list


Note - the entry will be removed from the list but the package will not be uninstalled from the device.

More reading - see Remotely Install Packages on Mac OS Devices.

5.2.3.7. View and Manage Device Group Memberships

Device groups let you deploy policies to multiple devices at once. This section lets you view group memberships for the device and add/remove it from groups.

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of a Mac OS device then select 'the 'Groups' tab




- The screen lists all groups of which the device is a member.
- All profiles which apply to the group are in-turn applied to the endpoint. See Assign Profiles to a Device Group if you want to learn more about this.



Column Heading	Description
Group	The group label. Click the group name to view and edit group details. See Edit a Device Group for more details.
Customer	The name of the company for which the group was created.
Number of Devices	The total count of devices in the group. Click the number to view and edit group details. See Edit a Device Group for more details.
Created By	Name of the admin who created the group. Click the name to view the admin's details. See View the Details of a User for more details.
Created	The date and time at which the group was created.

Add the device to a new group

- · Click 'Add to Group'
- Start typing the name of the target group and choose from the suggestions.




- You can add the device to multiple groups. Simply repeat the process to add the device to other groups.
- Click 'Add'.

Remove the device from a group



Select the group from the list and click 'Remove from Group'.



• Click 'Confirm' to remove the device from the selected groups.

Note - Any group profiles will are also removed from the device.

5.2.3.8. View Mac Device Logs

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Mac device > 'Logs'


- The 'Logs' tab shows all events that occurred on a specific device.
- This contrasts to 'Dashboard' > 'Audit Logs', which shows events on all devices.

View device logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices OR
 - Select 'Show all' to view every device enrolled to EM
- Click the name of a Mac OS device
- Click the 'Logs' tab

ITarian Endpoint Manager - Administrator Guide





There are three types of logs, each shown on a different tab. Each row on these tabs is a specific event.

Click on the following for details about each type of log:


- Alert Logs
- Monitor Logs
- Procedure Logs
- Alert Logs

A record of all events where an alert was generated on the endpoint. For example, logs are generated a breach of monitoring conditions.

View alert logs

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- · Click the name of the Mac OS device then select the 'Logs' tab
- Select 'Alert Logs'





Alert Logs - Table of Column Descriptions		
Column Heading	Description	
Alert Name	The alert template used in the event.	
	 An alert template is just a collection of settings that determines alert recipients, information included, priority etc. The template does not specify the condition under which the alert is generated. 	
	The 'Trigger Name' is the actual monitor that generated the alert.	
	 In the standard workflow, all monitors have the 'Default Alert' template applied to them. Click 'Configuration' > 'Templates' > 'Alerts' > 'Default Alert' to view the settings in the default template. 	
	 You can also create your own alert templates. See 'Manage Alerts' for more details. 	
	Click the alert name to view and configure its settings.	
Trigger Name	The monitor that generated the alert.	
	 You can create a monitor to watch activity on a device and alert you if certain conditions are met. 	
	For example, 'alert me if disk usage exceeds 90%' on a device.	
	Click the monitor name to view and configure its settings	
	See Manage Monitors for more details.	
Trigger Type	The possible value is 'Monitor'	
Hits Count (24 H Period)	The number of times this condition was triggered in the past 24 hours.	

Monitor Logs


- Monitors are scripts which keep track of specific items on a device. For example, you may set a monitor to track disk usage does not exceed a certain percentage.
- Monitors can be added to the 'Monitoring' section of a configuration profile
- Monitoring logs are shown for the past 24 hours.



- See Monitors for Mac OS Devices for help to create monitors.
- See Monitor settings for Mac OS Profile for help to add monitors to profiles

View monitoring logs

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- · Click the name of the Mac OS device then select the 'Logs' tab
- Click 'Monitoring Logs'




Monitoring Logs - Table of Column Descriptions	
Column Heading	Description
Monitor Name	The monitor that was triggered to create the log. Click the name to view and manage the conditions of the monitor. See Manage Monitors for more details.
Status	Whether or not the monitor is currently active on the device.
Hit Count	The number of times the monitored condition was breached in the last 24 hours.
Last Hit Time	Date and time the condition was last broken.
Last Update Time	Date and time when the information was last refreshed.
Details	 Click the 'Details' link to view a log of the breach events. See View Details of Monitoring Logs (given below) for more information.

Monitor Details

Click the 'Details' link to view event information and the conditions of a monitor:





Details are shown under three tabs:

Logs - The date and time when the event occurred. Also shows details about the monitoring rule that detected the event.

Monitoring Log Details - 'Logs' tab - Table of Column Descriptions		
Column Heading	Description	
Time	Date and time of the event.	
Status	The current status of the monitored condition on the device.	
Additional Information	Details on the condition monitored and the breach	

Tickets - Shows any service desk tickets created by the events.






Monitoring Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	

Statuses - Shows the current status of all conditions monitored on the device.



Monitoring Log Details - 'Statuses' tab - Table of Column Descriptions	
Column Heading	Description
Condition Type	The observed parameter of the monitor. Click the condition to view the details of the monitored parameter and configured thresholds. An example is shown below:






Procedure Logs

The procedures log tab shows scripts that were manually run on Mac devices as well as those run automatically via a profile. For help to create and run script procedures, see **Manage Procedures**.

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - · Select 'Show all' to view every device enrolled to EM
- · Click the name of the Mac device then select the 'Logs' tab
- Click 'Procedures Logs'



Procedure Logs - Table of Column Descriptions		
Column Heading	Description	
Procedure Name	The label of the script procedure that was run on the device. • Click the procedure name to view the parameters of the script.	

ITarian Endpoint Manager - Administrator Guide




	See Manage Procedures for more details.	
Started At	The date and time when the procedure commenced.	
Started By	Who or what launched the procedure.	
	 A profile name will be shown here if the procedure was scheduled in a profile which is active on the device. 	
	 An admins name or email address will be shown if the procedure was run manually. Click the name/email address to view the details of the admin. 	
Launch Type	Whether the procedure was scheduled or run manually.	
Executed By	The user account type used by Endpoint Manager to run the procedure.	
Finished At	The date and time when the procedure was completed.	
Status	Whether the script was successful or not.	
	You can configure an alert if a procedure deployment fails. See 'Manage Procedures' for help with this.	
Last Status Update	The date and time when the information was last updated.	
Details	Click the 'Details' link to view a log of the procedure's execution.	
	See the explanation of View Details of Script Procedure Logs given below.	

View Script Procedure Log details

• Click the 'Details' link to view details about a procedure's execution:





The details are displayed under two tabs:

Statuses - The date and time at which successive stages in the procedure were run, their success status and results.

Script Procedure Log Details - 'Statuses' tab - Table of Column Descriptions		
Column Heading	Description	
Time	The date and time of the procedure execution.	
Status	Whether the execution was successful or not.	
Additional Information	Provides details on the execution: If successful, displays the results of the procedure execution If failed, displays the reason for not running the procedure	

Tickets - Displays tickets raised for any failed procedures.





Script Procedure Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	

5.2.4. Manage Linux Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of a Linux device


The details page of a Linux device shows OS and software data, security info from Comodo Client Security and other information. The screen also lets you manage endpoint profiles, remotely install Linux packages and configure group membership.

Note: If you haven't done so already, you should first enroll users then enroll their devices.

View and manage a Linux device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group in the middle column to view only their devices
 Or
 - · Select 'Show all' to view every device added to EM
- Click the name of any Linux device to open its 'Device Details' pane:






Device details are shown in six tabs:

- Device Name The device label. You can change this as per your preferences. See View and Edit Linux
 Device Name for more details.
- Summary General details of the device, including device information, OS details and security configuration. See View Summary Information of Linux Device for more details.
- Networks Information about the network to which the device is connected, MAC address, IP address, and more. See View Network Information of a Linux Device for more details.



- Associated Profiles Profiles deployed on the device. See View and Manage Profiles Associated with a Linux Device for more details.
- Packages Installation State Linux packages that have been installed on the device via Endpoint
 Manager. See View Linux Packages Installed on a Device through Endpoint Manager for more details.
- Groups Device groups to which the device belongs. You can manage group membership from here. See
 View and Manage Device Group Memberships for more details

Administrators can remotely perform various tasks on the device using the options at the top of the interface.



- Manage Profiles Add or remove device profiles. See Assign Configuration Profiles to Selected Devices for more details.
- Install Linux Packages Remotely install Comodo Client Security for Linux package. See Remotely Install Packages on Linux Devices for more details.
- Refresh Device Information Contacts the device and updates displayed information. See Update
 Device Information for more details.
- Owner Change the user with whom the device is associated. You can also change the type of device to corporate or personal. See Change a Device's Owner and Change the Ownership Status of a Device for more details.
- Delete Device Removes the device from Endpoint Manager. See Remove a Device for more details.


5.2.4.1. View and Edit Linux Device Name

- Enrolled devices are listed by the name assigned to them by their owner.
- If no name was assigned then the actual device name or model number is used.
- Admins can change the device name as required. Name changes apply only in Endpoint Manager. The name will not change on the endpoint itself.
- 'Allow Auto Rename of Device Custom Name' If enabled, the custom name will be replaced by the device name/model number during the next sync. Disable this option if you want to keep the custom name.


Change a device name

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click on any Linux device then select the 'Device Name' tab





- Custom device name The current name of the device.
- Allow auto rename of device custom name Enabled The device's real name will automatically
 replace the custom name in this list during the next sync. Disabled the custom name is kept in EM
- Click the 'Edit' button at the right to change the name of the device.



• Enter the new name in the 'Custom Device Name' field

ITarian Endpoint Manager - Administrator Guide



- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name
 in the list. If this is enabled, the custom name will be automatically replaced with the original
 device's name or model number during the next sync with the communication client on the device.
- Click 'Save' for your changes to take effect.

The device will be listed with its new name.

To restore the name of the device as it was at the time of enrollment, click 'Edit' from the 'Device Name' interface, click 'Restore' at the right of the 'Custom device name field' and click 'Save'.


5.2.4.2. Summary Information of Linux Device

The 'Summary' tab contains information about the device, its operating system and Comodo Client Security (CCS) version.

View the device summary

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any Linux device then select the 'Summary' tab (if it is not already open).





- Device Summary Device name, user, type, model, last sync time with the client, device ownership status
 and more.
- OS Summary Details about the operating system of the device, including version and build.
- Security Products Info Details about Comodo Client Security (CCS) on the device, including version number, database version and update status.

5.2.4.3. View Network Information of a Linux Device


- The 'Networks' tab shows information about the networks to which the device is connected. This includes the MAC address of the device and more.
- Each network is shown in a separate box

View a device's network details

• Click 'Devices' > 'Device List'



- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- · Click on any Linux device then select the 'Networks' tab



5.2.4.4. View and Manage Profiles Associated with a Linux Device

The 'Associated Profiles' tab lists all configuration profiles currently active on an endpoint. A profile may have been applied to a device because:

- It is a default profile
- · It was specifically applied to the device
- It was specifically applied to the user of the device
- Because the device belongs to a device group
- Because the user of the device belongs to a user group

See Profiles for Linux Devices for more details on configuration profiles

View and manage profiles associated with a device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or

ITarian Endpoint Manager - Administrator Guide



- Select 'Show all' to view every device added to EM
- Click on any Linux device then select the 'Associated Profiles' tab

Joe Linux Owner: Herald						
	F	S	2 8,	⊑©		
Manage Profiles	Install Linux Packages	Refresh Device Information	Owner	Delete Dev	rice	
Device Name	Summary	Networks	Associated	Profiles	Packages Installation State	Groups
NAME	\$	SOURCE ASSOCIATE	ED.	II	NFORMATION ABOUT ASSOCIATION	DN
For Joe	(Owner		S	Successfully processed	
New Linux	[Device Group: First Li	nux Group	P	ending	
Second Linux Pro	ofile [Device		S	Successfully processed	
First Linux Profile	e [Device		S	Successfully processed	

Associated Profiles - Column Descriptions			
Column Heading	Description		
Name	The profile label. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.		
Source Associated	 How the profile was applied to the device. Profiles can be applied to a device in different ways: Profile was directly applied to a device. See View and Manage Profiles Associated with a Device for more details Profile was applied to a user. These profiles are in-turn deployed to all devices belonging to the user. See Assign Configuration Profiles to a Users' Devices for more details Profile was applied to a user group. These profiles are deployed to all devices owned by group members. See Assign Configuration Profile to a User Group for more details Profile was applied to a device group. These profiles are deployed to all devices in the group. See Assign Configuration Profile to a Device Group for more details Click the source to view and manage profiles associated with that source. 		
Information about Association	Whether the profile has been successfully applied to the device or is pending.		

Click the 'Name' column header to sort the items in the alphabetical order of the names of the items




Click the 'Manage Profiles' button to add or remove profiles. See **View and Manage Profiles Associated with a Device** for a full overview of this interface.

5.2.4.5. View Linux Packages Installed on a Device through Endpoint Manager

Endpoint Manager lets you remotely install packages on managed Linux endpoints.

View Linux packages installed on a device


- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any Linux device
- Click the 'Packages Installation State' tab:



Package Installation State - Table of Column Descriptions		
Column Heading	Description	
Name	The URL/filename of the package.	
State	Whether the installation was successful or not	
Created	The date and time at which the installation command was sent.	

- Click any column header to sort items in ascending/descending order of the entries in that column.
- Select an entry and click 'Delete Linux Package Installation State' to remove it from the list.





· Click 'Confirm' to remove the file from the list

Note - the entry will be removed from the list but the package will not be uninstalled from the device.

More reading - see Remotely Install Packages on Linux Devices.


5.2.4.6. View and Manage Device Group Memberships

• Device groups let you deploy policies to multiple devices at once.

Manage device group membership

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of a Linux device then select the 'Groups' tab:






- The interface lists all groups of which the device is a member.
- Group profiles are applied to all endpoints in the group.
 - See Assign Configuration Profiles to a Device Group if you want to learn more about this process.

Device Groups - Table of Column Descriptions		
Column Heading	Description	
Group	The group label. Click the group name to view and edit group details. See Edit a Device Group for more details.	
Customer	The name of the company for which the group was created.	
Number of Devices	The total count of devices in the group. Click the number to view and edit group details. See Edit a Device Group for more details.	
Created By	Name of the admin who created the group. Click the name to view the admin's details. See View the Details of a User for more details.	
Created	The date and time at which the group was created.	

Add a device to a new group

- · Click the 'Add to Group' button
- Select the group to which you want to add the device:






- Start typing the name of the group to see a list of suggestions.
- Repeat the process to add the device to other groups.
- Click the 'Add' button.

The device will be added to the group.

Remove a device from a group

- Select the groups from which you want to remove the device
- Click the 'Remove from Group(s)' button:



ITarian Endpoint Manager - Administrator Guide



Click 'Confirm' to remove the device from the selected groups.

Note - Any group profiles will also be removed from the device.

5.2.5. Manage Android Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device

- The device details page lets you view hardware/software details, manage profiles and manage installed apps.
- You can also send messages to or sound an alarm on the device, remotely lock the device, track device location and more.


Note: If you haven't done so already, you should first enroll users then enroll their devices.



View and manage an individual device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of any Android device to open the 'Device Details' pane:






The device details screen has seven tabs:

- Device Name Device label. Click the 'Edit' button if you wish to change the device name. See View and Edit Device Name for more details.
- **Summary** General information about the device. Includes basic device information, operating system details, network details and security configuration. See **View Summary Information** for more details.
- Installed apps Details of applications installed on the device. You can remotely block/release apps or uninstall applications. See Manage Installed Applications for more details.



- Associated Profiles Profiles which have been deployed to the device. You can add new profiles or remove existing profiles on the device. See View and Manage Profiles Associated with a Device for more details.
- Sneak Peek Pictures captured by the 'Sneak Peek' feature of Endpoint Manager. The 'Sneak Peek' feature photographs the person holding the device if they enter the wrong passcode too many times. You must enable sneak peek on a profile to use the feature. See View Sneak Peek Pictures to Locate Lost Devices for more details.
- Last Known Location The map location of the device when it last connected to Endpoint Manager. See
 View the Location of the Device for more details.
- **Groups** Shows all groups of which the Android device is a member. You can manage group membership from this tab. See **View and Manage Device Group Memberships** for more details.

Device tasks are shown along the top of the interface:



- Manage Profiles Add or remove device profiles. See Assign Configuration Profiles to Selected Devices for more details.
- Siren Sound an alarm on the device to locate it. See Generate an Alarm on Android Devices for more details.
- Send Message Send a text message to the user. See Send Text Messages to Mobile Devices for more details.
- Refresh Device Information Obtain updated details from the device. See Update Device Information for more details.
- Wipe / Corporate Delete all data stored in the device if it is lost or stolen. See Wipe Selected Mobile and Mac Devices for more details.
- Passcode Create a new screen lock passcode for selected devices. You can also remotely lock or unlock
 the device. See Set / Reset Screen Lock Password for Mobile Devices and Remotely Lock Mobile and
 Mac OS Devices for more details.
- **Delete Device** Remove the device from Endpoint Manager. See **Remove a Device** for more details.
- Owner Change the user with whom the device is associated. You can also change the type of device to corporate or personal. See Change a Device's Owner and Change the Ownership Status of a Device for more details.

5.2.5.1. View and Edit Device Name


Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Device Name'

- Enrolled devices are listed by the name assigned to them by their owner.
- If no name was assigned then the actual device name or model number is used.
- Admins can change the device name according to their preferences. Name changes apply only in Endpoint Manager. The name will not change on the device itself.
- 'Allow Auto Rename of Device Custom Name' If enabled, the custom name will be replaced automatically by the device name/model number during the next sync.

Change the device's name




- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' on the left to view every device enrolled to EM
- Click on any Android device then select the 'Device Name' tab



Custom device name - The current name of the device.

Allow auto rename of device custom name - Indicates whether the device's name will automatically replace the custom name in the list during the next sync with communication client.

Click the 'Edit' button at the right to change the name of the device.





- Enter the new name in the 'Custom Device Name' field
- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name
 in the list. If this is enabled, the custom name will be automatically replaced with the device's name
 or model number during the next sync with the communication client on the device.
- Click 'Save' for your changes to take effect.

The device will be listed with its new name.

 Click 'Edit' in the 'Device Name' interface, click 'Restore' at the right and click 'Save' to restore the name of the device as it was at the time of enrollment.

5.2.5.2. View Summary Information

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Summary' (if it is not open already)

 The 'Summary' tab shows general information about the device, its operating system, network and security status.

View device information summary


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or a group to view just their devices

Or

- · Select 'Show all' to view every device added to EM
- Click on any Android device then open the 'Summary' tab (if it is not already open).









- Device Summary Provides device details such as brand, model, International Mobile Equipment Identification (IMEI) number, last connection time, device battery level (at last connection time) and Ownership type of the device.
- **OS Summary** Provides details about the device's Operating System, including version number, memory usage and available internal and external storage space.
- Network Summary Provides details about the mobile and WiFi networks to which the device is connected, including the MAC addresses of the device for connection through Bluetooth and WiFi.
- Security Summary Provides details about important security settings of the device. For Android devices, details from Comodo Mobile Security (CMS) like Virus Signature Database version and update status are displayed.

5.2.5.3. Manage Installed Applications

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Installed Apps'


- The 'Installed Apps' tab shows all applications installed on a device with their package names and version numbers.
- You can block, unblock or remove apps as required.
- You can also see which other devices have the same applications installed.

Manage installed apps

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices

 Or
 - Select 'Show all' to view every device added to EM
- Click on any Android device then open the 'Installed Apps' tab





Installed Apps - Column Descriptions	
Column Heading	Description
Name	The label of the application. Click the application name to view all devices which have this app installed. This is useful if you want to apply an action to all devices which have a certain app installed.
Package	The application ID on the vendor app store. For example, 'cn.wps.moffice_i18n' can be found at https://play.google.com/store/apps/details?id=cn.wps.moffice_i18n.
Version	The version number of the application.
Verdict	Whether the application is allowed, blocked or blacklisted by EM.

• The list of apps on a device is updated in Endpoint Manager every 24 hrs. To refresh the list immediately, click 'Update Application List'.


Sorting and Filtering Options

- · Click any column header to sort the items in alphabetical order.
- Click the funnel icon at the right to open the filter interface:





 You can filter/search specific items based on app name, package or version. To start, enter the search criteria in full or part in the respective search field and click 'Apply'



 Use the check-boxes under 'Verdict' if you wish to see only allowed or only blocked applications in the search results.

Block Unwanted Apps

You can remotely block apps that are identified as malicious, suspicious or junk. The app is not uninstalled from the device but not allowed to run. Blocked apps can be released at a later date and allowed to run.

Block selected apps

• Choose the app(s) that you wish to block and simply click the 'Block' button.


The verdict of the app(s) will change to 'Blocked' and they will not be allowed to run on the device.

Release blocked apps




Select the blocked app(s) and click 'Unblock'.

The verdict of the app(s) will change to 'Allowed' and they will be allowed to run on the device.



Uninstall applications

Select the app(s) and click 'Uninstall'.



• Click 'Confirm' to uninstall the selected app(s) from the device.

5.2.5.4. View and Manage Profiles Associated with a Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Associated profiles'




- The 'Associated Profiles' tab displays a list of all currently active configuration profiles on the device. A
 profile may have been applied to a device because:
 - · It is a default profile
 - · It was specifically applied to the device
 - · It was specifically applied to the user
 - The device belongs to one or more device groups and inherited profiles from the group
 - The user belongs to one or more user groups and inherited profiles from the group

See 'Profiles for Android Devices' for more details on profiles and default profiles.

View and manage associated profiles

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - · Select 'Show all' to view every device added to EM
- · Click on any Android device then open the 'Associated Profiles' tab



Associated Profiles - Column Descriptions	
Column Heading	Description
Name	The profile label. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Source Associated	The channel through which the profile was applied to the device. Configuration profiles can be applied to a device in different ways: • Profiles can be directly applied to the device. See Assign Configuration Profiles to Selected Devices for more details. • Profiles applied to a user are deployed to all devices belonging to them. See Assign Configuration Profiles to User Devices for more details.



	 Profiles applied to a user group are deployed to all devices owned by group members. See Assign Configuration Profiles to a User Group for more details.
	 Profiles applied to a device group are deployed to all member devices in the group. See Assign Configuration Profiles to a Device Group for more details.
	Click a source to open the respective details interface.
Information about Association	The status of profile application to the device.

Add or Remove Profiles

Click 'Manage Profiles' at the top to add or remove profiles. See **Assign Configuration Profiles to Selected Devices** for more details.

5.2.5.5. View Sneak Peek Pictures to Locate Lost Devices


Click 'Devices' > 'Device List' > click the name of an Android device > 'Sneak Peek'

- Click 'Devices' > 'Device List' > click a device name > 'Sneak Peek'
- 'Sneak Peek' takes a photo of the device holder if the wrong password is entered a certain number of times.
 This helps you to recover mislaid or stolen Android devices.
- The photo is sent to Endpoint Manager along with the location and time it was taken.
- The feature can be enabled on a device profile. You can specify how many incorrect attempts should be allowed. See **Passcode** in **Profiles for Android Devices** for help to do this.
- If a front camera is not available, a photograph is taken using the rear-facing camera.

View Sneak Peek pictures

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on the name of any Android device then open the 'Sneak Peek' tab:






The page will display all Sneak Peek photographs collected by devices after a series of incorrect passcode entries:

Note: The images shown above are for illustration purposes only. The interface will actually show photographs picked-up by the device camera.

• Click on a picture to view see an enlarged view of the photograph and the location of the device at the time the photo was taken.





To remove the sneak peek picture, click the trash can icon at bottom right.



5.2.5.6. View the Location of the Device


Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Last Known Location'

- The 'Last Known Location' tab shows from where the device most recently contacted Endpoint Manager.
- You can refresh the location by clicking the 'Update' link.

View the location

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - · Select 'Show all' to view every device added to EM
- Click on the name of any Android device then open the 'Last Known Location' tab:

The location of the device is shown on a map.





The map shows the location of the device the last time it contacted EM.

Click 'Update' to view the current location of the device.


5.2.5.7. View and Manage Device Group Memberships

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an Android device > 'Groups'

- The 'Groups' tab shows all groups of which the device is a member.
- You can remove the device from a group or add it to a new group.

View and manage device group membership

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of any Android device then select the 'Groups' tab



- The interface lists all groups of which the device is a member.
- Any device group profiles will also be applied to the endpoint.

For more details about applying configuration profiles to device groups, see **Assign Configuration Profiles to a Device Group**.


Device Groups - Table of Column Descriptions	
Column Heading	Description
Group	The group label. Click the group name to view and edit group details. See Edit a Device Group for more details.
Customer	The name of the company for which the group was created.
Number of Devices	The total count of devices in the group.



	 Click the number to view and edit group details. See Edit a Device Group for more details.
Created By	Name of the admin who created the group. Click the name to view the admin's details. See View the Details of a User for more details.
Created	The date and time at which the group was created.

Add the device to a new group

· Click 'Add to Group'




- In the 'Choose Group(s)' field, start typing the name of the group to which you want to add the device. Select the desired group from the recommendations which appear.
- Repeat the process to add the device to other groups.
- · Click 'Add'.

The device is added to the group.

Remove the device from a group

Select the group from the list and click 'Remove from Group'.





Click 'Confirm' to remove the device from the group.

The device will be removed from the group. Any group configuration profiles will also be removed from the device.

5.2.6. Manage iOS Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device


- The device details page lets you view the model and OS details, manage profiles and manage installed apps.
- You can also send messages to or sound an alarm on the device, remotely lock the device, track device location and more.

Note: If you haven't done so already, you should first enroll users then enroll their devices.

View and manage an individual iOS device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of any iOS device to open the 'Device Details' pane:






The device details screen has six tabs:

- Device Name Device label. Click the 'Edit' button if you wish to change the device name. See View and Edit Device Name of an iOS device for more details.
- Summary General information about the device. Includes basic device information, operating system
 details, network details and security configuration. See View Summary Information of an iOS device for
 more details.
- Installed apps Details of applications installed on the device. See View Applications installed on an iOS Device for more details.
- Associated Profiles Profiles which have been deployed to the device. You can add new profiles or remove existing profiles on the device. See View and Manage Profiles Associated with an iOS Device for more details.
- Last Known Location The map location of the device when it last connected to Endpoint Manager. See
 View the Location of an iOS Device for more details.



 Groups - Shows all groups of which the iOS device is a member. You can manage group membership from this tab. See View and Manage Group Memberships of an iOS device for more details.

Device tasks are shown along the top of the interface:



- Manage Profiles Add or remove device profiles. See Assign Configuration Profiles to Selected Devices for more details.
- Send Message Send a text message to the user. See Send Text Messages to Mobile Devices for more details
- Refresh Device Information Obtain updated details from the device. See Update Device Information for more details.
- Wipe / Corporate Delete all data stored in the device if it is lost or stolen. See Wipe Selected Mobile and Mac Devices for more details.
- Passcode Create a new screen lock passcode for selected devices. You can also remotely lock or unlock
 the device. See Set / Reset Screen Lock Password for Mobile Devices and Remotely Lock Mobile and
 Mac OS Devices for more details.
- Send Agent Enrollment Link Forward a shortcut to the devices for enrollment of the MDM agent app on
 the device to Endpoint Manager. This is useful if the user has missed to activate the agent during device
 enrollment process. See Send Enrollment Link to iOS Devices for more details.
- Delete Device Remove the device from Endpoint Manager. See Remove a Device for more details.
- Owner Change the user with whom the device is associated. You can also change the type of device to corporate or personal. See Change a Device's Owner and Change the Ownership Status of a Device for more details.

5.2.6.1. View and Edit Device Name of an iOS Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Device Name'

- Enrolled devices are listed by the name assigned to them by their owner.
- If no name was assigned then the actual device name or model number is used.
- Admins can change the device name according to their preferences. Name changes apply only in Endpoint Manager. The name will not change on the device itself.
- 'Allow Auto Rename of Device Custom Name' If enabled, the custom name will be replaced automatically by the device name/model number during the next sync.

Change a device's name


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices

Or


Select 'Show all' on the left to view every device enrolled to EM



· Click on any iOS device then select the 'Device Name' tab



- Custom device name The current name of the device.
- Allow auto rename of device custom name Indicates whether the device's name will automatically replace the custom name in the list during the next sync with communication client.
- Click 'Edit' at the right to change the name of the device



- Enter the new name in the 'Custom Device Name' field
- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name in the
 list. If this is enabled, the custom name will be automatically replaced with the device's name or model
 number during the next sync with the communication client on the device.



Click 'Save' for your changes to take effect.

The device will be listed with its new name.

Click 'Edit' from the 'Device Name' interface, click 'Restore' at the right and click 'Save', to restore the name
as it was at the time of enrollment.

5.2.6.2. View Summary Information of an iOS Device


Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Summary' (if it is not open already)

 The 'Summary' tab shows general information about the device, its operating system, network and security status.

View device information summary

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or a group to view just their devices Or
 - Select 'Show all' to view every device added to EM
- Click on any iOS device then open the 'Summary' tab (if it is not already open).





- Device Summary Provides device details such as model, International Mobile Equipment Identification (IMEI) number, last connection time, device battery level (at last connection time) and Ownership type of the device.
- OS Summary Provides details about the device's Operating System, including version number, whether
 an iTunes account is associated with the device, whether iCloud backup is enabled and more..



- Network Summary Provides details about the mobile and WiFi networks to which the device is connected, including the MAC addresses of the device for connection through Bluetooth and WiFi.
- Security Summary Provides details about important security settings of the device.


5.2.6.3. View Applications installed on an iOS Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Installed Apps'

- The 'Installed Apps' tab shows all applications installed on a device with their package names and version numbers.
- You can also see which other devices have the same applications installed.

View installed apps

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on any iOS device then open the 'Installed Apps' tab



Column Heading	Description
Name	The label of the application.
	Click the application name to view all devices which have this app installed.
	This is useful if you want to apply an action to all devices which have a certain app



	installed.
Package	The bundle identifier of the app. This is a unique id used by Apple to identify an app.
Version	The version number of the application.
Verdict	Whether the application is allowed, blocked or blacklisted by EM.

- The list of apps on a device is updated in Endpoint Manager every 24 hrs. To refresh the list immediately, click 'Update Application List'.
- Click any column header to sort the items in alphabetical order.
- Click the funnel icon at the right to filter the list using various criteria. interface:

5.2.6.4. View and Manage Profiles Associated with an iOS Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Associated profiles'

- The 'Associated Profiles' tab displays a list of all currently active configuration profiles on an Android/iOS device. A profile may have been applied to a device because:
 - It is a default profile
 - · It was specifically applied to the device
 - It was specifically applied to the user
 - The device belongs to one or more device groups and inherited profiles from the group
 - The user belongs to one or more user groups and inherited profiles from the group

See 'Profiles for iOS Devices' for more details on profiles and default profiles.


View and manage associated profiles

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices

Or

- Select 'Show all' to view every device added to EM
- · Click on any iOS device then open the 'Associated Profiles' tab





Column Heading	Description
Name	The profile label. Click the name of a profile to open the 'Edit Profile' interface. See Edit Configuration Profiles for more details.
Source Associated	The channel through which the profile was applied to the device. Configuration profiles can be applied to a device in different ways:
	 Profiles can be directly applied to the device. See Assign Configuration Profiles to Selected Devices for more details.
	 Profiles applied to a user are deployed to all devices belonging to them. See Assign Configuration Profiles to User Devices for more details.
	 Profiles applied to a user group are deployed to all devices owned by group members. See Assign Configuration Profiles to a User Group for more details.
	 Profiles applied to a device group are deployed to all member devices in the group. See Assign Configuration Profiles to a Device Group for more details.
	Click a source to open the respective details interface.
Information about Association	The status of profile application to the device.

Add or Remove Profiles

Click 'Manage Profiles' at the top to add or remove profiles. See **Assign Configuration Profiles to Selected Devices** for more details.




5.2.6.5. View the Location of an iOS Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Last Known Location'

- The 'Last Known Location' tab shows from where the device most recently contacted Endpoint Manager.
- You can refresh the location by clicking the 'Update' link.

View the location

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click on the name of any iOS device then open the 'Last Known Location' tab:





The map shows the location of the device the last time it contacted EM.


5.2.6.6. View and Manage Group Memberships of an iOS Device

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Groups'

- The 'Groups' tab shows all groups of which the device is a member.
- You can remove the device from a group or add it to a new group.

View and manage device group membership

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of any iOS device then select the 'Groups' tab



- The interface lists all groups of which the device is a member.
- · Any device group profiles will also be applied to the endpoint.

For more details about applying configuration profiles to device groups, see **Assign Configuration Profiles to a Device Group**.

Column Heading	Description
Group	The group label. Click the group name to view and edit group details. See Edit a Device Group for more details.
Customer	The name of the company for which the group was created.
Number of Devices	The total count of devices in the group. Click the number to view and edit group details.




	See Edit a Device Group for more details.
Created By	Name of the admin who created the group.
	Click the name to view the admin's details.
	See View the Details of a User for more details.
Created	The date and time at which the group was created.

Add the device to a new group

Click 'Add to Group'

The 'Add Device to Group' dialog will appear.

• In the 'Choose Group(s)' field, start typing the name of the group to which you want to add the device. Select the desired group from the recommendations which appear.




- Repeat the process to add the device to other groups.
- · Click 'Add'.

The device will be added to the group.

Remove the device from a group

Select the group from the list and click 'Remove from Group'.





• Click 'Confirm' to remove the device from the group.

The device will be removed from the group. Any group configuration profiles will also be removed from the device.

5.2.7. View User Information

• User information tells you about the owner of a device. Details include email address and phone number.


To view the user information of a device

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM

The 'Owner' column shows the user of each device.

- Click the user's name to open the 'User Details' pane.
- Click the 'Edit' button to modify user details. For more details on this area, see 'View User Details' section.





5.2.8. Remove a Device

- Click 'Devices' > 'Device List'
- Select target devices
- Click 'Delete Device'.

Warning: Once a device is deleted from EM, all configuration profiles and apps installed by EM will also be removed from the device.

Windows Devices - You have the option to also uninstall the communication and/or security client when removing the device.

Android, iOS, Mac OS and Linux devices - Users can manually uninstall the clients and iOS profile from their device. **Instructions for uninstalling the agent/software** are available at the end of this section.


If you wish to reinstate the device in future then you need to re-enroll it. Device enrollment is explained in **Enroll User Devices for Management**.


Remove a device from Endpoint Manager

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the devices you want to remove



• Click 'Delete Device' from the options at the top. If 'Delete Device' is not available, click 'More' at top-right then 'Delete Device' from the options.






A confirmation is shown:






If you have selected Windows devices, you can choose to uninstall the communication client and/or the CCS software in the confirmation dialog:



• Click 'Confirm' to remove the device from Endpoint Manager.

Alternatively, you can remove a device from its device details interface.

- · Click 'Devices' and choose 'Device List'.
- Click on the name of the device to be removed to open the device details interface.



Click 'Delete Device' from the options at the top. If 'Delete Device' is not available here, click 'More' at the
top right and choose 'Delete Device' from the options.



Remove the communication client app from an Android device

- Navigate to 'Settings' > 'Apps' on the Android device
- Select 'Comodo Client'
- Tap the 'Uninstall' button.

The communication client app will be removed from the device.

Remove the EM profile from an iOS device

- Navigate to 'Settings' > 'General' on the iOS device
- Select 'Profile' > 'Comodo Profiles' (certificate and EM)
- Tap the 'Remove' button.

The EM profile will be removed from the device.

Remove the EM profile from Mac OS devices

- Navigate to 'Settings' > 'General' on the Mac OS endpoint.
- Select 'Profile' > 'Comodo Profiles' (certificate and Endpoint Manager)
- Click the 'Remove' button.

The Endpoint Manager profile will be removed from the device.

Remove the communication client from Linux device

- Open the console terminal
- Enter the following command:

\$ sudo systemctl stop itsm && sudo systemctl disable itsm && sudo rm -f /etc/systemd/system/itsm.service && sudo rm -rf /opt/COMODO.

5.2.9. Remote Management of Windows and Mac OS Devices

- Click 'Settings' > 'Portal Setup' > 'Extensions Management' to enable remote control for your account.
- The remote control feature lets you remotely access Windows and Mac devices to solve issues, install third
 party software, and run system maintenance.
- You can also transfer files and folders between the local and remote computers.

Remote Control

- First, install the remote control application on your admin computer:
 - Click 'Devices' > 'Bulk Installation Package'
 - Click the 'Remote Control by ITarian' tab
 - Choose the operating system of your admin machine
 - Click 'Download'
- After installation, there are two ways you can take over devices:
 - Use the standalone remote control application OR
 - Use Endpoint Manager Click 'Devices' > 'Device List' > 'Device Management' > select a device > click the 'Remote Control' button.



- For additional security, you can assign custom ports on the device to handle the remote connection. You
 can configure the ports by adding a 'Remote Control' section to the device profile.
 - See Remote Control Settings for Windows devices and Remote control Settings for Mac OS
 Profile if you want to read more about this.
- The viewer supports clip-board sharing between your computer and the managed device.
- You can also use key combinations such as 'Ctrl+Alt+Del', 'Alt+F4' and 'Ctrl+C' on the remote machine.
- You can view individual or all monitors if the target has a multi-monitor setup

See the following sections for more help:

- · Download and install the viewer
- Use the Viewer
- Transfer files and folders to / from remote computer

Download and install the viewer

- Click 'Devices' > 'Bulk Installation Package'
- Select the 'Remote Control by ITarian' tab
- · Choose the operating system of your admin machine
- Click 'Download'.
- · Install on your local machine

Tip: ITarian customers - You can also download the app from the ITarian portal.

- Login to ITarian
- · Click 'Tools' on the menu bar
- Locate the 'Remote Control by ITarian' tile
- Click 'Download'
- Install on your local machine


Use the viewer

- Once installed, you can launch the remote control viewer from your desktop
- You can also take control direct from the EM interface:
 - Click 'Devices' > 'Device List' > 'Device Management' > select a Windows / Mac OS device > Click the 'Remote Control' button.
 - Note A warning message is shown for Windows devices if you attempt remote control
 outside of a maintenance window. This is shown if you access via EM interface.


Access the remote control viewer

Double click the desktop shortcut so or the system tray icon to open the login screen:





- ITarian customers Click the 'ITarian' tab then login with your ITarian portal username and password
 - The region selector allows you to choose the ITarian hosted service closest to your location. Select the location nearest to you for the best performance / fastest connection.



- Select 'Stay Signed in' if you want the RC application to store your login credentials. The application will not ask for your credentials to login in future.
- Click 'Sign In'

ITarian Endpoint Manager - Administrator Guide



- If 'Two-Factor Authentication' is enabled for your account, then you have to enter the authentication code generated in the 'Google Authenticator' app on your mobile device.
- Two-factor authentication (2FA) is mandatory for accounts with more than 50 devices. 2FA options either via Google authenticator app or via SMS code sent to your mobile phone.
- Click here to find out how to configure two-factor login settings.


The 2FA screen shown depends on the selected method:

Google Authenticator




 Enter the code generated in the Google authenticator app and click 'Submit'

SMS Code



- · Click 'Request Verification Code'
- In the next screen, enter the code that you received in your phone, then click 'Submit'
- Stand-alone Endpoint Manager customers and Endpoint Manager admin users- Click the 'Endpoint Manager' tab then enter your Endpoint Manager URL and your login credentials. Your EM URL will use the format https://<your company name>.cmdm.comodo.com, where <your company name> is your EM company name.
 - If 'Two-Factor Authentication' is enabled for your account, then you have to enter the authentication code generated in the 'Google Authenticator' app on your mobile device. **Click here** to find out how to configure two-factor login settings.





- Select 'Stay Signed in' if you want the RC application to store your login credentials. The
 application will not ask for your credentials to login in future.
- · Click 'Sign In'

Tip: The remote control application will save your login credentials even if you forget to enable 'Stay Signed in'.



Note -EM admins only - The 'Remote Control' tool notifies you if your password is about to expire within next seven days, or already expired.

DESKTOP-IAO70M6
John


Consider changing your password
Your password will expire in 4 days. Please change your password.

Change password

Click 'Change password', if you want to change password at this time.

You will be taken to the Endpoint Manager portal to change your password.


The viewer application will open with a list of enrolled Windows / Mac OS endpoints:





Language Settings

- · Click the ellipsis button at top-right of the app
- Click 'Settings' to open language options:




- Choose the language you require from the drop-down then click 'Save Settings'. This determines the language you see in the remote control application.
 - A notification box is shown on endpoints when you take over their machine. This box states the name of the person connected and the session duration etc.
 - The notification is in the language of the operating system IF the OS is English, Russian, Spanish, German, French, Portuguese or Chinese.
 - English is used if the OS is of any other language.
 - Examples:
 - You choose 'Russian' but connect to a Spanish PC Notification is shown in Spanish.
 - You choose 'Russian' but connect to a Bulgarian PC Notification is shown in English
 - You choose 'Russian' and connect to a Russian PC Notification is shown in Russian

Proxy Server Settings

You can configure a proxy through which you want to connect to managed endpoints.



- Click the ellipsis button then 'Settings'
- Click the proxy server icon on the left of the settings page:




- Do Not Use Proxy The remote control tool will establish a direct connection to the endpoint
- Use Local Proxy Settings Use a proxy to connect to endpoints.
 - Host Enter the IP address or the hostname of your proxy server
 - Port The port on your proxy server that the remote control tool should connect to.
- Authentication If your proxy server requires authentication, enter the UN/PW here.
- Establish direct connection if proxy fails Allow the remote control tool to fallback to a direct internet connection if the proxy fails.
 - If you specify a proxy but disable direct connection, then the remote control tool will not be able to connect to endpoints if the proxy fails
 - Leave the direct connection option enabled to ensure you can access endpoints at all times
- Click 'Save Settings'

Remotely manage an endpoint

Move your mouse over an endpoint and click the remote desktop icon on the right:





The following message is shown to end-users if configured appropriately:



You have the following options:

- Take remote control of the device without permission from the user
- Ask for permission and take control if the user allows. Automatically take control if the user does not respond.
- Disable remote control entirely
- See Remote Control Settings for more details.


The following notification appears on the endpoint when you have established control:




You can configure the endpoint notification box in the 'Remote Control' section of a profile.

• Click 'Configuration Templates' > 'Profiles' > 'Add Profile Section' > 'Remote Control' You can now access the desktop of the remote computer:





- You can interact with the target device to perform tasks as required.
- Use the toolbar at the top of the interface to perform the following actions:



Full Screen - The remote desktop will cover your entire display, without the operating system's window-framing interface.


Click the same icon to exit full screen mode

Position - Click and drag the tool bar to your preferred location.

Pin - Lock or unlock the tool bar to the title bar in full screen view.


Minimize/Maximize - Show/hide tool bar options.





Actions - Send control commands to the endpoint.


- Send Ctrl + Alt + Del (Available only for Windows devices) Opens the Windows security screen. This allows you to lock the computer, log the current user out of the remote machine, change passwords, view the local task manager or shut down/restart/hibernate the machine.
- Lock Session Locks the managed endpoint.
 A password will be required to unlock the endpoint.
- Send Special Keys If enabled, allows you to send key combination commands such as Ctrl+C, Windows + R and so on.
 - The special key combinations are dependent on the operating systems of the local (admin) device and the managed remote device. See the list of available special key combinations given below.



View - Change the display size of the remote desktop. The available options are:

- **Best Fit** Automatically adjusts the screen resolution for the best visual experience.
- **Scaled** Displays the target desktop with the resolution of the admin computer
- Original Displays the target desktop at its own resolution
- Full screen Displays the remote desktop in full screen view


Multi-Screen - The multi-screen icon only appears if the target point endpoint has a multi-monitor setup. The drop-down shows all monitors connected to the endpoint and allows you to choose which to view.



- Select 'Switch Screen' to move to the next screen on the list
- Select 'All Monitors' to view all connected screens simultaneously
- Select an individual monitor to view it in stand-alone mode

Help - Shows the 'About Remote Control' dialog which shows version number and copyright information.





Available Special Key Combinations

	Managed Re	emote Device
Admin Device	Windows	Mac OS
Windows	'Windows' key is sent only to the remote device Shortcuts in combination with 'Windows' key are applied only to the remote device	'Windows'/'Command' key is sent only to the remote device. Exceptions: • Ctrl+Alt+Del • Win+L PRINT SCREEN and NUMLOCK are not sent to remote device NumPad digit keys always behave as arrow-keys on Mac OS 'Context Menu' key is sent as zero scan code and appears as key 'a'.
Mac OS	All Shortcuts with 'Windows'/'Command' key are applied to the remote device, except 'Windows'/'Command' key+Esc Command+Tab - Switches between applications F11 - Shows desktop Ctrl +Up Arrow - Shows all Windows Ctrl+Down Arrow - Shows active application Window	If Apple is keyboard used: Media buttons (e.g. PLAY, STOP, MISSION CONTROL), POWER, EJECT keys and all system shortcuts with these keys are applied only to the local device. Shortcuts with COMMAND are applied to the remote device, except 'COMMAND' key+Esc Command+Tab - Switches between applications Ctrl +Up Arrow - Shows all Windows Ctrl+Down Arrow - Shows active application Window Fn+F11 - Shows desktop



		Fn+F12 - Shows Dashboard or enable standard key in Keyboard settings
	•	f non-Apple keyboard is used:
		Shortcuts with WIN are applied to the emote device, except 'WIN' key+Esc
		Command+Tab - Switches between applications
	• (Ctrl +Up Arrow - Shows all Windows
		Ctrl+Down Arrow - Shows active application Window
	• F	-11 - Shows desktop
	• F	F12 - Shows Dashboard


- Full list of Windows keyboard shortcuts https://support.microsoft.com/en-us/help/12445/windows-keyboard-shortcuts.
- Full list of MAC keyboard shortcuts https://support.apple.com/en-us/HT201236.

5.2.9.1. Transfer Items to / from the Remote Computer


There are two ways you can manage files on remote devices:

- **Endpoint Manager** Click 'Devices' > 'Device List' > select a running Windows device > Click 'Remote Tools' > 'File Explorer'. Windows devices only.
- Remote Control application Click 'Devices' > 'Device List' > 'Device Management' > select a Windows device > Click the 'File Transfer' button. Windows and Mac devices.
- This section explains how to transfer files using the remote control app.
- Download and install the remote control app.
 - Click 'Devices' > 'Bulk Installation Package'
 - · Click the 'Remote Control by ITarian' tab
 - Choose the operating system of your admin machine
 - Click 'Download'
- Open and login to the remote control app.
- Move your mouse over an endpoint and click the file transfer icon on the right:





The interface shows the file systems of the local and remote computers in adjacent panes:



You can transfer files, create folders, rename folders and more:



- Go to the root folder of the selected drive/partition



Go one level up the file structure





- Return to the previous location




- Add current folder to favorites.
 - You can add folders you often access to favorites
 - Click the address bar to access your favorite folders.
 - See Add and manage favorites if you need more help.



Folder address bar

- Select a drive / partition then browse to the desired folder
- Use the drop-down to view recently accessed items and your favorites.
- Recent folders shows the last five folders you accessed.



Pause and resume file transfer sessions.



 See Suspend / Resume file transfer sessions if you need help with this.



- Transfer files from the local device to the remote device
 - See Transfer files / folders between the local and remote devices if you need help with this.



- Transfer files from the remote device to the local device
 - See Transfer files / folders between the local and remote devices if you need help with this.



- Remove files / folders
 - See Delete a folder / file if you need help with this.



- Create a new folder
 - See Create a folder if you need help with this.




- Rename a file / folder
 - See Edit a folder / file name if you need help with this.





- Refresh the content
- The lower pane shows the progress of your transfers. You can stop, pause or resume on-going transfers:



Column Header	Descriptions
Status	The progress of the transfer. The progress of the transfer. Statuses include 'Preparing', 'In-progress', 'Pending', 'Completed', 'Canceled', 'Paused', 'Conflict' and 'Failed'.
Source	Location of the item on the origin device.
Destination	Location to which the item is being copied.
Size	File size.
Speed	The rate of the file transfer.
Progress	Shows the transfer process in percentage.
Time	Date and time of file transfer.
Remains	Time left to complete the transfer
Controls	
世	Expand / collapse the pane.
≡ _x	Clears the transfer entries in the table.
O	Restart a canceled, paused or failed file transfer
(8)	Stop a file transfer.
0	Pause a file transfer.
Q	Search for a file/folder that was part of a transfer operation.



The file management interface lets you:

- Suspend / resume a file transfer session
- Transfer files / folders between the local and remote devices
- · Create a folder
- Edit a folder / file name
- Delete a folder / file
- Stop a file transfer
- · Restart a file transfer
- Pause / resume a file transfer
- Add folders to favorites
- Auto-close the session when all transfers are finished

Suspend / resume a file transfer session

When a file transfer session is in progress, you can pause and resume it.

Click 'Suspend Session' / 'Resume Session' button at top-right



- When you suspend a file transfer session, all individual file transfers are paused.
- Individual file transfers are resumed from where they were stopped when the session is resumed again.


File transfer sessions can be paused for a maximum of 2 hours, after which the session is terminated.

Transfer Files between the Local and Remote Device


Copy items from local computer to remote computer

- In the left pane, select the items you want to transfer from the local computer
 - Use the 'Shift' or 'Ctrl' keys to select multiple items
- In the right-pane, browse to the destination folder on the remote device
- Click 'Send' (right arrow)
- Or
- Drag-and-drop the items from the left pane to the right pane






Click 'Proceed' to at the confirmation box:



You will see the following message if the file already exists in the destination:



- Overwrite The file you are copying from your machine replaces the file in the remote device
- Keep both The file you are copying is appended with a version number. For example 'File_name(1)'


Copy items from the remote device to the local computer

- Select the items you want to copy from the remote machine in the right-hand pane
 - Use the 'Shift' or 'Ctrl' keys to select multiple items
- Browse to the local folder you want to copy them to in the left-hand pane




- Click 'Receive' (left arrow)
- Or
- Drag-and-drop the items from the right pane to the left pane

A confirmation is shown:



- · Click 'Proceed' to continue the copying operation
- You will see the following message if the file already exists in the destination:



- Overwrite The file from the remote device replaces the file on your local machine.
- Keep both The file from the remote device is appended with a version number. For example 'File_name(1)'


You can view the status of the transfer in the lower pane.

Note - You can send and receive files at the same time.

Create a Folder

Click the folder icon on the local or remote device






Enter folder name and click 'OK'

Edit a Folder / File Name


- Select a folder / file on the local or remote device
- Click the edit icon



- Update the name of the folder / file and click 'OK'
 - Alternatively, just click on an item and rename it.

Delete Folders / Files

- · Select the items you want to delete
- Click the trash can icon
- Hold the 'Shift" or 'Ctrl' keys to select multiple items





Click 'OK' to confirm

Stop a File Transfer

To stop a file transfer, select it from the status pane below and click 'Stop'



- The file transfer process is canceled
- You can restart the transfer or remove from the status list. When you start a canceled file transfer, it starts
 again from the beginning.
- Click 'Clear Logs' at the top to remove all entries

Restart a File Transfer



The transfer will start from the beginning and show as completed when done.

Pause / Resume a File Transfer

When a file transfer is in progress, select it and click 'Pause' above



- · The process will stop and show as 'Paused'
- · To resume a paused file transfer, select it and click 'Start' above






The file transfer will resume from where it was paused.

Add and manage favorites

- You can add folders you access often to your favorites for quick access
- Click the address bar to view your favorite folders.
- You can add up to five folders to favorites

Add favorites

- Browse to the folder you want to favorite. The folder path is shown in the address bar.
- Click the start icon at the left of the address bar:




· Alias Name - Enter a friendly name for the folder to easily identify it in the drop-down

ITarian Endpoint Manager - Administrator Guide



- · Local path Auto-populated with the path of the chosen folder
- · Click 'Add to Favorite'

The folder is added and available for quick access from the address bar drop-down:




- Repeat the process to add more favorites
- Note: You can add maximum of five folders to the favorites list.

Edit a favorite

• Open the favorite folder and click the star icon






- Edit the name and path as required
- · Click Save for your changes to take effect

Remove a favorite

- Open the favorite folder and click the star icon
- Click 'Delete Favorite' in the 'Edit Favorite' dialog.

Automatically terminate the file transfer session on completion of file transfers

• Click 'X' to close the app while a transfer is in-progress



• Click 'Close after transfers completed' in the warning dialog:

The session automatically terminates after all file transfers are complete.



5.2.10. Remotely Manage Folders and Files on Windows Devices

- Click 'Devices' > 'Device List'
- Select a running Windows device
- Click 'Remote Tools' > 'File Explorer'

The file explorer interface lets you remotely access files/folders on any managed Windows device.


You can transfer items to and from your local device and the remote device. You can also create / rename / delete items on the remote device.

 Note - You can also use the stand-alone remote control utility to manage files on Windows Devices. Click here find out more.

View files on a managed Windows device


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to Endpoint Manager
- Select the Windows device you want to view
- Click 'Remote Tools' > 'File Explorer':






Alternatively, click the name of the device to open 'Device Details' > select 'Remote Tools' > 'File Explorer'
from the options at the top.

Note - you might see an alert if you try to use this feature outside of a maintenance window:




• **Select user type** – Choose the user account under which you want to remotely manage files on the target device.





- Click 'Connect to Remote Host'
- Click 'Cancel Connection' to terminate immediately.
- A request message may be shown to the end-user if so configured:




- Note: You can configure these messages by adding a Remote Tool Settings section to a profile.
 Click 'Configuration Templates' > open the target profile > Click 'Add Profile Section' > 'Remote Tools'.
 You have the following choices:
 - Silent control Take control without notifying the end-user
 - Ask then allow Ask end-user permission but take control anyway if they don't respond within a set time
 - Ask then deny access Ask end-user permission but close the connection if they don't respond
 within a set time.
 - **Do not allow** Prohibit remote take-over of target devices associated with this profile.
- The following notification is shown on the endpoint during a remote session:





· The file explorer interface will open after connecting to the device:



- Use the drop-down at upper-right to choose a drive/partition on the remote device.
- · Folders and files, including hidden items, are shown in list view
 - Click the tree icon Tree at top-left to change to tree view.
- You can browse to any path by double-clicking on a folder

Tip - You can also enter a path in the field at the top of the interface.

• The controls at the top let you navigate the remote file system:

- The controls at the top let you havigate the remote life system
- Switch between tree view and list view
- Return to the previous location
- Go one level up the folder tree
- Go to the root folder of the selected drive/partition

ITarian Endpoint Manager - Administrator Guide






- Transfer files / folders from your computer to the remote device.
 - See Upload Files / Folders to Remote Device for more details.
- Copy selected files/folders to your computer from the remote device.
 - See Download Files / Folders from Remote Device to your Computer for more details.
- Create a new folder on the remote device.
 - See Create New Folder on Remote Device for more details
- <u>A</u>I
- Set a new name for a file/folder on the remote device.
 - See Rename File / Folder on Remote Device for more details.
- Delete
- Remove unwanted items from the remote device.
 - See Delete Folder / File from Remote Device for more details
- C
- Refresh the content of the current folder.

Download Items from a Remote Device

- Browse to the file / folder you want to download from the remote device
- Select the file / folder and click the download icon (right-click and select multiple files / folders):




The file will be copied to your computer.

Note: Only files of size up to 50 MB can be downloaded.

Create a New Folder on Remote Device

- Browse to the location on the remote device where you want to create the new folder
- Click the 'New folder' icon:






Enter a name for the folder and click 'Create'.

The folder will be added at the location you chose. You can upload files from your computer to the new folder. The user can also save files in the new folder.


Upload Items to a Remote Device

Click the 'Upload' icon in the control bar:





- Select 'Upload file(s)' or 'Upload folder(s)' from the drop-down
- Drag-and-drop files / folders into the box, or click inside the box to navigate to an item
- Click 'Start Uploading'




Note: The max. file / folder size you can upload is 50 MB

Rename Items on the Remote Device

Navigate to and select the item you want to rename



Click the 'Rename' icon in the control bar:




- Enter a new name for the item
- Click 'Rename'

Delete Items from the Remote Device

- · Navigate to and select the item you want to remove
- · Click the 'Delete' icon in the control bar:






· Click 'Delete' in the confirmation dialog

Note: Items deleted cannot be restored on the remote device.

Notification

The device user can view your file activities by clicking the down arrow in the notification:



Click the 'End Session' to close the remote connection.


Endpoint Manager logs your remote browsing sessions in 'Dashboard' > 'Audit Logs'. See **Audit Logs** in **The Dashboard** for more details.




5.2.11. Manage Processes on Remote Windows Devices

The process explorer lets you remotely manage running processes on any managed Windows device.

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Select the target Windows device
- Click 'Remote Tools' > 'Process Explorer':




You might see an alert if you try to access this feature outside of a maintenance window:




• **Select user type** – Choose the user account under which you want to remotely manage processes on the target device.





- Click 'Connect to Remote Host' to establish the connection.
- Click 'Cancel Connection' to terminate immediately.
- A request message is shown to end-user if configured appropriately:




- You have the following configuration options:
 - Silent control Take control without notifying the end-user
 - Ask then allow Ask end-user permission but take control anyway if they don't respond
 within a set time
 - Ask then deny access Ask end-user permission but close the connection if they don't respond within a set time
 - **Do not allow** Prohibit remote take-over of target devices associated with this profile.
 - See Remote Tools Settings for more details.
- The user is shown a notification during remote connections:





Users can click 'End session' to terminate the connection.

The 'Processes' interface for the selected device appears:



All processes that are currently running on the device are shown in the EM interface.


- Use the button at top-right to toggle between flat list and tree list views
- · Click the funnel icon to filter processes by various criteria
- Click the right arrow beside a process name to view its child-processes.
- Terminate running processes by selecting them then clicking the 'End Process' button
- 'Real Time Auto-Update' gets the latest information about a process from an endpoint every few seconds
- Start typing the process name in the search field. Matching results will be shown for the letters entered.

Processes - Column Descriptions			
Column Header	Descriptions		
App/Process	The label of the process or the parent application that triggered the process.		
Account	The user account with which the process the running. The system access privileges for the process are limited by the user account.		
PID	The process identification number.		
Status	Whether the process is running or suspended.		
CPU Memory Disk	Indicates the resource usage of the respective hardware/connection bandwidth by the process.		




Network GPU	
Start time	The date and time the process commenced.

• The following notification is shown on the endpoint while you are connected:



The endpoint user can view your activities by clicking the arrow on the left:




5.2.12. Manage Services on Remote Windows Devices


Service explorer lets you remotely view all running services on a managed Windows device.

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - · Select 'Show all' to view every device enrolled to EM
- Select the target Windows device
- Click 'Remote Tools' > 'Service Explorer':






You might see an alert if you try to access this feature outside of a maintenance window:




• **Select user type** – Choose the user account under which you want to remotely manage services on the target device.






- Click 'Connect to Remote Host' to establish the connection.
- Click 'Cancel Connection' to terminate immediately.
- A request message is shown to the end-user if notifications are enabled:



- Note. You can configure these notices in **remote tool settings**. You have the following options:
 - Silent control Take control without notifying the user
 - Ask then allow Ask user permission, but take control anyway if they don't respond within a set time
 - Ask then deny access Ask end-user permission, and close the connection if they don't respond within a set time
 - **Do not allow** Prohibit remote take-over of devices that use this profile.

Once the connection has been established, Endpoint Manager shows all running services on the remote device:






- Use the buttons above the table to start, pause and restart selected services
- Click the funnel icon to filter services by various criteria
- Search for a service by typing its name in the search field. Matching results are shown for the letters entered.
- The following notification is shown on the endpoint while you are connected:



The users can view your activities by clicking the arrow on the left:







5.2.13. Use the Command Prompt on Remote Windows Devices

The commands tool lets you run commands in the remote device's command prompt. You can also run commands on the device's Power Shell.

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- · Select the target Windows device
- Click 'Remote Tools' > 'Commands Interface':




You might see an alert if you try to access this feature outside of a maintenance window:






• **Select user type** – Choose the user account under which you want to remotely use command prompts on the target device.




- Click 'Connect to Remote Host' to establish the connection.
- Click 'Cancel Connection' to terminate immediately.
- A request message is shown to the end-user if notifications are enabled:




- Note. You can configure these notices in **remote tool settings**. You have the following options:
 - Silent control Take control without notifying the user
 - Ask then allow Ask user permission, but take control anyway if they don't respond within a set time
 - Ask then deny access Ask end-user permission, and close the connection if they don't respond
 within a set time
 - Do not allow Prohibit remote take-over of devices that use this profile.

Once the connection is established, you can see the command prompt on the remote device:





- · Run command lines as required on the remote machine
- Click 'Power Shell'




· Run Power Shell commands as required on the remote machine

The following notification is shown on the endpoint while you are connected:



The users can view your activities by clicking the arrow on the left:





5.2.14. Apply Procedures to Windows and Mac Devices

Procedures are instruction sets designed to accomplish a specific task on target devices. There are two types - script procedures and patch procedures.

- You can run procedures on single or multiple devices from the 'Devices' > 'Device List' screen.
- You can also run them on an ad-hoc basis in 'Configuration Templates' > 'Procedures', or by adding them to a profile. See Apply Procedures to Devices and Procedure Settings for details about these methods.
- Windows devices make sure **patch management** is not disabled. You can check this by looking at the 'Patch Management' section of a profile. If the profile doesn't have such a section, then patching is allowed.


Note – Currently, you can only create custom scripts procedures for MAC devices.

This section explains how to run procedures from 'Devices' > 'Device List'.

Run procedures on devices


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - · Select a company or a group to view just their devices
 - 0
 - Select 'Show all' to view every device enrolled to EM
- · Choose your target devices then click the 'Run Procedure' button





· Alternatively, click the device name then 'Run Procedure' button





- Type the name of the procedure name in the field provided.
 - If you don't know the full name of the script, try entering a single keyword to narrow the list. For example, 'Install', 'Inventory', 'Disk', 'Alert', 'Windows', 'Activate', 'Logs', 'Client', etc.
 - Click 'Configuration Templates' > 'Procedures' to view a full list of existing procedures.
- Select the procedure you want to run from the recommendations.
- Only approved procedures are listed. Only one procedure can run at a time.

Run as Local System User / **Run as Logged in user** - Choose the user account under which the procedure should run on the target devices. This option is not available for patch procedures.

Maintenance window status – A **maintenance window** is a time-slot reserved for running procedures on your managed endpoints. This section tells you how many of your current target devices are involved in a maintenance window.

- **Total number of devices outside of maintenance window** The number of target devices that are not part of a maintenance window. The procedure can run on these devices.
- Number of devices blocked by maintenance windows settings Target devices on which you cannot run the procedure because they are part of a maintenance window, and an admin has blocked procedures outside the window.
- Number of devices warned by maintenance window settings The number of devices that are part
 of a maintenance window but only have warnings enabled. You can still run the procedure on these
 devices.



• Skip devices warned by maintenance windows settings - Admins can enable a warning if somebody attempts to run a procedure outside of the window. This setting means the procedure will not run on devices which are part of a maintenance window which has warnings enabled.

Configure parameters - Script procedures only. Enter custom variables for procedure strings. You can skip this step If you want to use the default values for all parameters. For more info on default values, see **Create a Custom Procedure**.

Click the 'Run' button to execute the procedure on your target devices.

An alert is generated if the procedure fails (presuming alerts have been enabled).

You can view procedure event logs in the following places:

Device Logs interface:

- Click 'Devices' > 'Device List' > 'Device Management'
- Click the device name to open its details screen
- Windows Select the 'Logs' tab and select 'Script Logs', 'Patch Logs' or 'Third Party Patch logs' depending on the type of the procedure
- Mac Select the 'Logs' tab then 'Procedure Logs'

Procedures interface

- Click 'Configuration Templates' > 'Procedures'
- Click the name of the procedure to open the procedure configuration interface
- Select the 'Execution Log' tab
- See View Procedure Results for more details.

5.2.15. Remotely Install and Manage Packages on Windows Devices

Click 'Devices' > 'Device List' > select a target device > Click 'Install or Updates Packages' button.

The device management screen lets you install/update Comodo applications and third-party packages on Windows endpoints. You have the following options:

- Additional Comodo Packages Install Comodo Client Security (CCS) and Comodo Client Endpoint Detection and Response (EDR)
- Custom MSI/Packages Install a package of your choice by specifying the URL of the package.
- Update Additional Comodo Packages Install the latest versions of CCS, EDR and/or the communication client.
- Uninstall Additional Packages Remove Comodo Client Security (CCS) from endpoints

You can choose the following reboot options:


- Force reboot after 5, 10, 15 or 30 minutes
- Suppress the reboot entirely
- Warn the end-user about the reboot and allow them to postpone it. You can also send a message to the
 end-user.

Install MSI / EM packages

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top menu
 - Select a company or a group to view just their devices
 Or



- Select 'Show all' to view every device in EM
- · Select your target Windows devices using the check-boxes on the left
- Click 'Install or Manage Packages':



Alternatively, click on the name of the device > select 'Install or Manage Packages'.

The drop-down contains the following options:

- Install Additional Comodo Packages
- Update Additional Comodo Packages
- Install Custom MSI/Packages
- Uninstall Additional Packages

Tip: You can remotely install CCS on a Windows endpoint by clicking the shield icon 😌 next to the device name.


Install Comodo packages

- Click 'Install or Manage Packages'
- · Select 'Install Additional Comodo packages'

Note:

- The packages must be enabled in 'Extensions Management' to appear in this screen.
- Click 'Settings' > 'Portal Set-up' > 'Extensions Management' to enable or disable packages.
- See 'Manage Endpoint Manager Extensions' if you wish to read more about extensions.






- Install Comodo Client Security Available for endpoints that do not have CCS installed. CCS is
 a complete endpoint security suite which features a powerful antivirus, enterprise class firewall,
 advanced host intrusion prevention and automatic containment of unknown files. You can
 configure which CCS components are installed by applying a configuration profile.
 - Note The option to change the CCS version is only visible if enabled in portal settings. If not enabled then the 'Default version' is deployed.
- Install Comodo Client EDR Installs the Comodo Endpoint Detection and Response (EDR)
 client. EDR is a powerful event analysis tool that provides real-time monitoring and detection of
 malicious events on Windows endpoints.
 - Note -You must first have added EDR to your ITarian account. Click 'Store' in ITarian console to do so.

You need to restart the endpoint to complete the agent installation. You have the following reboot options:

• 'Force the reboot in...' - restart the end-point a certain period of time after installation. Choice of 5, 10, 15 or 30 minutes

The following message will be displayed on the device:





The device will be restarted automatically when the time period elapses.

- 'Suppress the reboot' Do not restart the machine after installation. CCS will only become fully functional after the device is restarted.
- Warn about the reboot and let users postpone it' Show an alert to the user which advises them that their computer needs to be restarted. You can enter a custom message which is shown to the user:



Users can restart the endpoint immediately by clicking 'Reboot now', or postpone it by picking a time in the 'Remind me in' drop-down.


Note: the CCS components which are active depends on the profile applied to the device. Components include firewall, antivirus, auto-containment, HIPS, Valkyrie and more.

- Click 'Devices' > 'Device List' > click device name > 'Associated Profiles', to see the profiles active on a
 device.
- Click 'Configuration Templates' > 'Profiles' to view and configure profiles
- See View and Manage Profiles Associated with a Device, Assign Configuration Profile(s) to a User's Devices, Assign Configuration Profiles to a User Group and Assign Configuration Profiles to a Device Group for help with profiles.

Update EM Packages

- Select 'Update Additional Comodo packages' from the 'Install or Manage Packages' drop-down
- The 'Update Additional Comodo packages' dialog lists all packages with available updates:






- Update Communication Client Only available for devices with an out-dated version of the communication client. As the name suggests, the communication client allows EM to send and receive updates to/from devices.
- Update Comodo Client Security Install database and software updates for CCS on the device.
 Only available for endpoints with out-dated versions of CCS.
 - Note 1 The option to choose CC and CCS versions will be available if configured in portal settings. If the option is not selected, then the default version configured in portal settings will be updated.
 - Note 2 Make sure to upgrade to a higher version. Deployment of a lower version than the
 existing client is not supported.

CCS requires the endpoint to be restarted in order for the installation to take effect. You have the following reboot options:




• **'Force the reboot in...'** - restart the end-point a certain period of time after installation. Choice of 5, 10, 15 or 30 minutes

The following message will be displayed on the device:



The device will be restarted automatically when the time period elapses.

- 'Suppress the reboot' Do not restart the machine after installation. CCS will only become fully functional after the device is restarted.
- 'Warn about the reboot and let users postpone it' Show an alert to the user which advises them that their computer needs to be restarted. You can enter a custom message which is shown to the user:




Users can restart the endpoint immediately by clicking 'Reboot now', or postpone it by picking a time in the 'Remind me in' drop-down.

Install third-party MSI packages

Choose 'Install Custom MSI/Packages' from the 'Install or Manage Packages' drop-down

The 'Install Custom MSI/Packages' dialog will appear.






- MSI/Package URL enter the location of the installer. Make sure it is from a https site. For example, https://www.hass.de/files/nodes/story/45/npp.6.8.4.installer.msi
- Command-line Options Enter any required installation switches (optional).
 - You need only enter the command here. E.g. /L or /quiet
 - Click the 'Read more' link to read more about command-line options.
- · Choose the reboot option you prefer:
 - 'Force the reboot in...' restart the end-point a certain period of time after installation. Choice of 5, 10, 15 or 30 minutes

The following message will be displayed on the device:





The device will be restarted automatically when the time period elapses.

- 'Suppress the reboot' Do not restart the machine after installation. CCS will only become fully functional after the device is restarted.
- Warn about the reboot and let users postpone it' Show an alert to the user which advises
 them that their computer needs to be restarted. You can enter a custom message which is shown
 to the user:



Users can restart the endpoint immediately by clicking 'Reboot now', or postpone it by picking a time in the 'Remind me in' drop-down.

- Maintenance window status Details of any maintenance windows in the device's profile.
 - **Total number of devices outside of maintenance window** The number of devices that are not part of a maintenance window. The installation can run on these devices.
 - Number of devices blocked by maintenance windows settings The number of devices on which you cannot run the installation because the admin has blocked installs outside of maintenance window.
 - Number of devices warned by maintenance window settings The number of devices that are part of a maintenance window and have warnings enabled. You can still install on these devices.
 - Skip devices warned by maintenance windows settings A maintenance window is a timeslot reserved for running important tasks on target devices. Admins can enable a warning if somebody attempts an installation task outside of the window. This setting will skip those devices which have been added to a maintenance window with warnings enabled.
- Click 'Install'

Uninstall Additional Packages

Click 'Install or Manage Packages' > 'Uninstall Additional Packages'

There are two ways you can remove CCS from endpoints:


CCS MSI uninstaller (preferred) – Runs a wizard to remove the security client from the endpoint.



CCS Removal tool – Downloads a special utility to force-remove the client.

You should only use the cleanup tool if you are not able to remove CCS with the MSI uninstaller.

• Make your selection then click 'Uninstall':



The target devices may need restarting to complete the removal.

The uninstall is logged as an event in 'Dashboard' > 'Audit Log'


5.2.16. Remotely Install Packages on Mac OS Devices

Admins can remotely install CCS onto Mac OS devices from the 'Device Management' interface.

Install Mac OS packages

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device in EM
- · Select the target Mac OS devices using the check-boxes on the left
- Click the 'Install or Manage Packages' button then 'Install macOS Packages'





- Choose 'Install Comodo Client Security'
- Click 'Install'
- A command is sent to install CCS on the target endpoints. The application becomes effective immediately after installation.
- You can view the installation status as follows:
 - Click 'Devices' > 'Device List'
 - Click on the name of the device > select 'Packages Installation State'.
 - See View Mac OS Packages Installed on a Device through Endpoint Manager for more details.

Note: The actual settings of CCS depends on the profile applied to the device:

- Click 'Devices' > 'Device List' > click device name > 'Associated Profiles', to see the profiles active on a device.
- Click 'Configuration Templates' > 'Profiles' to view and configure profiles

The following sections contain more help on profiles:

- View and Manage Profiles Associated with a Device
- Assign Configuration Profile(s) to a User's Devices
- Assign Configuration Profiles to Selected Devices
- Assign Configuration Profiles to a User Group
- Assign Configuration Profiles to a Device Group

5.2.17. Remotely Install Packages on Linux Devices

Admins can remotely install CCS onto Linux devices from the 'Device Management' interface.


Install Linux packages

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top menu
 - Select a company or a group to view just their devices



Or

- · Select 'Show all' to view every device in EM
- · Select the target Linux devices using the check-boxes on the left
- Click the 'Install or Manage Packages' button then 'Install Linux Packages':



- Alternatively, click on the name of the device > select 'Install Linux Packages'.
- · Choose 'Install Comodo Client Security'
- Click 'Install':
- A command is sent to install CCS on the target endpoints. The application becomes effective immediately
 after installation.
- You can view the installation status as follows:
 - Click 'Devices' > 'Device List'
 - Click on the name of the device > select 'Packages Installation State'.
 - See View Linux Packages Installed on a Device through Endpoint Manager for more details.

Note: The actual settings of CCS depends on the profile applied to the device:

- Click 'Devices' > 'Device List' > click device name > 'Associated Profiles', to see the profiles active on a
 device.
- Click 'Configuration Templates' > 'Profiles' to view and configure profiles

The following sections contain more help on profiles:

- View and Manage Profiles Associated with a Device
- Assign Configuration Profile(s) to a User's Devices
- Assign Configuration Profiles to a User Group
- Assign Configuration Profiles to a Device Group



5.2.18. Send Enrollment Link to iOS Devices

Click 'Devices' > 'Device List' > 'Device Management' > click the name of an iOS device > 'Send Agent Enrollment Link'

• Endpoint Manager lets you resend a shortcut for enrollment of the MDM agent app installed on the device, if the user has missed to complete the device enrollment process.

Background:


iOS device enrollment process involves two steps

- 1. Installation of MDM profile
- 2. Installation and enrollment of MDM agent app. The MDM agent is essential to connect the device to Endpoint Manager:

The agent app download and installation starts after the installation of the MDM profile:



- Once the agent is installed, a green 'Run after install' icon appears on the home screen
- The user needs to tap the icon in order for the agent to enroll itself to Endpoint Manager.



If the user misses to tap the icon and accidentally removed the shortcut from the home screen, you can send the shortcut from the Endpoint Manager portal. This enables the user to enroll the agent to EM.

See Enroll iOS Devices to read more.

Resend agent enrollment link


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or




- Select 'Show all' to view every device added to EM
- · Click the name of the iOS device to which you want to send the enrollment link

The device details interface opens.

· Click 'Send Agent Enrollment Link'



The command is sent to the device. The green shortcut icon for enrolling the agent to EM, reappears on the home screen of the device.




The user needs to tap the icon to enroll the agent installed on the device to Endpoint Manager.



5.2.19. Install Apps on Android/iOS Devices


- Endpoint Manager allows you to push applications to all enrolled mobile devices
- You can add apps that you intend to distribute to devices to the EM Application Store.
 - Click 'Application Store' > 'iOS Store' or 'Android Store'
 - See Application Store for help to upload apps
- The sync between the EM server and the devices takes place every 24 hours. Alternatively, you can sync immediately by clicking 'Inform Devices Now' in the Android / iOS application store interface.

Managed devices are sent notifications about newly added apps:




Users should tap the notification to open the 'Applications' page:





- All Displays all apps available for installation, including mandatory and optional apps.
- Required Apps that must be installed to comply with the EM profile applied to the device.
- Tap 'Install' to download and install the apps.

Endpoint Manager also sends notification to devices if a mandatory or recommended app is uploaded to the **Application Store**.



• Tap 'Install required apps' to install mandatory apps.

5.2.20. Generate an Alarm on Android Devices

Click 'Devices' > 'Device List' > 'Device Management' > select an Android device > 'Siren'

- If a device is mislaid, lost or stolen, you can make it sound an alarm to help locate it. The alarm will sound at full volume, even if it is set to silent mode.
- You can stop the alarm from the same interface.
- The alarm can also be generated on several devices at once to grab the attention of users.

Note: This feature is available only for Android devices.

- Generate alarm on a single device
- Generate alarm on several devices


Generate alarm on a single device



- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the device on which you want to sound an alarm

The device details interface opens.

Click 'Siren' on the top then choose 'Siren On'



You can also choose the following extras:

- Vibrate The device will vibrate along with the siren
- Make screen flash The device screen will flash intermittently along with the siren
- Click the 'Send' button to issue the alarm.
- Click 'Siren' > 'Siren Off' from the same interface, to switch off the alarm.

Tip: You can configure default siren playing duration in the Android client settings interface.


- Click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Android' > 'Client Configuration' > 'Edit' to set up default siren playing duration
- See Configure Android Client General Settings to read more about Android client settings.

Generate alarm on several devices

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or



- Select 'Show all' to view every device added to EM
- · Select the devices on which you want to sound an alarm
- Click 'Siren' at the top and choose Siren On' or click 'More...', select 'Siren' and choose 'Siren On'



You can also choose the following extras:

- Vibrate The devices will vibrate along with the siren
- Make screen flash The devices' screen will flash intermittently along with the siren
- Click the 'Send' button to issue the alarm

Stop the alarm

- Select the device(s) which should stop sounding an alarm, from the 'Device Management' interface.
- Click 'Siren' at the top and choose 'Siren Off'.

5.2.21. Remotely Lock Mobile and Mac OS Devices

Click 'Devices' > 'Device List' > 'Device Management' > select an Android, iOS or Mac device > 'Passcode > 'Lock'

- Admins can remotely lock devices to prevent them being accessed by unauthorized persons, or to generally block access to the device.
- Locked devices can only be opened by entering a passcode on the device.



The remote lock feature is available only for Android and iOS devices and Mac devices installed with MDM profile. See Enroll Mac OS Endpoints, if you need more details about enrollment of Mac devices with MDM profile.

The following sections contain more information on:


- · Lock a single device
- Lock several devices at-once

Remotely lock a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the Android, iOS or Mac OS device you want to lock. This opens the device details interface.
 - Android or iOS device
 - Mac OS device

Android or iOS device

- Click the 'Passcode' button at the top and choose 'Lock'.
 - If 'Passcode' is not displayed, click 'More...', select 'Passcode' and choose 'Lock' from the options




The command to lock the device is sent immediately. The device can only be unlocked by entering the screen lock password.

Mac OS device

- Click the 'Lock' button at the top
 - If 'Lock' is not shown, click 'More...' and choose 'Lock' from the options

You need to specify a new passcode before the device will lock:






- Enter a passcode and click 'OK'
- · Communicate the new password to the user
- The user can unlock the device only by entering the new passcode you set

Remotely lock several devices at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select all devices that you want to lock





The lock command is sent. The devices will be locked and the user(s) can unlock the device(s) by entering the screen lock password.

Note: If you select only one MAC OS device, you have to specify a passcode as explained above.

5.2.22. Wipe Selected Mobile and Mac Devices

Click 'Devices' > 'Device List' > 'Device Management' > select a device > Click 'More' > 'Wipe/Corporate'

- Click 'Devices' > 'Device List' > select a device > Click 'More' > 'Wipe/Corporate'.
- Confidential documents and sensitive information can be stolen from a lost or stolen device.
- To prevent such data loss, admins can remotely erase the contents of a lost device.
 - Additionally, you can configure a profile to wipe a device if the wrong password is entered a set number of times.
 - Click 'Configuration Templates' > 'Profiles' > click on an iOS/Android profile > 'Add Profile Section'
 'Passcode', to set this feature.
- The remote wipe feature is available only for Android and iOS devices and Mac devices installed with MDM profile. See Enroll Mac OS Endpoints, if you need more details about enrollment of Mac devices with MDM profile.

The following sections explain how to:

- Wipe a single device
- Wipe several devices at-once


Wipe a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices



Or

- Select 'Show all' to view every device added to EM
- Click on the name of the device you want to wipe. This will open the device details page.
- Click the 'Wipe / Corporate' button from the options at the top
 - or click 'More...' and choose 'Wipe / Corporate' from the options




- Choose the type of wipe:
 - Corporate Wipe Removes only the Endpoint Manager communication client and configuration profiles
 - **Full Wipe** Erases all data from the device and the SD card. The device will be returned to default factory settings.
- Click the 'Wipe' button to send the command.

Wipe several devices

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - · Select 'Show all' to view every device added to EM
- Select the target devices to be wiped
- Click 'Wipe / Corporate' from the options at the top or click 'More...' and choose 'Wipe / Corporate' from the
 options.





- Choose the type of wipe:
 - Corporate Wipe Removes only the Endpoint Manager communication client and configuration profiles
 - **Full Wipe** Erases all data from the device and the SD card. The device will be returned to default factory settings.
- Click the 'Wipe' button to send the command.

5.2.23. Assign Configuration Profiles to Selected Devices

Click 'Devices' > 'Device List' > 'Device Management' > select a device > Click 'Manage Profiles'


- The 'Device Management' interface lets you view the configuration profiles in effect on selected devices. You can also apply new configuration profiles or remove profiles.
- Profiles applied from this interface will be added to any existing profiles on the device (such as profiles from a device group or user group).
- If the settings in a profile clash with those in another profile, Endpoint Manager follows the 'Most Restrictive' policy. For example, if a profile allows the use of the camera and another restricts its use, the device will not be able to use the camera.

See Create Configuration Profiles, for more details on profiles.



Manage profiles applied to a device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the device you want to manage and click 'Manage Profiles' from the options at the top



 Alternatively, click the name of the device to be managed to open its 'Device Details' interface and choose 'Manage Profiles' from the options at the top


The list of profiles currently active on the device will be displayed.



Manage Profiles - Column Descriptions	
Column Heading	Description
OS Type	Indicates the operating system of the device.
Profile Name	The profile label.
Created By	The admin who added the profile. Click the name to open the user information interface of the admin. See View User Details for more details.

Note: Device group and user group profiles applied to the device will not be shown here. Profiles applied to a device through different channels can be viewed from the respective 'Device Details' interface. See **View and Manage Profiles Associated with a Device** for more details.

To add a profile to the device, click 'Add Profiles' from the top left.






A list of all profiles applicable to the chosen device, excluding those that are already applied to the device is shown.

Select the profile(s) to be applied to the device

Tip: You can use the search and filter options that appear on clicking the funnel icon at the top right to search for the profile(s) to be applied.

- Click 'Save' at the top left to add the selected profile(s) to the device.
- To remove existing profile(s), select the profiles to be removed from the 'Manage Profiles' interface and click on 'Remove Profiles' from the options that appear on top.



The selected profile(s) will be removed from the device immediately.

5.2.24. Set / Reset Screen Lock Password for Selected Devices

Click 'Devices' > 'Device List' > 'Device Management' > select an Android or iOS device > 'Passcode'

- Endpoint Manager lets you remotely set a new screen lock passcode (or reset the existing code) for enrolled Android devices from the 'Device Management' interface.
- You can also send a passcode reset command to iOS devices, enabling the user to set a new password.

The following sections explain more about:

- Remotely set a passcode for a single device.
- Reset password for a single device.
- Remotely set password for several devices at-once




Reset password for several devices at-once

Remotely set a passcode for a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - · Select 'Show all' to view every device added to EM
- Click the name of the Android device for which a new passcode is to be created or changed

This opens the 'Device Details' interface for the device.

- Click 'Passcode' > 'Set Screen Passcode'
 - If 'Passcode' is not shown, click 'More...', select 'Passcode' and choose 'Set Screen Passcode' from the options



Enter the new password in the 'password' text field.

Tip: You can use the eye icon at the right end of the text field to display of hide the typed password. If a Passcode conditions are defined in the profile active on the devices, make sure to enter the new password that complies with the profile.

Click 'Set'.


The command is sent to the device and the device is locked.

• Communicate the password to the user. The user should use only the new password to unlock the device.



Reset password for a single device

- Click 'Devices' > 'Device List'
- · Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the Android or iOS device for which you want to remove the password
- Click the 'Passcode' button at the top and choose 'Reset Screen Passcode'.
 - If 'Passcode' is not shown, click 'More...', select 'Passcode' and choose 'Reset Screen Passcode' from the options




The command is sent to the device and the current screen lock password is cleared. A message is also sent to the device regarding the password change. If a password profile is applied the device, the user is required to create a new password that complies with the profile.

Remotely set password for several devices at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the Android devices to set a new password.
- Click the 'Passcode' button at the top and choose 'Set Screen Passcode'.
 - If 'Passcode' is not shown, click 'More...', select 'Passcode' and choose 'Set Screen Passcode' from the options





Enter the new password in the 'password' text field.

Tip: You can use the eye icon at the right end of the text field to display of hide the typed password. If a Passcode conditions are defined in the profile active on the devices, make sure to enter the new password that complies with the profile.

· Click 'Set'.

The command is to all the devices at-once.

Communicate the password to the users of the devices


From the next unlock operation, the users should enter the new password to unlock the device.

Reset password for several devices at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or



- Select 'Show all' to view every device added to EM
- Select the Android and iOS devices for which you want to clear passwords.
- Click the 'Passcode' button at the top and choose 'Reset Screen Passcode'.
 - If 'Passcode' is not shown, click 'More...', select 'Passcode' and choose 'Reset Screen Passcode' from the options



The password reset command is sent to all the devices. The current screen lock passwords on the devices are cleared. A message is sent to the device regarding the screen lock password change. If a password profile is configured in the device, the user should enter a new password that complies with the profile.

5.2.25. Update Device Information

- The communication client on an enrolled device sends information about the device to Endpoint Manager.
- This includes OS version, memory status, network details, IMEI number, location, MAC address of Bluetooth, MAC address of WiFi and so on.
- The interval at which the device sends this information can be configured in the 'Settings' interface.
- Device information can also be fetched in real time by opening device details then clicking 'Refresh Device Information'.

The following sections explain more about:

- Get updated information from a single device
- Get updated information from several devices at once

Get updated information from a single device


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM



Click the name of the device to refresh the information from

The 'Device Details' interface will open with information on the device fetched from last polling time of the agent installed on the device.


· Click 'Refresh Information' from the options at the top



Get updated information from several devices

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- · Select the devices to refresh information from.
- · Click 'Refresh Device Information' from the options at the top
 - If 'Refresh Device Information' is not displayed, click 'More...', and choose 'Refresh Device Information' from the options





5.2.26. Send Text Messages to Mobile Devices

Click 'Devices' > 'Device List' > 'Device Management' > select an Android or iOS device > 'Send Message'

Endpoint Manager lets you send text messages to enrolled Android and iOS devices. This comes in handy if you need to send important notifications to all users.

Note: For iOS devices, the EM communication client should be installed for this feature to be supported.

- Send message to a single device
- Send message to several devices at-once


Send a text message to a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the target device to which the message should be sent

The 'Device Details' interface opens.

· Click 'Send Message' from the options at the top.






- Enter the text message in the 'Message' field.
- Click the 'Send' button.

The message will be sent to the device for the user's attention.

Send a text message to several devices at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the target devices to which you wish to send messages
- Click 'Send Message' from the options at the top or click 'More...' and choose 'Send Message' from the drop-down





- Enter the text message in the 'Message' field.
- · Click the 'Send' button.

The message will be sent to the selected devices for the users' attention.



5.2.27. Restart Selected Windows Devices

Click 'Devices' > 'Device List' > 'Device Management' > select a Windows device > 'Reboot'

- Endpoint Manager lets you remotely restart Windows machines as required.
- You can also specify how long to delay the restart, add a warning message to be displayed to users and allow them to postpone the restart.

Note: The reboot option is only available for Windows devices.

The following sections explain more about:

- · Restart a single device
- Restart several devices at-once


Restart a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the Windows device to be restarted

The device details interface opens.

Click the 'Reboot' option at the top.






- Configure your reboot options in the 'Reboot' dialog
- Maintenance window status Details of any maintenance windows in the device's profile.
 - Total number of devices outside of maintenance window The number of devices that are not part
 of a maintenance window. The reboot can proceed on these devices.
 - Number of devices blocked by maintenance windows settings The number of devices that you
 cannot reboot because the admin has blocked reboots outside of the maintenance window.
 - Number of devices warned by maintenance window settings The number of devices that are part of a maintenance window and have warnings enabled. You can still reboot these devices.
 - Skip devices warned by maintenance windows settings A maintenance window is a time-slot
 reserved for running important tasks on target devices. Admins can enable a warning if somebody
 attempts to reboot outside of the window. This setting will skip those devices which have been
 added to a maintenance window with warnings enabled.

Restart the end-point after a certain period of time

- Choose 'Force the reboot in' and select the delay period.
- Click 'Send message and reboot'

The message will be displayed at the device as shown below:





The device will be restarted automatically when the time period elapses.

Restart the end-point at user's convenience

- Choose 'Warn about the reboot and let users postpone it.
- Enter the message to be displayed to the user in the 'Reboot message' field.
- Click 'Send message and reboot'

The message will be displayed at the device as shown below:




• The user can choose to restart the endpoint immediately by clicking 'Reboot now' or postpone the restart operation by selecting the period from the 'Remind me in' drop-down and clicking 'Postpone'.

Restart several devices at once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the target Windows devices to be restarted
- Click 'Reboot' from the options at the top or click 'More' and choose 'Reboot' from the options





 Configure your reboot options in the 'Reboot' dialog as explained above and click 'Send message and reboot'.



5.2.28. Change a Device's Owner


- Click 'Devices' > 'Device List' > 'Device Management' > select a device > 'Owner' > 'Change Owner'
 Endpoint Manager lets you assign device ownership from one user to another user.
 - Change ownership of a single device
 - Assign multiple devices to single owner at-once

Change the device ownership of a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the device whose ownership is to be changed

The 'Device Details' interface opens.

- Click 'Owner' from the options at the top or click 'More' and choose 'Owner' from the drop-down
- Select 'Change Owner' from the options
- Start typing the first few characters of the name of the new user to whom the device is to be assigned and choose the user from the options
- · Click 'Change'






The ownership of the device will be changed to the new user. The configuration profiles in effect on the device, associated with the previous user and the user group to which the previous user is a member, will be removed and the profiles, pertaining to the new user and the user group to which the new user is a member, will be applied to the device.

Assign several devices to a user at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the target devices to be associated with a new user

Tip: You can change devices pertaining to different users to be assigned to a single new user.

- Click 'Owner' from the options at the top or click 'More' and choose 'Owner' from the drop-down
- Select 'Change Owner' from the options





- Start typing the first few characters of the name of the new user to whom the device is to be assigned and choose the user from the options
- Click 'Change'

All selected devices will be assigned to the new user. The configuration profiles in effect on the device, associated with the previous users and the user groups to which the previous users are members, will be removed and the profiles, pertaining to the new user and the user group to which the new user is a member, will be applied to the device.

5.2.29. Change the Ownership Status of a Device

Click 'Devices' > 'Device List' > 'Device Management' > select a device > 'Owner' > 'Change Ownership Type'

- Admins can set the ownership status of a device depending on whether it belongs to a user or to the company.
- There are three ownership types 'Personal', 'Corporate' and 'Not Specified'. The ownership type is shown in the 'Summary' tab of the device details interface.
 - Click 'Devices' > 'Device List' > 'Device Management' > click on the name of a device to open its 'Device Details' interface
- By default, any new device enrolled to Endpoint Manager will have an ownership status of 'Not Specified'.
- Ownership types do not have any impact on device security policy or how the device is treated by EM. It is a just a descriptive label which allows admins to more easily identify and group devices.

The following sections explain more about:


- Change ownership status of a single device
- Change ownership status of several devices at-once

Set the ownership status of a single device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Click the name of the target device whose ownership status you wish to change.

The device details interface opens.






- Click 'Owner' from the options at the top or click 'More' and choose 'Owner' from the drop-down
- Select 'Change Ownership Type' from the options
- Choose the ownership type from the following options:
 - Personal
 - Corporate
 - · Not Specified
- Click 'Change'.

Set the ownership status of several devices at-once

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab above the control buttons
 - Select a company or group on the left to view only their devices
 Or
 - Select 'Show all' to view every device added to EM
- Select the devices whose ownership status you wish to change.
- Click 'Owner' from the options at the top or click 'More...' and choose 'Owner' from the drop-down
- Select 'Change Ownership Type' from the options





- Choose the ownership type to be assigned to the selected devices and click 'Change'. The available options
 are:
 - Personal
 - Corporate
 - Not Specified

5.2.30. Generate Device List Report

Click 'Devices' > 'Device List' > 'Device Management' > 'Export' > 'Export to CSV'


- You can create a report on all managed devices listed in the 'Device Management' table.
- The report contains operating system details, hardware details, last activity, CCS configuration, resource usage and more for each device.

Generate device list report

- Click 'Devices' > 'Device List' > 'Device Management'
- Apply any filters that you require.



Click 'Export' > 'Export to CSV' or click 'More' > 'Export' > 'Export to CSV':



A confirmation message is shown:

Report has been created. Please, check «<u>Reports</u>» in dashboard

See 'Reports' in 'Dashboard' for more information on how to view and download reports.

5.3. Bulk Enrollment of Devices

Windows, MAC and Linux

• Click 'Devices' > 'Bulk Installation Package' > 'Bulk Installation Package' tab.

The bulk installation area lets you download the communication client package. You need to install this client on target devices to enroll them to Endpoint Manager.

After downloading the installation package, you can deploy it to target devices using any of the following methods:

Windows

- Active Directory group policy object (GPO)
- Auto Discovery and Deployment Tool (ADDT)
- Manual installation

Mac OS and Linux:

Manual installation



Android and iOS:


You can bulk enroll iOS and Android devices belonging to users that were imported from Active Directory.

- See Import User Groups from LDAP for help to import users from AD.
- After importing users, Android devices can be enrolled by installing the agent. iOS devices can be enrolled by deploying a configuration profile.
- See Enroll Android and iOS Devices of AD Users for help with this.

5.3.1. Enroll Windows, Mac OS and Linux Devices by Installing the Communication Client

You need to install the communication client on Windows, Mac OS and Linux devices to enroll them to endpoint manager.

Click 'Devices' > 'Bulk Installation Package' > 'Bulk Installation Package' tab



Select the 'Bulk Installation Package' tab.

See the following sections for more details:

- Enrollment of Windows Devices Via AD Group Policy.
- Enrollment of Windows, Mac OS and Linux Devices by Offline Installation of Agent
- Enrollment of Windows Devices using Auto Discovery and Deployment



5.3.1.1. Enroll Windows Devices Via AD Group Policy

- · You can enroll devices in bulk by creating an Active Directory (AD) group policy
- You need to download the communication client package and, if required, the transformed MST file. You
 then need to add these items to the GPO.
 - The MST file includes information about the proxy that the client should use to connect to Endpoint Manager and other Comodo servers.
 - By default, all devices enrolled via AD are assigned to the currently logged-in admin. You can change the person to whom the devices are assigned during the package download process.
 - After enrollment, you can assign devices to their correct owners in the 'Devices' interface. See Change
 a Device's Owner for help.

Download the installation package

- Click 'Devices' > 'Bulk Installation Package'
- Select the 'Bulk Installation Package' tab
- Create your custom installer by completing the form. Scroll down for a table that explains the form fields.
- **Download Installer** Download the setup file for installation via Group Policy Object (GPO),
 - The installer package is created in .msi format. You can transfer the file to the required network location
 and create a software installation policy for deployment to your endpoints. Once the agent is installed,
 it establishes communication with the EM server and begins importing devices.
- Download MST File Download an installer that includes proxy server information for client communication with Endpoint Manager.
 - As above, save the file on the AD server from where you want to enroll the endpoints, and add to the GPO created for the .msi file. After the agent is installed, it will establish communications with EM via the proxy servers and begin importing devices.
- For help to create a GPO for bulk enrollment, see https://community.itarian.com/help/topic-459-1-994-14747-EM---Bulk-Enrollment-via-Active-Directory.html.
- Imported devices inherit the configuration profile of the device owner. The configuration profile of the device
 user is automatically applied to the device.

	Bulk Installation Package - Form Parameters	
Parameter	Description	
User	Devices enrolled by AD GPO are assigned to the currently logged-in admin by default. Specify a different user if required. • Start typing the name of a user and choose from the suggestions that appear.	
Customer	Choose the company to which the endpoints should be assigned. This field only applies to ITarian MSP customers. It does not apply to ITarian Enterprise, or EM stand-alone customers.	
Device Group	The device group to which the enrolled devices should be added (optional). Any group profiles will also be applied to the devices you add. See Assign Configuration Profiles to a Device Group if you want more help with this.	
Package Options	Operating system - Select Window OS version (64 bit, 32 bit or hybrid package) Clients:	



 Comodo Client Security (CCS) - Optional. This client installs security software such as antivirus, firewall and auto-containment. Note - The option to choose CC and CCS versions is only available if
enabled in portal settings . If the option is not enabled, then the 'Default version' is deployed.
CCS is selected, you can also configure the following:
ditional Options:
 Database - Choose whether to include the latest virus database with the installation package. This increases file size. If disabled, the client will download the latest database anyway when you run the first scan.
 Profile - Default is 'Windows - Security Level 1' profile. Choose a different profile if required.
 Type the first few characters of a profile and choose from the suggestions that appear.
CS only. Endpoints need to be restarted to complete CCS installation. You have the owing restart options:
• Force the reboot in Restart the endpoint a certain length of time after installation. Select the delay period from the drop-down. A warning message will be shown to the user prior to the restart.
Suppress reboot - Endpoint is not auto-restarted. The installation will be finalized when the user next restarts the endpoint.
 Warn about reboot and let users postpone it - Shows a message to the user which tells them that the endpoint needs to be restarted. The user can choose when the restart happens.
Optional. Type a custom message in the 'Reboot Message' field.
nfigure which messages are shown to the user regarding the installation.
 Show error messages if installation failed - Notifies the user if the installation is not successful.
 Show a confirmation message upon completion of installation - Notifies the user if the installation is successful. Type your message in the box provided.
ecify a proxy server through which the clients should connect to Endpoint Manager d other Comodo servers. If you do not set a proxy then the clients will connect directly per network settings.
 Enter the IP address/hostname of the proxy server and port in the respective fields.
 Enter the user-name and password of an administrative account on the proxy server in the Proxy Login and Proxy Password fields
te: If you specify a proxy here then you must also configure the same proxy settings the profile on the device:
 Click 'Configuration Templates' > 'Profiles' > open the device profile > 'Add Profile Section' > 'Clients Proxy'



Tip: For more help on using GPO for remote installation of software, please see https://support.microsoft.com/en-us/kb/816102.

5.3.1.2. Enroll Windows, Mac OS and Linux Devices by Offline Installation of Agent

- Click 'Devices' > 'Bulk Installation Package' > 'Bulk Installation Package'
- You can download a custom Windows, MAC or Linux installer for offline installation of the client.
- You can specify the user to whom the enrolled device is assigned, and the initial configuration profile
 applied to the device.
- You must already have added the user of the device to EM. You can only create installation packages for existing users.

Download the installation package

- Click 'Devices' > 'Bulk Installation Package'
- Select the 'Bulk Installation Package' tab
- Create your custom installer by completing the form. Scroll down for a table that explains the form fields.
- **Download Installer** Download the installation file for your chosen operating system. Once the agent is installed, it establishes communication with the EM server and begins importing devices.
 - Windows Creates a .msi file if only the communication client is selected. Creates a .exe file if both communication and security client are selected.
 - MAC OS Creates a .pkg installer file.
 - Linux Creates a .run file.
- Download MST File Windows only. Download a .mst installer that includes proxy server information for client communication with Endpoint Manager. File should be installed by command line.

	Bulk Installation Package - Form Parameters	
Parameter	Description	
User	Specify the user to whom the target endpoints should be assigned. By default, this is the currently logged in user. You can always can this later if required.	
	Start typing the name of a user and choose from the suggestions that appear.	
Customer	Choose the company to which the endpoints should be assigned.	
	This field only applies to ITarian MSP customers. It does not apply to ITarian Enterprise, or EM stand-alone customers.	
Device Group	The device group to which the enrolled devices should be added (optional).	
	Any group profiles will also be applied to the devices you add.	
	See Assign Configuration Profiles to a Device Group if you want more help with this.	
Package Options	Operating system	
	Choose the target OS and package type you want. The options are:	
	Windows	



- Windows X64 For 64-bit Windows OS
- Windows X86 For 32-bit Windows OS
- Windows X86 & X64 (hybrid package) Suitable for both 64-bit and 32-bit
 Window OS. Select if your network has a mixture of 64-bit and 32-bit versions.

Mac OS (Recommended)

- Installs both the communication client and the configuration profile on the Mac device.
- Choose this option if you want to use Endpoint Manager for both MAC security (antivirus etc) AND for general MAC management.
- If you select this option, you must install an Apple Push Notification (APN) certificate on your portal to communicate with the devices.
 - Apple only allow one portal to control a MAC device via APN. If you
 want to use a different portal to manage WIFI, VPN, device
 permissions etc, then choose 'MAC OS without MDM Profile' instead.
 - See Add Apple Push Notification Certificate for help to install the certificate.

Mac OS without MDM Profile

- Installs just the communication client on the Mac device.
- Choose this option if you only want to use Endpoint Manager for security on Mac devices.
- This option lets you continue to use a different portal for general MAC management while using Endpoint Manager to manage security.
- This option means you cannot use Endpoint Manager to manage the following profile items:
 - Certificates
 - Restrictions
 - VPN
 - Wi-Fi
- To help you make a decision, you can see what is included the items above by checking the 'Profiles' area.
 - Click 'Configuration Templates' > 'Profiles' > open a MAC profile OR create a new MAC profile > 'Add Profile Section'
 - Add, for example, a 'Restrictions' section to see what is covered.
- See Profiles for Mac OS Devices if you want more help on MAC profiles.

Linux

- Ubuntu / Debian (Hybrid Package) Suitable for both 64-bit and 32-bit
- RHEL / CentOS (Hybrid Package) Suitable for both 64-bit and 32-bit

Clients

Communication Client (CC) - Mandatory. This client enrolls the endpoint and handles communication between the endpoint and endpoint manager.

Comodo Client Security (CCS) - Optional. This client installs the security software, including antivirus, firewall and auto-containment.



	Additional Options (Windows only)
	Database - Choose whether to include the latest virus database with the installer. This increases file size. If disabled, the client will download the latest database anyway when you run the first scan.
	Profile - Choose a configuration profile for the endpoints (optional).
	Type the first few characters of a profile and choose from the suggestions that appear.
	Profile
	Select the configuration profile you want to apply to the target devices.
	 If you do not choose a profile then the default OS profile is applied.
	 Click 'Configuration Templates' > 'Profiles' to view and configure endpoint profiles. You can review the default OS profiles in here.
	 Tip: You can always add or remove profiles later. The default OS profile will implement good, baseline settings for security and usability.
	 See View and Manage Profiles Associated with a Device if you want to read more about profiles.
Restart Control Options (For Windows only)	CCS only. Endpoints need to be restarted to complete CCS installation. You have the following restart options:
	Force the reboot in Restart the endpoint a certain length of time after installation. Select the delay period from the drop-down. A warning message will be shown to the user prior to the restart.
	 Suppress reboot - Endpoint is not auto-restarted. The installation will be finalized when the user next restarts the endpoint.
	 Warn about reboot and let users postpone it - Shows a message to the user which tells them that the endpoint needs to be restarted. The user can choose when the restart happens.
	Optional. Type a custom message in the 'Reboot Message' field.
UI Options (For Windows	Configure which messages are shown to the user regarding the installation.
only)	 Show error messages if installation failed - Notifies the user if the installation is not successful.
	 Show a confirmation message upon completion of installation - Notifies the user if the installation is successful. Type your message in the box provided.
Proxy Settings (For Windows only)	Specify a proxy server through which the clients should connect to Endpoint Manager and other Comodo servers. If you do not set a proxy then the clients will connect directly as per network settings.
	 Enter the IP address/hostname of the proxy server and port in the respective fields.
	Enter the user-name and password of an administrative account on the proxy server in the Proxy Login and Proxy Password fields
	Note: If you specify a proxy here then you must also configure the same proxy settings in the profile on the device:
	Click 'Configuration Templates' > 'Profiles' > open the device profile > 'Add



	Profile Section' > 'Clients Proxy'

5.3.1.3. Enroll Windows Devices using Auto Discovery and Deployment Tool

- You can use the auto-deployment tool to install the Endpoint Manager communication and security clients on target endpoints.
- By installing the clients you will enroll the endpoints to Endpoint Manager.
- You first need to create client installation files using the 'Bulk Installation Package' interface in 'Devices'

Note - The user of the device should already have been added to Endpoint Manager. You can download installation packages only for existing users.

Download ADDT and installation packages

- Click 'Devices' > 'Bulk Installation Package'
- Each installation package is custom-created for a specific user, customer, group, operating system etc.
- Complete the fields in the form to generate your custom package:


Bulk Installation Package - Form Parameters	
Parameter	Description
User	Specify the user to whom the target endpoints are assigned. • Start typing the name of a user and choose from the suggestions that appear.
Customer	Choose the company to which the endpoints should be assigned. • This field only applies to ITarian MSP customers. It does not apply to ITarian Enterprise, or EM stand-alone customers
Device Group	The device group to which the enrolled devices should be added (optional). Any group profiles will also be applied to the devices you add. See Assign Configuration Profiles to a Device Group if you want more help with this.
Package Options	 Operating system - Select 'Windows' Choose platform - Select Windows OS version (64 bit, 32 bit or hybrid package) Clients: Communication Client (CC) - Mandatory. This client enrolls the endpoint. Comodo Client Security (CCS) - Optional. This client installs security software such as antivirus, firewall and auto-containment. Additional Options: Database - Choose whether to include the latest virus database with the installation package. This increases file size. If disabled, the client will download the latest database anyway when you run the first scan.



Profile - Choose a configuration profile for the endpoints (optional).
 Type the first few characters of a profile and choose from the suggestions that appear.
If you do not choose a profile then the default profiles for the operating system will be applied.
Tip: You can add or remove profiles later. See View and Manage Profiles Associated with a Device for more details.
CCS only. Endpoints need to be restarted to complete CCS installation. You have the following restart options:
 Force the reboot in Restart the endpoint a certain length of time after installation. Select the delay period from the drop-down. A warning message will be shown to the user prior to the restart.
 Suppress reboot - Endpoint is not auto-restarted. The installation will be finalized when the user next restarts the endpoint.
 Warn about reboot and let users postpone it - Shows a message to the user which tells them that the endpoint needs to be restarted. The user can choose when the restart happens.
Optional. Type a custom message in the 'Reboot Message' field.
Configure which messages are shown to the user regarding the installation.
 Show error messages if installation failed - Notifies the user if the installation is not successful.
 Show a confirmation message upon completion of installation - Notifies the user if the installation is successful. Type your message in the box provided.
Leave these blank as these settings are not required for offline installation packages.

- Click 'Download Installer' when you have completed the form.
- · You will now download TWO items:
 - 1. The installation package. This will have a name like 'installer_2dr846534e83.exe'
 - 2. The Auto-Deployment tool (ADDT). This tool helps you deploy the installation package to your network:





ADDT is a portable app which does not require installation. ADDT lets you deploy the clients via Active Directory, Workgroup or network address.

 For more details about how to deploy applications via ADDT, visit https://community.itarian.com/help/topic-452-1-955-13345-Introduction-to-Auto-Discovery-and-Deployment-Tool.html.

5.3.2 Enroll the Android and iOS Devices of AD Users


- This section explains how to enroll the devices of users who were imported from Active Directory. See
 Import User Groups from LDAP if you need help to import users first.
- Setup involves installing the communication client on the user's device. After installation, the user should login to the client using their domain username and password.
- Please follow the steps below to import the devices:

Get the enrollment links Import Android devices Import iOS devices


Get the enrollment links

- Click 'Devices' > 'Device List' on the left
- Click the 'Enroll Device' button above the table Or
- Click the 'Add' button on the menu bar and choose 'Enroll Device'.





Click 'Show Enrollment Instructions' in the enroll devices dialog:



Scroll down the section 'Or enroll Active Directory Services':



Enroll Device

Make sure that you selected the operating system of the device that you want to enroll.

For Windows devices

Enroll using this link: https://frontfork-frontfork-msp.dmdemo.comodo.com:443/enroll/windows/msi/token/c0d79905564935390076bff051546b41

For macOS devices

- 1) Open the following link on the browser of the device you want to enroll https://frontfork-frontfork-msp.dmdemo.comodo.com:443/enroll/apple/index/token/c0d79905564935390076bff051546b41
- When you have installed *itsm.mobileconfig* file, use this link to download and install Communication Client application: https://static.dmdemo.comodo.com/download/itsmagent-installer.pkg

For iOS devices

Open the following link on the browser of the device you want to enroll <a href="https://frontfork-fron

HOSE no.

Port: 443

Token: c0d79905564935390076bff051546b41

Or enroll active directory devices

For Windows devices

https://help.comodo.com/topic-399-1-856-11229-ITSM-%E2%80%93-Bulk-Enrollment-via-Active-Directory.html

For Apple devices

Enroll using this link: https://frontfork-msp.dmdemo.comodo.com:443/enroll/apple/login

Use the login and password of your domain.

For Android devices

Download and install Communication Client tapping the following link: https://play.google.com/store/apps/details?id=com.comodo.mdm

Upon completion of the installation, enroll using this link: $\underline{\text{https://frontfork-msp.dmdemo.comodo.com:}} 443/\underline{\text{enroll/android/login}}$

Use the login and password of your domain.


- You next need to send your target users the appropriate setup links for their device operating system.
- Users should open the links on the target device itself



See Import Android devices or Import iOS devices as required.

Android Devices:

- Email the Android client download and enrollment links to target users
- Users should open the mail on the device you want to enroll
- First click the agent download link then install the client on the device.
- After installation is complete, the user should next open the enrollment link.
- This will open the Endpoint Manager login page. Users can login with their domain username and password:



 After agreeing to the EULA, the user should hit 'Activate' to grant admin privileges to the communication client:





← Device administrator



Mobile Device Management..

Activating administrator will allow Mobile Device Management Client to perform the following operations:

Erase all data

Erase the phone's data without warning by performing a factory data reset.

Change the screen lock

Change the screen lock.

Set password rules

Control the length and the characters allowed in screen lock passwords and PINs.

Monitor screen-unlock attempts

Monitor the number of incorrect passwords typed when unlocking the screen and lock the phone or erase all the phone's data if too many incorrect passwords are typed.

Lock the screen

Control how and when the screen locks.

Set screen lock password expiry


Change how frequently the screen lock

CANCEL

ACTIVATE

• After activation, the client will open at the home screen :






The device is now enrolled and can be remotely managed from the Endpoint Manager console.

iOS Devices:

- iOS users first need to install a device profile, then install the Endpoint Manager app.
- Email the Apple enrollment link to all target users. Users should open the mail on the device you want to enroll.
- Users should open the link to download and install the enrollment profile:



Users should follow the wizard to complete profile installation.

ITarian Endpoint Manager - Administrator Guide




- The Endpoint Manager login page will appear when installation is complete. Users should login with their domain username / password.
- The device will connect to Endpoint Manager and commence the app installation process:



- User should select 'Install'. The app is downloaded from their iTunes store account. Users may need to login with their Apple account.
- After installation, users should open the green 'Run After Install' icon:





· User should next accept the EULA to complete device enrollment:



.... 🕏 🗀

4:43 **√ ◄** Safari

END USER LICENSE AGREEMENT AND TERMS OF SERVICE

COMODO ENDPOINT MANAGER

THIS AGREEMENT CONTAINS A BINDING ARBITRATION CLAUSE.

IMPORTANT - PLEASE READ THESE TERMS CAREFULLY BEFORE USING THE COMODO ENDPOINT MANAGER SOFTWARE (THE "PRODUCT"). THE PRODUCT MEANS ALL OF THE ELECTRONIC FILES PROVIDED BY DOWNLOAD WITH THIS LICENSE AGREEMENT. BY USING THE PRODUCT, OR BY CLICKING ON "I ACCEPT" BELOW, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, THAT YOU UNDERSTAND IT, AND THAT YOU AGREE TO BE BOUND BY ITS TERMS. IF YOU DO NOT AGREE TO THE TERMS HEREIN, DO NOT USE THE SOFTWARE, SUBSCRIBE TO OR USE THE SERVICES, OR CLICK ON "I ACCEPT".


Product Functionality

Comodo Endpoint Manager (EM) allows administrators to manage, monitor and secure mobile devices which connect to enterprise wireless networks. Once a device has been enrolled, administrators can remotely apply configuration profiles which determine that device's network access rights, security settings and general preferences. EM also allows administrators to monitor the location of the

Accept Decline

• The device will be successfully enrolled to Endpoint Manager once the client is installed:





App Catalog - Shows Endpoint Manager apps that are ready to be installed:

5.4. Download and Install the Remote Control Tool

- The remote control tool allows admins and staff to take remote control of Windows and Mac OS endpoints.
- This is useful in a number of circumstances, including troubleshooting, running system maintenance and providing training to users.
- You can download the tool from Endpoint Manager, or from the ITarian console:
 - Endpoint Manager Click 'Devices' > 'Bulk Enrollment Package' > 'Remote Control by ITarian'.
 - ITarian console Click 'Tools' > Click 'Download' in the 'Remote Control by ITarian' tile.
- The tool should be installed on your admin computer (the computer from which you want to control the remote endpoints).
- Once installed, the tool can be started from the desktop application or from the EM admin console.
- See Remote Management of Windows and Mac OS Devices for more help to takeover Windows and Mac OS devices

Limitations:


ITarian Endpoint Manager - Administrator Guide




- The remote control tool uses WebRTC and Chromoting protocols to connect to Windows devices. It uses
 the Chromoting protocol alone to connect to Mac OS devices.
- Chromoting is supported by MAC OS and by Windows 7, 8/8.1, 10. It is not support by Windows XP.
- WebRTC is not supported by Mac OS

Download RC from EM interface

- Click 'Devices' > 'Bulk Installation Package'.
- Select the 'Remote Control by ITarian' tab



• Select the OS of the computer on which you want to install the tool.




Click 'Download' and save the setup file.

Download RC from ITarian Console

- Login at https://itarian.com/app/msp/login
- Click 'Tools' in the top-menu
 - The 'Tools' area is a repository of enterprise productivity and security tools
- Click the 'Download' button in the 'Remote Control for ITarian' tile






- Select the operating system of your admin machine.
- Click 'Download' and save the file.


Install the tool

• Launch the set up file to start the installation wizard:






- Language Select your preferred language. Options available are English, Spanish and Russian.
- EULA You must read and accept the End User License Agreement before continuing. After doing so, click 'Install' to start the installation.



After installation is complete, click 'Launch' to start the application.






- Login to the application to start managing Windows or Mac OS endpoints.
 - ITarian customers Click the 'ITarian' tab then login with your ITarian portal username and password
 - Stand-alone Endpoint Manager customers Click the 'Endpoint Manager' tab then enter your Endpoint Manager URL and login details. The URL will have the format https://<your-company-name>.cmdm.comodo.com, where <your-company-name> is your Endpoint Manager company.
- See Remote Management of Windows and Mac OS Devices if you need help to use the remote application.



6. Configuration Templates

The 'Configuration Templates' section lets you create and manage profiles for Android, iOS, Mac, Windows and Linux devices.

- Each profile lets you to specify a device's network access rights, overall security policy, antivirus scan schedule and other settings.
- Once created, profiles can be applied to devices/device groups and users/user groups.
- You can also add procedures and monitors to a profile (Windows devices only).
 - Procedures let you automate a range of tasks on your protected endpoints. Example procedures
 include patch installation, disk de-fragmentation and so on. Procedures can also be deployed as
 stand-alone instructions.
 - Monitors are scripts which track events on your endpoints and take specific actions if their
 conditions are met. For example, 'Alert me when a USB removable disk is connected to the
 system', or 'Create a log entry if CPU usage goes above 75% for a certain length of time'.
- Alerts You can configure monitors to generate alerts if their conditions are met.
 - The 'Alerts' area contains templates which specify general settings for those alerts.
 - For example, 'Create a ticket on service desk', 'Create a notification in the portal', 'Send a notification to the following users'.
 - You can create different alert templates and apply them to different monitors as required.



The 'Configuration Templates' tab contains the following sub sections:

- Profiles A list of every profile added to Endpoint Manager.
 - A profile lets you define a device's security policy, network access rights, antivirus scan schedule and other settings.



- 'Default Profiles' are applied to newly added devices if no user or user group profile exists. Default
 profiles are available for iOS, Android, Mac OS, Windows and Linux devices
- · You can mark custom profiles as 'default' if you wish.
- Profiles can be applied to individual devices/users, device groups and user groups. You can add new profiles, export profiles, and import profiles.
- Alerts Alert templates govern what happens when you receive an alert from a procedure/monitor. For
 example, an alert template can tell EM to send you a notification if the conditions of a monitor are met.

Unless you change it, the 'Default Alert' settings are applied to new monitors/procedures. Click 'Configuration Templates' > 'Alerts' then click on 'Default Alert' to view these settings. You can also create custom alert templates as required.

See 'Manage Alerts' for more details.

- Procedures Contains a list of predefined and custom procedures that can be executed on enrolled devices. Procedures can be run ad-hoc on selected devices or scheduled in a profile to run at set intervals.
 See 'Manage Procedures' for more details.
- Monitors A monitor is a script which tracks events on your network and takes specific actions if its
 conditions are met. For example, 'Alert me when a USB removable disk is connected to the system', or
 'Create a log entry if CPU usage goes above 75% for a certain length of time'.

You can add a monitor to a Windows profile by adding a 'Monitoring' section. See **Manage Monitors** for more details.

- Data Loss Prevention Data loss prevention (DLP) discovery rules let you scan managed devices for files that contain sensitive information. For example, credit card numbers, social security numbers etc.
 - Discovery rules let you specify the areas you want to scan, and the type of data you want to search for.
 - You then add the rules to profiles.
 - See Data Loss Prevention Rules for help to configure the rules.
 - You can view discovered files at 'Security Subsystems' > 'Data Loss Prevention'

The interface lets you:

- Create/Import Configuration Profiles
- View the Profiles
- Edit Configuration Profiles
- Manage Default Profiles
- Manage Procedures
- Manage Alerts
- Manage Monitors
- Create and manage data loss prevention rules

6.1. Create Configuration Profiles


- Click 'Configuration Templates' > 'Profiles'
- A configuration profile is a collection of settings which can be applied to devices managed by Endpoint Manager.
- Each profile lets you specify a device's network access rights, overall security policy, antivirus scan schedule and other settings.
- Profiles can be created and managed separately for iOS, Android, Mac OS, Windows and Linux devices.
- Once created, a profile can be applied to an individual device, to a group of devices, to a user, to a user group, or designated as a 'default' profile.



- You can also create new profiles by cloning or importing a profile.
 - Note Please don't confuse Endpoint Manager profiles with Apple DEP profiles. DEP profiles are
 only for enrolling devices to Apple's Device Enrollment Program. Endpoint Manager profiles are for
 day-to-day device management.

Create a configuration profile

- Click the 'Configuration Templates' > 'Profiles'
- Click 'Create' from the options at the top



The 'Create' drop-down lets you add new profiles for Android, iOS Mac OS, Windows and Linux devices.

- You can create as many profiles as you want for different use-cases.
- You can apply multiple profiles to a single device. The most restrictive policy will prevail if there is a conflict in settings.
 - For example, if one profile allows the use of camera and another restricts its use, the device will not be able to use the camera.
- You can create a new Windows profile by defining security settings for each component of Comodo Client Security (CCS). In addition, you can import the current CCS configuration from an endpoint to use as a profile for other endpoints.
- The interface also allows you to export an existing Windows profile in .cfg format. You can import the profile at a later time for re-use or modification.

See the following sections for help with OS-specific profiles:

- Profiles for Android Devices
- Profiles for iOS Devices
- Profiles for Mac OS Devices
- Profiles for Linux Devices
- Profiles for Windows Devices
- Import Windows Profiles



6.1.1. Profiles for Android Devices

Android profiles let you configure a device's network access rights, security restrictions, scan schedule, and other settings.

Process in brief:


- Click 'Configuration Templates' > 'Profiles'
- Click 'Create' > 'Create Android Profile'
- Type a name and description for your profile then click the 'Create' button. The profile now appears in 'Configuration Templates' > 'Profiles'.
- New profiles have only one section 'General'. Click 'Add Profile Section' to add settings for various security and management features. Each section you add will appear as a new tab.
- Once you have fully configured your profile you can apply it to devices, device groups, users and user groups.
- You can make any profile a 'Default' profile by selecting the 'General' tab then clicking the 'Edit' button.

This part of the guide explains the processes above in more detail, and includes in-depth descriptions of the settings available for each profile section.

Create an Android profile

- Click 'Configuration Templates' > 'Profiles'
- Click the 'Create' button > 'Create Android Profile':






- Enter a name and description for the profile
- · Click the 'Create' button

The Android profile is created and the 'General Settings' section is displayed. The new profile is not a 'Default Profile' by default.






- A 'default' profile is one that is applied automatically to any device which matches its operating system. You
 can have multiple 'default' profiles per operating system.
- Click the 'Make Default' button if you want this profile to be a default.
 - Alternatively, click the 'Edit' button on the right of the 'General' settings screen and enable 'Is Default'.
- Click 'Save'.

Tip: You can set any profile as a default in the 'Profiles' screen. See Edit Configuration Profiles for more details.

The next step is to add profile sections.

- Each profile section contains a range of settings for a specific security or management feature.
- For example, there are profile sections for 'Browser Restrictions', 'Antivirus Settings', 'Network Restrictions', 'VPN' and so on.
- You can add as many different sections as you want when building your device profile.
- To get started:
 - Click 'Add Profile Section'
 - Select the security component that you want to include in the profile:






Note: Many Android profile settings have small information boxes next to them which indicate the OS and/or device required for the setting to work correctly.

For example, the following box indicates that the setting supports KNOX 2.0+ (Samsung For Enterprises) devices and tablets only

KNOX 2.0+/Tablets only

The settings screen for the selected component is shown. After saving, it is available as a link at the top.






The following sections explain more about each of the sections:

- Antivirus
- Bluetooth Restrictions
- Browser Restrictions
- Certificate
- Email
- Active Sync
- Kiosk
- Native App Restrictions
- Network Restrictions
- Passcode
- Restrictions
- VPN
- Wi-Fi
- Other Restrictions

Configure Antivirus settings

Click 'Antivirus Settings' in the 'Add Profile Section' drop-down





Antivirus Settings - Table of Parameters		
Form Element	Туре	Description
AV scanning exclusion list	Text Field	Lets you add trusted apps.
		Trusted apps are excluded from real-time, on-demand and scheduled antivirus scans run on the devices. You can add apps installed from the Google Play Store and apps installed through the EM App store.
		Enter the bundle identifier of the app that you want to exclude from antivirus scanning.
		For more details on getting the bundle identifier for an app, see the explanation given below this table.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
		Click to add more 'AV scanning exclusions list' fields.
		 Click — to remove an item from the 'AV scanning exclusion list ' field.
Automatically terminate	Checkbox	If enabled, any malware found is stopped from running.
malware process		From this point it might be ignored (allowed to remain on the device) or uninstalled, depending on the settings in Android client antivirus settings .
		To view these settings, click:
		'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Android' > 'Antivirus'
Schedule scan	Checkbox	Select if you want to automate the process of antivirus scanning. Select the checkbox beside the day(s) that you want the scheduled scan to run.

Click the 'Save' button.

The settings are saved and shown under the 'Antivirus Settings' tab. You can edit settings or remove the 'Antivirus Settings' section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Obtain Bundle/Package Identifier

The bundle identifier is a string that identifies the .apk package used to install the app.

For Google Play Apps:

The bundle identifier can be found at the end of the app's Google Play download URL.

For example, 'com.comodo.batterysaver' is the Comodo Battery Saver app id in the URL


https://play.google.com/store/apps/details?id=com.comodo.batterysaver

For Enterprise Apps installed through EM App Store:

The bundle identifier can be viewed from the App Details screen of the App.

- Click 'App Store' from the left and choose Android
- Click on the app from the list displayed at the right






The bundle identifier is displayed in the 'Bundle ID' field.

Configure Bluetooth Restrictions settings

The feature is supported for Samsung for Enterprise (SAFE) devices only.

Click 'Bluetooth Restrictions' from the 'Add Profile Section' drop-down



Bluetooth Restrictions Settings - Table of Parameters		
Form Element	Туре	Description
Allow Device discovery via Bluetooth	Checkbox	Allows discovery of other devices via Bluetooth.
Allow Bluetooth Pairing	Checkbox	Allows users' devices to pair with other their devices via Bluetooth.
Allow Outgoing Calls	Checkbox	Allows users to make calls using Bluetooth enabled devices (eg. hands-free devices)



Bluetooth Restrictions Settings - Table of Parameters		
Allow Bluetooth Tethering	Checkbox	Allows users to enable/disable Bluetooth tethering option.
Allow connection to Desktop or Laptop via Bluetooth	Checkbox	Allow users to enable/disable Bluetooth connection with Desktop or Laptop.
Allow data transfer	Checkbox	Allows data transfer between devices via Bluetooth.

Click the 'Save' button.

The settings are saved and shown under the 'Bluetooth Restrictions' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Configure Browser Restrictions settings

The feature is supported for Samsung for Enterprise (SAFE) devices only.

Click 'Browser Restrictions' from the 'Add Profile Section' drop-down

The 'Browser Restrictions' settings screen will be displayed.



Browser Restrictions Settings - Table of Parameters		
Form Element	Туре	Description
Allow Pop-ups	Checkbox	Pop-ups in browsers will be allowed on user devices.
Allow Javascript	Checkbox	Java scripts will be allowed on user devices
Accept Cookies	Checkbox	Users will be allowed to modify Cookies settings on their devices.
Remember Form Data for later use	Checkbox	Users will be allowed to use Auto Fill settings on their devices.
Show Fraud Warning Settings	Checkbox	Users will be allowed to view Fraud Warning Settings on their devices.

Click the 'Save' button.



The settings are saved and shown under the 'Browser Restrictions' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Configure Certificate settings

The 'Certificate' settings section is used to upload certificates and will act as a repository from which certificates can be selected for use in other areas like 'Wi-Fi, 'Exchange Active Sync' and 'VPN'.

Click 'Certificate' from the 'Add Profile Section' drop-down

The 'Certificate' settings screen will be displayed.



Certificate Settings - Table of Parameters		
Form Element	Туре	Description
Name	Text Field	Enter the label of the certificate.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Description	Text Field	Enter an appropriate description for the certificate.
Data	Browse	Browse to the location of the stored certificate and select the certificate.
	button	Note: Only certificate files with extensions 'pub', 'crt' or 'key' can be uploaded.

· Click the 'Save' button.

The certificate will be added to the certificate store.






- Click 'Add Certificate' and repeat the process to add more certificates.
- · Click on the name of the certificate to view the certificate key and edit the name

You can add any number of certificates to the profile and remove certificates at anytime. See **Edit Configuration Profiles** for more details.

Configure Email settings

Note: The feature is supported for Samsung for Enterprise (SAFE) devices only. This area allows administrators to configure email settings on devices.

Click 'Email' from the 'Add Profile Section' drop-down



Email Settings - Table of Parameters		
Form Element	Туре	Description
Configure for Type*	Drop-down	Choose the protocol for incoming mail server from IMAP and POP.
Email address*	Text Field	Enter the email address of the user at the incoming mail server If the profile is for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		The email address of the users to whom the profile is associated are automatically added to the profile while rolling out the same to the devices.
		See Create and Manage Custom Variables for more details on variables.



Email Settings - Table of Parameters		
Account Display Name	Text Field	Enter a label to identify the user's email account at the incoming mail server, if the profile is for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
		The email address of the users to whom the profile is associated are automatically added to the profile while rolling out the same to the devices.
Set as Default Account	Checkbox	The email account is set as default for the users.
Mail Server Host Name (for Incoming Mail) *	Text Field	Enter the host name or IP address of the incoming mail server, if the profile is for a single user.
		Click the variables button + Variables to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Mail Server Port Number (for Incoming Mail) *	Text Field	Enter the server port number used for incoming mail service for a single user,
		For POP3, it is usually 110 and if SSL is enabled it is 995. For IMAP, it is usually 143 and if SSL is enabled it is 993.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Login (for Incoming Mail)*	Text Field	Enter the username for the email account of the user at the incoming mail server if the profile is for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
		The email usernames of the users to whom the profile is associated are automatically added to the profile while rolling out to the devices.
Password (for Incoming Mail)*	Text Field	Enter the password for the email account of the user at the incoming mail server if the profile is for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
		The email passwords of the users to whom the profile is associated are automatically added to the profile while rolling out to the devices.
Use SSL Incoming	Checkbox	Communication between incoming mail server and devices is encrypted using SSL (Secure Socket Layer Protocol).



Email Settings - Table of Parameters		
Accept All Certificates (for Incoming Mail)	Checkbox	The device automatically accepts all SSL certificates from the incoming mails.
Accept TLS Certificates (for Incoming Mail)	Checkbox	The device automatically accepts all secure certificates for TLS (Transport Secure Layer Protocol) from the incoming mails.
Mail Server Host Name (for Outgoing mail)*	Text box	Enter the host name or IP address of the outgoing (SMTP) mail server for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Mail Server Port Number (for Outgoing Mail) *	Text box	Enter the server port number used for outgoing (SMTP) mail service, if the profile is for single user.
		If no port number is specified then ports 25, 587 and 465 are used in the given order.
		Click the variables button + Variables to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Login (for outgoing Mail)*	Text Field	Enter the username for the email account of the user at the outgoing (SMTP) mail server if the profile is for a single user.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
		The email usernames of the users to whom the profile is associated are automatically added to the profile while rolling out to the devices.
Password (for outgoing Mail)*	Text Field	Enter the password for the email account of the user at the outgoing (SMTP) mail server if the profile is for a single user.
		Click the variables button + Variables to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
		The email passwords of the users to whom the profile is associated are automatically added to the profile while rolling out to the devices.
Use SSL (for Outgoing Mail)	Checkbox	Communication between outgoing mail server and devices is encrypted using SSL.
Accept All Certificates (for Outgoing Mail)	Checkbox	The device automatically accepts all SSL certificates from outgoing mails.
Accept TLS Certificates (for Outgoing Mail)	Checkbox	The device automatically accepts all secure certificates for TLS (Transport Secure Layer Protocol) from outgoing mails.
Sender Name	Text Field	Enter the name that should appear in the 'From' field of the sent emails from the device if the profile is for a single user.
		Click the variables button + Variables to insert dynamic values if the



Email Settings - Table of Parameters		
		profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Set Signature	Text Field	Enter the signature and other details that appears at the end of the mails sent from the device.
		Click the variables button to insert dynamic values if the profile is for several users.
		See Create and Manage Custom Variables for more details on variables.
Prevent Moving Mail to other Accounts	Checkbox	The user cannot move sent or received mails to another account.
Always Vibrate on New Email Notification	Checkbox	The device vibrates in addition to sound alert when a new email is received.
Vibrate on New Email Notification if device is silent	Checkbox	The device vibrates when a new email is received, when the device is in silent mode.

Click the 'Save' button.

The settings are saved and shown under the 'Email' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.


Configure ActiveSync settings

ActiveSync settings allows you to configure user access to Exchange Server mail accounts.

Note: Please make sure users are not blocked from using the email client on their devices in **Native App Restrictions**

• Click 'ActiveSync Settings' from the 'Add Profile Section' drop-down





ActiveSync Settings - Table of Parameters		
Form Element	Туре	Description
Email Address *	Text Field	Click the 'Variables' button and click beside '%u.mail' from the User Variables' list. The email address of the users to whom the profile is associated are automatically filled. For more details on variables, see Create and Manage Custom Variables.
User Name *	Text Field	Click the 'Variables' button and click beside '%u.login' from the User Variables' list. The username of the users to whom the profile is associated are automatically filled. For more details on variables, see Create and Manage Custom Variables.
Domain *	Text Field	Enter the domain name in the field. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Server Address *	Text Field	Enter the server address of the ActiveSync. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Password	Text Field	Leave the field blank. The user needs to enter the password while configuring the email account for the first time. After it is validated, the users can access the email account without entering the password.
Account Display Name	Text Field	Enter a label to identify the user's email account at the exchange server.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.



ActiveSync Settings - Table of Parameters		
Email Signature	Text Field	Enter the signature and other details that appears at the end of the mails sent from the device.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Maximum Email Size	Comobo Box	The maximum size of email that the user can download from the server. Use the controls or enter the value in the field.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Sync Emails	Drop-down	Choose the period for which the emails are to be kept synchronized between the device and the exchange server from the recent past, from the drop-down.
Sync Calendar	Drop-down	Select the period for which the calendar events are to be synchronized between the device and the exchange server, from the drop-down.
Use SSL	Checkbox	Communication between the device and the exchange server is encrypted using SSL (Secure Socket Layer Protocol).
As default account	Checkbox	The email address is used as default for sending out emails.
Accept all certificates	Checkbox	The device automatically accepts all SSL certificates.
Can sync contacts	Checkbox	Allows synchronization of user contacts between device and exchange server.
Can sync calendar	Checkbox	Allows synchronization user created calendar events between the device and the exchange server.
Can sync tasks	Checkbox	Allows synchronization of user scheduled tasks between the device and the exchange server.
Manual roaming sync	Checkbox	The user can use the sync feature manually while away from the home network.
Always vibro on new email	Checkbox	The device will vibrate when a new email is received.

Fields with * are mandatory.

Click the 'Save' button.

The settings are saved and shown under the 'ActiveSync Settings' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.


Configure Kiosk settings

Note: This feature is only supported by Samsung for Enterprise (SAFE) devices.

Background: Kiosk mode is a feature intended to help administrators lock-down mobile devices by limiting the applications that are able to run on a device. 'Locking' a device to particular applications can prevent users from opening other applications or straying into important device configuration areas. You can also block aspects of the OS should you wish. An example is a retail or school environment where only certain apps should be used on the device.



Click 'Kiosk' from the 'Add Profile Section' drop-down



Kiosk Settings - Table of Parameters		
Form Element	Туре	Description
Kiosk Mode Type	Drop- down	The two Kiosk modes are: Default mode - Run multiple apps in Kiosk mode. Users will not be able to run non-kiosk applications. Kiosk mode can only be exited by entering the admin bypass password.
		Single App mode - Users can only run the single application that you specify. Users will not be able to run non-kiosk applications. Kiosk mode can only be exited if the admin disables it in the EM console.
		Restrictions on access to other device functions, such as task manager and the status bar, can also be configured for either mode.
If 'Single App' is selected as	Kiosk Mode	Туре:
Enter ID of Kiosk Apps	Text Field	Enter the Package ID of the app that will run in Kiosk mode.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
		See Obtain Bundle/Package Identifier for more details on Package ID.
If 'Default mode' is selected as Kiosk Mode Type:		
Enter ID of Kiosk Apps	Text Field	Enter the package IDs of the apps that will run in Kiosk mode.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
		See Obtain Bundle/Package Identifier for more details on Package ID.



Kiosk Settings - Table of Parameters		
		Click to add more app IDs.
		Click the — button to remove an item from the list
Block Multi-Window Mode	Checkbox	Users cannot open multiple windows.
Block Task Manager	Checkbox	Users cannot access task manager screen.
Hide Navigation Bar	Checkbox	The navigation bar is not shown on the devices.
Hide System Bar	Checkbox	The system bar is not shown on the devices.
SMS/MMS blocking	Checkbox	All SMSs and MMSs to the device are blocked.
Block Keys	Drop- down	This feature lets you selectively block touch keys and icons available on device screen.
		For example, if you do not want the device owners to use 'Caps Lock' key you can block it.
		Click in the 'Block Keys' field:
		Select Keys
		Scroll down to view the full list and select the key.
		× 2 × 5 × Envelope × F9
		Repeat the process to add more keys to the blocked keys list.
- J		ult mode' is selected as Kiosk Mode Type:
Show messenger App	Checkbox	Allows the messenger app on the device.
Show email App	Checkbox	Allows the email app on the device.
Show dialer App	Checkbox	Allows the phone dialer app on the device.
Show admin bypass button	Checkbox	Adds the 'Admin bypass' button to the device screen. The user can tap the button and enter the password to exit from the Kiosk mode.
Admin bypass password	Text Field	Enter the password required to exit the Kiosk mode.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.

• Click the 'Save' button.

The settings are saved and shown under the 'Kiosk' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.




Configure Native App Restriction settings

Native applications are those applications that come with the device operating system. Examples include the email and gallery apps. Admins can restrict users from accessing these native applications if required.

Note: Native app restrictions are only available on Samsung which support KNOX 1.0 +

Click 'Add Profile Section' > 'Native App Restrictions'



Native Application Restrictions Settings - Table of Parameters		
Form Element	Туре	Description
Allow Gmail	Checkbox	Users can the access Gmail app.
Allow Email	Checkbox	Users can the access the default email app.
Allow Browser	Checkbox	Users can access the default Android browser on their devices.
Allow Gallery	Checkbox	Users can access Gallery on their devices.
Allow Settings	Checkbox	Users can change their device settings.
Allow Google Play	Checkbox	Users can access Google Play on their mobile devices.
Allow YouTube App	Checkbox	Users can access the YouTube app.
Allow Google Maps & Navigation	Checkbox	Users can access Google Maps and Navigation app on their devices.
Allow Google and Voice Search	Checkbox	Users can use Google and Voice Search services.

Click the 'Save' button.


The settings are saved and shown under the 'Native App Restriction' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.



Configure Network Restriction settings

The feature is supported for Samsung for Enterprise (SAFE) devices only.

· Click 'Network Restrictions' from the 'Add Profile Section' drop-down



Network Restrictions Settings - Table of Parameters		
Form Element	Туре	Description
Allow Emergency Calls only	Checkbox	Allows users to make only emergency calls.
Allow Voice Roaming	Checkbox	Allows users to make/receive voice call during roaming.
Allow Sync during Roaming	Checkbox	Allows the use of Sync feature while roaming.
Allow Data Roaming	Checkbox	Allows users to enable 'Data Roaming' option on their devices to access data services during roaming.
Allow USB Tethering	Checkbox	Allows users to enable 'USB Tethering' option for sharing their data connection through USB tethering.
Allow Wi-Fi access point settings editing	Checkbox	Allows users to edit the Wi-Fi access point settings to create a Wi-Fi hotspot for sharing their data connection.
Allow user to add Wi-Fi networks	Checkbox	Allows users to add additional Wi-Fi networks.
Wi-Fi Network Minimum Security Level	Drop-down	Fi network. The options available are:
		• Open



		 WEP WPA 802.1x EAP (LEAP) 802.1x EAP (FAST) 802.1x EAP (PEAP) 802.1x EAP (TLS) 802.1x EAP (TLS)
Allow SMS	Drop-down	Allows text messages as per the option selected: • All - Allows both incoming and outgoing text messages. • Incoming Only - Allows incoming text messages only. • Outgoing Only - Allows outgoing text messages only. • None - Both incoming and outgoing text messages are blocked.
Allow MMS	Drop-down	 Allows multimedia messages as per the option selected: All - Allows both incoming and outgoing multimedia messages. Incoming Only - Allows incoming multimedia messages only. Outgoing Only - Allows outgoing multimedia messages only. None - Both incoming and outgoing multimedia messages are blocked.
Blacklisted SSIDs	Text Field	Specify the name (SSID) of the wireless network that should be blacklisted. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables. Click the button to add more 'Blacklisted SSID' fields. Click the minus button beside an SSID to remove it from the list




Click the 'Save' button.

The settings are saved and shown under the 'Network Restrictions' tab. You can edit the settings or remove the section from the profile at anytime See **Edit Configuration Profiles** for more details.

Configure Passcode settings

· Click 'Passcode' from the 'Add Profile Section' drop-down



Passcode Settings - Table of Parameters		
Form Element	Туре	Description
Passcode Type	Drop-down	Select the type of passcode from the drop-down that the user should configure for unlocking screen lock. The options available are:
		No passcode enforcement
		Only letters
		Letters and numbers
		Only numbers
		Letters, numbers and a special symbol
		Requires some kind of password
Minimum Passcode Length	Drop-down	Select the minimum number of passcode characters that can be configured by the user. (4-16 characters).
Maximum Idle Time	Drop-down	Select the maximum time period that can be set as idle time out period for

ITarian Endpoint Manager - Administrator Guide



		device screen lock, from the drop-down.
Maximum Failed Attempts for Wipe	Drop-down	Select the maximum number of allowed unsuccessful login attempts for device wipe (4-16). Set the value as '0' for unlimited.
		If the number of failed attempts crosses this value, the data in the device will be automatically wiped off. This is useful to prevent the data from the device being stolen, if somebody, other than the user, tries to login to the device by entering guessed passcodes.
Maximum Failed Attempts for Sneak Peek	Drop-down	Select the maximum number of allowed unsuccessful login attempts for 'Sneak Peek' feature (4-16). Set the value as '0' for unlimited.
		The 'Sneak Peek' feature makes the device take a photograph with the front-facing camera if the wrong passcode is entered a certain number of times - hopefully getting a picture of the person holding a lost/stolen device. Photographs are forwarded to the EM server.
		The photograph(s) sent by the device can be viewed from the 'Device Details' interface that can be accessed by clicking 'Devices' > 'Device List' > the device name > 'Sneak Peek' tab. See View Sneak Peek Pictures to Locate Lost Devices for more details.
		Note: If the device does not have a front camera, the rear camera will capture a photograph and forward to the EM server.
Maximum Passcode Age (days)	Text Field	Enter the maximum period in days for which a passcode can be valid. After the number of days specified in this field, the passcode will expire. The user needs to change the passcode before the current one expires.
Passcode History Requirements	Text Field	Set how many unique, new passcodes must be created before the user can re-use an old password.
		This feature is available for Android 3.0 and later versions only.




Click the 'Save' button.

The settings are saved and shown under the 'Passcode' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Configure Restriction settings

Click 'Restrictions' from the 'Add Profile Section' drop-down



Restrictions Settings - Table of Parameters		
Form Element	Туре	Description
Allow Turn-off background Sync	Checkbox	Select this to allow users to disable background synchronization setting on their devices.
Allow Bluetooth	Checkbox	Select this to allow users to enable/disable Bluetooth on their devices.
Allow Camera	Checkbox	Select this to allow users to use the camera
Allow Un-encrypted devices	Checkbox	Select this to enable users to use device without turning on the storage encryption feature. This feature is available for Android 3.0 and later versions only.
Allow to run Apps installed from unknown sources	Checkbox	Select this to allow users to run installed applications that were download from unknown sources
Cellular Connection Control	Radio	Choose whether or not to allow the device to connect to the internet



Restrictions Settings - Table of Parameters		
Bu	ittons	through a cellular network (2G/3G/4G):
		Cellular Connection on - Maintains the data connection through cellular network enabled, irrespective of user settings under 'Settings' > 'Wireless and Network settings' in the device.
		Cellular Connection off - Maintains the data connection through cellular network disabled, irrespective of user settings under 'Settings' > 'Wireless and Network settings' in the device.
		 User Choice - The connection is enabled or disabled as per the user's setting under 'Settings' > 'Wireless and Network settings' in the device.



Restrictions Settings - Table of Parameters			
WiFi Connection Control	Radio Buttons	Choose whether or not to allow the device to connect to WiFi networks and hotspots from the options.	
		WiFi Connection on - Always maintains the WiFi connection enabled, irrespective of user's setting under 'Settings' > 'Wireless and Network settings' in the device.	
		WiFi Connection off - Always maintains the WiFi connection disabled, irrespective of user's setting under 'Settings' > 'Wireless and Network settings' in the device.	
		User Choice - The connection is enabled or disabled as per the user's setting under 'Settings' > 'Wireless and Network settings' in the device.	
Location Service Control	Radio Buttons	Choose whether or not to allow the location services on the device from the options:	
		Location Service Always On - Always maintains the location services enabled, irrespective of the user's setting on the device.	
		 Location Service Always Off - Always maintains the location services disabled, irrespective of the user's setting on the device. 	
		User Choice - The location service is enabled or disabled as per the user's setting on the device.	

• Click the 'Save' button.


The settings are saved and shown under the 'Restrictions' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Configure VPN settings



Note: The feature is supported for only Samsung for Enterprise (SAFE) devices.

· Click 'VPN' from the 'Add Profile Section' drop-down



Form Element	Description
Configure for type	Choose the VPN connection type from drop-down. The options available are:
	• L2TP,
	• PPTP,
	L2TP/IPSec PSK,
	IPSec, XAuth PSK
	IPSec XAuth RSA.
VPN Connection Name	Enter a label for the connection. This is shown on the device.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Host name of the VPN Server	Enter the IP address or host name of the VPN server.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Username / Password	Enter the login credentials for the device to connect to the VPN server.
	Click the variables button to insert dynamic values. See



Form Element	Description
	Create and Manage Custom Variables for more details on variables.
DNS Search Domains	Enter the IP address or hostname of the DNS server that devices will use for searching domain names.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
For L2TP	
Enable L2TP Secret	If enabled, the pre-shared L2TP should be entered in the next field L2TP Secret
L2TP Secret	If L2TP Secret is enabled, then the pre-shared key should be entered here by the user or selected from 'Variables'
For PPTP	
Enable Encryption	If selected, the connection is encrypted between the devices and the VPN server.
For L2TP/IPSec PSK	
Enable L2TP Secret	If enabled, the pre-shared L2TP should be entered in the next field L2TP Secret
L2TP Secret	If L2TP Secret is enabled, then the pre-shared key should be entered here by the user or selected from 'Variables'
IPSec Pre-Shared Key	If IP Sec Identifier is enabled, then the pre-shared key should be entered here by the user or selected from 'Variables'
For IPSec Xauth PSK	
IP Sec Identifier	Enter the IPSec identifier in the field.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
IPSec Pre-Shared Key	If IP Sec Identifier is enabled, then the pre-shared key should be entered here by the user or selected from 'Variables'.
Use for persistent connect	Forcibly maintains the VPN connection always at the enabled state, irrespective of user's settings through 'Settings' > 'Wireless and Networks' in the device. In order to enable this feature, the following conditions are to be satisfied:
	The profile should have been created already and rolled out to the devices. Hence the administrator will be able to enable this feature after rolling out the profile and then by editing the profile. See Edit Configuration Profiles for more details.
	 Suits to all VPN connections types, except PPTP The VPN server and the DNS server should have been specified by their IP addresses in IPv4.

· Click the 'Save' button after entering or selecting the parameters.

The VPN connection setting is added to the profile.






- Click 'Add VPN' and repeat the process to add more VPN connections.
- Click the name of a connection to view and edit its settings

You can add any number of VPN connection settings to the profile at anytime. See **Edit Configuration Profiles** for more details.

Configure Wi-Fi settings

Click 'Wi-Fi' from the 'Add Profile Section' drop-down



Wi-Fi Settings - Table of Parameters		
Form Element	Туре	Description
SSID	Text Field	Enter the Service Set Identifier (SSID), the name of the wireless network that a device should connect to.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Hidden SSID	Checkbox	If enabled, users will be able to access the hidden wireless network too. Users must know the hidden SSID details and the required credentials.
Wi-Fi Configuration Type	Drop-down	Select the type of encryption used by the wireless network from the drop-down. The options available are:
		• Open
		• WEP
		WPA / WPA2 - PSK
		• 802.1x EAP
		The settings for each type is explained in the next table Wi-Fi configuration type settings.



Wi-Fi Configuration Type settings


Wi-Fi Configuration Type Settings - Table of Parameters			
Security Configuration Type	Description		
Open	No password is required for accessing the Wi-Fi network by the user.		
WEP	Authentication Password - Enter the password to access the Wi-Fi network.		
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.		
WPA / WPA2 - PSK	Authentication Password - Enter the password to access the Wi-Fi network.		
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.		
802.1x EAP	Manage Custom Variables for more details on variables. 1. EAP Authentication Protocol - Select the EAP authentication protocol from the drop-down. Applicable for Samsung for Enterprise devices SAFE 1.0 + version. PEAP TLS TTLS TTLS 2. Phase 2 Authentication Protocol - Select the Phase 2 authentication protocol from the drop-down. Applicable for Samsung for Enterprise devices SAFE 1.0 + version. None PAP MSCHAP MSCHAP MSCHAP MSCHAP MSCHAP TCC Certificate - Select the user certificate from the drop-down or upload it using the 'Add New' button. CA Certificate - Select the CA certificate from the drop-down or upload it using the 'Add New' button. Authentication Username - Enter the username for Wi-Fi authentication. Applicable for Samsung for Enterprise devices SAFE 1.0 + version. Authentiation Password - Enter the password for Wi-Fi authentication. Applicable		
	for Samsung for Enterprise devices SAFE 1.0 + version. 7. Authentication Domain - Enter the details for RADIUS Server authentication.		
	pplicable for Samsung for Enterprise devices SAFE 1.0 + version.		
	8. Anonymous Identity - Enter the username that can be used for anonymous access. Applicable for Samsung for Enterprise devices SAFE 1.0 + version.		
	9. Encryption Key - Enter the encryption key to access the Wi-Fi network. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.		



Click the 'Save' button after entering or selecting the parameters.

The 'Wi-Fi' network' is saved to the profile.

- Click 'Add Wi-Fi' and repeat the process to add more Wi-Fi networks.
- Click the SSID of the network to view and edit its settings.




You can add or remove Wi-Fi networks at any time. See Edit Configuration Profiles for more details.

Configure 'Other Restrictions' settings

The feature is supported for Samsung for Enterprise (SAFE) devices only.

• Click 'Other Restrictions' from the 'Add Profile Section' drop-down



Other Restrictions Settings - Table of Parameters				
Form Element	Туре	Description		
Allow USB	Checkbox	Allows users to establish connections via USB ports.		
Use Network Time	Checkbox	Allows users to enable/disable network provided values in Date & Time		



Other Restrictions Settings - Table of Parameters		
		settings.
Allow Microphone	Checkbox	Allows users to use microphone. If this is disabled, users can use microphone for receiving and making calls only.
Allow Near Field Communication (NFC)	Checkbox	Allows devices to establish connection via NFC
Allow Mock Locations	Checkbox	Allows users to enable/disable 'Mock Location' in developer mode settings.
Allow SD Card	Checkbox	Users can use SD card on their devices.
Allow SD Card Write	Checkbox	Users can store data on the SD card.
Allow Screen Capture	Checkbox	Users can take screenshot of the device screen.
Allow Clipboard	Checkbox	Users will be allowed to use clipboard memory.
Backup my data	Checkbox	Users will be allowed to take a backup of data in their devices.
Visible Passwords	Checkbox	Allows users to enable/disable show password feature.
Allow USB Debugging	Checkbox	Allows users to enable/disable 'USB Debugging' option in developer mode settings.
Allow Factory Reset	Checkbox	Allows users to reset the device to factory settings.
Allow OTA Upgrade	Checkbox	Allows devices to receive Over-the-air (OTA) upgrade for software updates.

The settings are saved and shown under 'Other Restrictions' tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

6.1.2. Profiles for iOS Devices

iOS profiles let you specify a device's network access rights, restrictions and other general settings.

Process in Brief:

- Click 'Configuration Templates' > 'Profiles'
- Click 'Create' > 'Create iOS Profile'
- Type a name and description for your profile then click the 'Create' button. The profile will now appear in 'Configuration Templates' > 'Profiles'.
- New profiles have only one section 'General'. Click 'Add Profile Section' to add settings for various security and management features. Each section you add will appear as a new tab.
- Once you have fully configured your profile you can apply it to devices, device groups, users and user groups.




You can make any profile a 'Default' profile by selecting the 'General' tab then clicking the 'Edit' button.

This part of the guide explains the processes above in more detail, and includes in-depth descriptions of the settings available for each profile section.

Create an iOS profile


- Click 'Configuration Templates' > 'Profiles'
- Click the 'Create' button > 'Create iOS Profile':



- Enter a name and description for the profile
- Click the 'Create' button

The new profile will open at the 'General Settings' section:






- The profile is not a 'default' profile at this stage. A 'default' profile is one that is applied automatically to any device which matches its operating system. You can have multiple 'default' profiles per operating system.
- Click the 'Make Default' button if you want this profile to be a default.
 - Alternatively, click the 'Edit' button on the right of the 'General' settings screen and enable 'Is Default'.
- Click 'Save'.

The next step is to add profile sections.


- Each profile section contains a range of settings for a specific management feature.
- For example, there are profile sections for 'Email', 'Single Sign-On', 'LDAP', 'Cellular Networks' and so on.
- You can add as many different sections as you want when building your device profile.
- To get started:
 - · Click 'Add Profile Section'
 - Select the component that you want to include in the profile:





- · Configure the component as required
- Click 'Save'
- This add a new tab for the component to the profile:





The following links explain more about each section:

- Air Play
- Air Print
- APN
- Calendar
- Cellular Networks
- Certificate
- Contacts
- Active Sync
- Global Proxy HTTP
- LDAP
- E-Mail
- Passcode
- Proxy
- Restrictions
- Single Sign-On
- Subscribed Calendars
- VPN
- Per -App VPN
- Web Clip




- Wi-Fi
- App Lock

AirPlay settings

These settings let you whitelist devices which can play content from managed iOS devices via Apple Airplay. Example devices are televisions, monitors, stereo systems.

Note: If you do not create a whitelist then managed mobile devices will be able to broadcast to any Airplay capable device.

• Click 'Air Play' from the 'Add Profile Section' drop-down The 'Air Play' settings screen will be displayed.



AirPlay Settings Configuration - Table of Parameters		
Form Element	Туре	Description
White List Devices ID	Text Field	Enter the identifier of the output device that you want to whitelist for Air Play. The ID numbers of the devices should be entered in the format as given below:
		XX:XX:XX:XX:XX
		Note: The whitelist is applicable for supervised iOS 7+ devices and will not apply for all other devices.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
		Click the button to add more 'Device ID' fields.
		Click beside an item to remove it from the list.
Device Name	Text Field	Enter the name of the Air Play output device that you entered above. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables. Click the 'Add' button to add more devices
		Click the seside a device name to remove it from the list.



AirPlay Settings Configuration - Table of Parameters		
Password	Text Field	Enter the password for the AirPlay destination that you entered above.
Add	Button	Click this button to add another 'Devices' section.

The 'Air Play' device is added to the list.



You can add multiple Air Play devices to the profile.


- Click 'Add Air Play' to add more devices
- Click a device name to edit its settings

You can edit the settings or remove the section from the profile at anytime. See Edit Configuration Profiles if you

AirPrint settings

These settings let you specify the default printer your devices use with the 'Air Print' feature.

Click 'Air Print' from the 'Add Profile Section' drop-down



Form Element	Туре	Description
IP Address	Text Field	Enter the network address of the Air Print printer you wish to use.
Resource Path	Text Field	Enter the resource path of the printer, for example, printers/ HP_LaserJetPro_M1136_series.




Form Element	Туре	Description
Add	Button	Click this button to add another AirPrint section.

You can add more printers by repeating the process. To remove a printer, click the 'X' button beside the printer.

Click the 'Save' button.

The printer will be added to the list.




- Click 'Add Air Print' and repeat the process to add more printers,
- Click the name of a printer to view and edit its settings of a printer.

You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

APN settings

Note: APN settings have been deprecated in favor of cellular settings in iOS 7 and above.

Click 'APN' from the 'Add Profile Section' drop-down





Form Element	Туре	Description
Access Point Name (APN)*	Text Field	Enter the name of the GPRS access point provided by the cellular service provider.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Access Point User Name /	Text Fields	Enter the login of the APN account to connect to the access point.
Access Point Password		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Proxy Server / Proxy Port	Text Field	Enter the host name and connection port of the proxy server.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.


Fields marked * are mandatory.

· Click the 'Save' button.

You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Calendar settings

Click 'Calendar' from the 'Add Profile Section' drop-down





Form Element	Description
Account Description	Enter the display name of the CalDav account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Host Name*	Enter the CalDav host name or IP address.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Port	Enter the port number on which to connect to the server.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
CalDav Account	The user name of the CalDav user.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Password	The password for the CalDav account. Leave the field blank. The user will be prompted to enter the password while configuring the account for the first time. After it is validated, the users can access the account without entering the credentials.
Use SSL	If enabled, SSL connection will be established with the CalDav server.
Principal URL	The URL of the CalDav account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.

Fields marked * are mandatory.

• Click the 'Save' button after entering or selecting the parameters.

The calendar account host will be added to the list.



- · Click 'Add Calendar' to add more calendar servers
- Click the host name of a calendar server to view and edit its settings


You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Cellular Network settings

Note: A cellular network setting cannot be applied if an APN setting is already installed. This feature is available for iOS 7 and later versions only.

Click 'Cellular Networks' from the 'Add Profile Section' drop-down





Form Element	Туре	Description
Name	Text Field	Enter the name for this configuration, specifying the cellular service provider.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Authentication Type	Drop- down	Select the user authorization type used by the service provider. The options are CHAP or PAP.
Username / Password	Text Field	Enter login credentials for the provider network. This is required to authenticate the request.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
APNs		






· Click 'Save' .

This will add a 'Cellular Networks' tab to the profile. You can edit the settings or remove the section at anytime. See **Edit Configuration Profiles** if you want help with this.

Certificate settings

The certificate settings area lets you upload certificates which can be used to secure other aspects of Endpoint Manager. For example, you can select your uploaded certificates in the 'Wi-Fi, 'Exchange Active Sync' and 'VPN' areas.

Click 'Add profile section' > 'Certificate'



Form Element	Description
Name	Enter a label for the certificate.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Description	Enter an appropriate description for the certificate.
Data	Click 'Browse' and upload you certificate. Supported extensions - 'p12'. 'pub', '.crt', '.key'.
Password	Enter the password for importing the certificate.

Click the 'Save' button.

The certificate will be added to the certificate store.




- Click 'Add Certificate' and repeat the process to add more certificates.
- Click on the name of a certificate to view the certificate key and edit its name.

You can add any number of certificates to the profile and remove certificates at anytime. See **Edit Configuration Profiles** for more details.

Contacts settings

· Click 'Contacts' from the 'Add Profile Section' drop-down



Form Element	Description
Account Description	Enter the display name of the CardDav account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Host Name* / Account Port*	Enter the CardDav server details. This includes hostname / IP address and server port.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Username / Account	The login credentials of the CardDav user account.
Password	Click the variables button to insert dynamic values. See Create



Form Element	Description
	and Manage Custom Variables for more details on variables.
Use SSL	If enabled, a secure SSL connection will be used for communications with the CardDav server.
Principal URL	Enter the 'Principal URL' of the CardDav account.

Fields marked * are mandatory.

• Click the 'Save' button after entering or selecting the parameters.

The contact account is added to the list.



You can add multiple contacts accounts to the profile.


- · Click 'Add Contacts' and repeat the process to add more accounts
- Click the hostname of the contact account to view or edit its details

The settings will be saved and shown under 'Contacts' tab. See Edit Configuration Profiles for more details.

ActiveSync settings

• Click 'Add Profile Section' > 'ActiveSync Settings'





Form Element	Description
Account Name	Enter the Exchange ActiveSync account name.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Exchange ActiveSync host*	Enter the Exchange host name (Microsoft Exchange Server).
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Allow Move	If enabled, the user can move sent or received mails to another account.
Disable Mail Recent Syncing	If enabled, recently used emailed addresses are not synced with other devices via iCloud.
Prevent App Sheet	If enabled, mails cannot be sent using third-party applications.
Use SSL	If enabled, communication between Exchange server and devices will be encrypted using SSL.
S/MIME Enabled	If enabled, users can sign and encrypt email messages from their devices. Please note that certificates have to be installed in users' devices before this feature can be used.
Domain	Email domain name.
	Click the 'Variables' button and click beside '%u.mail' from the 'User Variables' list. The email address of the users to whom the profile is associated will be automatically filled. For more details on variables, see Create and Manage Custom Variables.




Form Element	Description
User Name	User name for the account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Email Address	Address of the account. Click the 'Variables' button and click beside '%u.mail' from the 'User Variables' list. The email address of the users to whom the profile is associated will be automatically filled. For more details on variables, see Create and Manage Custom Variables.
Password	Leave the field blank. The user will be prompted to enter the password while configuring the email account for the first time. After it is validated, the users can access the email account without entering the password.
Past days of mail to sync	Choose the period for which the emails are to be kept synchronized between the device and the exchange server from the recent past, from the drop-down.
User Certificate	Select the user client authentication certificate from the drop-down or upload it using the 'Add New' button.

This will add the ActiveSync section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Global HTTP proxy settings

Click 'Add Profile Section' > 'Global Proxy HTTP'



Form Element	Description
Name	Enter the host name of the proxy you want devices to use.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.

ITarian Endpoint Manager - Administrator Guide



Form Element	Description
Proxy type	Select the proxy type from the drop-down. The options available are: None Manual Auto If you select 'Manual', enter the IP address of the proxy server, proxy server port, proxy username and proxy password in the respective fields. If you select 'Auto', enter the URL of the Proxy Pac, select whether or not the device can directly connect to the destination if Pac server is not reachable and whether or not the device can bypass the proxy server to display the login page for captive networks from the respective check box options.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.


Click the 'Save' button.

This will add a 'Global Proxy HTTP' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

LDAP settings

Click 'Add Profile Section' > 'LDAP'





Form Element	Description
Account description	Enter the display name of the LDAP account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account hostname	Enter the hostname or IP address of the AD server.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Account Username / Account	Login credentials for the LDAP account.
Password	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Use SSL	If enabled, the communication will be encrypted.
Search settings	Configure the settings for searching email contacts from the LDAP server. See



Form Element	Description
	'Search the LDAP directory' below for more details.

Search the LDAP directory

Admins can search for email contacts in the domain using the search feature.



LDAP Search Settings - Table of Parameters		
Form Element	Туре	Description
Description	Text Field	Enter the name of the search
Scope	Drop-down	Level of search on the LDAP tree structure. Base - Searches only the defined search base. One level - Searches the base and the first level below it. Subtree - Searches the base and all levels below.
Search base	Text Field	Enter the search base for which the search will be restricted. For example, you might want to allow users to search only for other email users via LDAP.

- You can add more search settings by clicking the Add button .
- To remove an item, click the * button.
- · Click the 'Save' button.

The LDAP account will be added to the list.






You can add multiple LDAP accounts.

- Click 'Add LDAP' and repeat the process to add more LDAP servers
- · Click the hostname of an LDAP account to view and edit its settings

This will add a 'LDAP' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Email settings

Click 'Add Profile Section' > 'E-mail'





Form Element	Description
Email Account Description	Enter a label for the email account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Allowed values are email type POP and email type IMAP *	Select the mail protocol. Possible values are IMAP and POP.
Path Prefix	This will be visible if IMAP is chosen as Email Type in the previous step. Enter the path of the inbox in the field.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Email account name	Enter a label to identify the user's email account at the incoming mail server, if the profile is for a single user.
	Click the variables button to insert dynamic values if the profile is for several users.
	See Create and Manage Custom Variables for more details on variables.
	The email address of the users to whom the profile is associated will be automatically added to the profile while rolling out the same to the devices.
Email address	Enter the email address of the user at the incoming mail server If the profile is for a single user.
	Click the variables button to insert dynamic values if the profile is for several users.
	The email address of the users to whom the profile is associated will be automatically added to the profile while rolling out the same to the devices.
	See Create and Manage Custom Variables for more details on variables.
Allow Move	If enabled, the user can move sent or received mails to another account.
Designates the incoming mail	Enter the host name of the incoming mail server or its IP address.
server host name (or IP address)*	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Designates the incoming mail server port number*	Enter the server port number used for incoming mail service. For POP3, it is usually 110 and if SSL is enabled it is 995. For IMAP, it is usually 143 and if SSL is enabled it is 993.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Incoming mail server username	Enter the username for the email account of the user at the incoming mail server if the profile is for a single user.
	Click the variables button to insert dynamic values if the profile is for several users.
	See Create and Manage Custom Variables for more details on variables.
	The email usernames of the users to whom the profile is associated will be automatically added to the profile while rolling out to the devices.
Allowed values are email auth	Select the type of authentication method for the mail account from the drop-



Form Element	Description
password and email auth none *	down. The options available are:
	None
	Password
	CRAM MD5
	• NTLM
	HTTP MD5
Incoming password	Leave the field blank. If authentication is chosen in the previous step, then user needs to enter the password while configuring the email account for the first time. After it is validated, the users can access the email account without entering the password.
Incoming mail server use SSL	If enabled, communication between incoming mail server and devices is encrypted using SSL.
Outgoing mail server host name*	Enter the host name or IP address of the outgoing (SMTP) mail server for a single user.
	Click the variables button * Variables to insert dynamic values if the profile is for several users.
	See Create and Manage Custom Variables for more details on variables.
Designates the outgoing mail server port number*	Enter the server port number used for outgoing mail service. If no port number is specified then ports 25, 587 and 465 are used in the given order.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Outgoing mail server username	Enter the username for the email account of the user at the outgoing (SMTP) mail server if the profile is for a single user.
	Click the variables button to insert dynamic values if the profile is for several users.
	See Create and Manage Custom Variables for more details on variables.
	The email usernames of the users to whom the profile is associated are automatically added to the profile while rolling out to the devices.
Outgoing mail server authentication*	Select the type of authentication method for outgoing mail server from the drop-down. The options available are:
	None
	Password
	CRAM MD5
	• NTLM
	HTTP MD5
Outgoing password	Leave the field blank. If authentication is chosen in the previous step, then user needs to enter the password while configuring the email account for the first time. After it is validated, the users can access the email account without entering the password.
Outgoing password same as incoming password	If enabled, the password for incoming mail server will be used for outgoing mail server too.



Form Element	Description
Disable email recents syncing	If enabled, recently used emailed addresses are not synced with other devices via iCloud.
Signing and encryption permessage	If enabled, the device digitally signs and encrypts your mail per-message.
Prevent App Sheet	If enabled, outgoing mails can be sent from this account only via mail app.
Outgoing mail server Use SSL	If enabled, communication between outgoing mail server and devices is encrypted using SSL.
S/MIME enabled	If enabled, users can sign and encrypt email messages from their devices. Please note that certificates have to be installed in users' devices before this feature can be used.

The e-mail account will be added to the profile.



You can add several email accounts to the same profile.


- Click 'Add Mail' and repeat the process to add more email accounts.
- Click the name of an email account to view and edit its settings

You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Passcode settings

Click 'Passcode' from the 'Add Profile Section' drop-down





Form Element	Description
Allow simple value	Allows users to use repeated or sequential characters in their passwords. For example, '9999' or ABCD.
Require alphanumeric value	Compels users to use at least one number or letter in their passwords.
Minimum passcode length	The minimum number of characters that a password should contain. The option is available to set from 1 to 16.
Minimum number of complex characters	The minimum number of symbols (non alphanumeric characters such as *, %, @) that a password should contain. The option is available to set from 1 to 4.
Maximum passcode age	Enter the maximum number of days that a password can be valid. The availble option is from 1 day to 730 days. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Maximum idle time	Select the period of time in minutes that a device can be idle before it's screen is automatically locked.
Passcode history	New passwords should not match previously used passwords. Specify the number of last used passwords that should be stored for comparison.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Maximum grace period for device lock	Select the period from the drop-down how soon the device can be unlocked since last used without prompting the user to enter the password. The option is




Form Element	Description
	available from 'Immediately' to '4 Hours' If 'Immediately' is selected, the user has to enter the password each time the device is unlocked.
Maximum number of failed attempts	Select the number of unsuccessful login attempts that can be tried by a user before the device is wiped clean of all its data and settings. The option is available to set from 4 to 10. After 6 unsuccessful login attempts, there will be a time delay before a password can be entered again and the time delay period increases with each failed login attempt. This time delay begins only after the sixth attempt, so if you select the period as 6 or lower, there will be no time delay and data will be erased after the final attempt.
Allows the user to modify Touch ID	If enabled, allows user you to modify the biometric authentication to unlock your device, make purchases and so on.

- Click 'Save'.
- You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Proxy settings

Click 'Proxy' from the 'Add Profile Section' drop-down



Form Element	Description
	Enter a label for the proxy to be shown to the device users. Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.



Form Element	Description
Proxy	Select the proxy type from the drop-down. The options available are: None Manual Auto If you select 'Manual', enter the details for IP address of the proxy server, proxy server port, proxy username and proxy password in the respective fields. If you select 'Auto', enter the URL of the Proxy Pac. Click the variables button Variables to insert dynamic values. See Create and Manage Custom Variables for more details on variables.

The proxy server configuration is added to the profile.



You can add more proxy server accounts to the profile.

- Click 'Add Proxy' and repeat the process to add more proxy server accounts.
- Click the name of a proxy server account to view or edit its details.


This will add a 'Proxy' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Restrictions settings

Click 'Restrictions' from the 'Add Profile Section' drop-down

ITarian Endpoint Manager - Administrator Guide





Device Functionality	
Form Element	Description
Allow installing apps	The user can install or update apps from the Apple App Store. If left unchecked, the App Store icon is removed from the device's home screen.
Allow app uninstall	The user can to uninstall applications.
Allow use of the iMessage	The user can quickly and easily chat over iMessage or SMS/MMS.
Allow camera	The user can to take photos, videos or use FaceTime (if enabled). If left unchecked, the camera icon is removed from the device and camera is disabled.
Allow face time	The user can use FaceTime. Please note the 'Allow face time' can be enabled only if 'Allow Camera' is enabled.
Allow Personal Hotspot	Allows users to setup Wi-Fi hot-spots from their device, and allow other devices to connect.
Allow screen shot	Allows users to take screenshots on their device.
Allow global background fetch when roaming	Select this to allow the device to sync data when in roaming mode abroad.
Allow assistant	If enabled, users can use Siri voice commands and dictation.
Allow assistant while Locked	If enabled, users can use Siri even when the device is locked. The checkbox will be active only when 'Allow Assistant' is enabled.
Allow assistant user generated content	If enabled, users can use Siri to query user-generated content from the Internet or device. (Supervised mode only.)



Forces the use of the profanity filter assistant	If enabled, enforces profanity filter for Siri.
Allow voice dialing	Select this to allow the user to dial their phone using voice commands.
Allow passbook while locked	If enabled, Passbook notifications will be displayed even when the device is locked.
Allow in app purchases	Select this to allow the user to make in-app purchases from the device.
Force iTunes store password entry	If enabled, users have to enter their Apple ID to enter the iTunes store.
Allow multiplayer gaming	Select this to allow the user to play multiplayer games in Game Center.
Allow adding Game Center friends	If enabled, users can add friends in Game Center.
Allow account modification	Select this to allow user account modifications on devices. Note: This feature is available for iOS 7+ and supervised devices only.
Allow air drop	Select this to allow Air Drop on devices.
	Note: This feature is available for iOS 7+ and supervised devices only.
Allow find my friends modification	Select this to enable Find My Friends feature on devices. Note: This feature is available for iOS 7+ and supervised devices only.
Allow fingerprint for unlock	Select this to enable Touch ID to unlock devices. Note: This feature is available for iOS 7+ and supervised devices only.
Allow Game Center	If enable, users can access Game Center, an online multiplayer social gaming network. Note: This option is available for supervised devices only.
Allow host pairing	Select this to allow host pairing on devices.
	Note: This feature is available for iOS 7+ and supervised devices only.
Allow lock screen control center	Select this option to allow Control Center to be displayed in the lock screen.
	Note: This feature is available for iOS 7 and later versions.
Allow lock screen notifications view	Select this option to allow Notification Center to be displayed on the lock screen.
	Note: This feature is available for iOS 7 and later versions.
Allow lock screen today view	Select this option to allow the Today View from Notification Center to be displayed in the lock screen.
	Note: This feature is available for iOS 7 and later versions.
Allow OTAPKI updates	Select this option to allow over-the-air public key infrastructure (OTAPKI) updates on the device.
	Note: This feature is available for iOS 7 and later versions.
Allow UI configuration profile installation	Select this option to allow users to install UI configuration profiles. Note: This option is available for supervised devices only.
Earge limit ad tracking	·
Force limit ad tracking	Select this to limit ad tracking on devices. Note: This feature is available for iOS 7 and later versions.



os 10.3 vices data to edit or debit n the I any file,
data to edit or debit n the I any file,
edit or debit n the I any file,
n the I any file,
l any file,
option in the vices only.)
tion to
and
h iOS 8 and
nd definition
h iOS 8.1.3
rd feature. ly with iOS
ct feature. h iOS 8.1.3
k feature. h iOS 8.1.3
the Apple



Allow music service and music	If enabled, it allows third-party apps to add music to user's iCloud music library.
	Note: This feature is available for iOS 9.0 and later versions.
Allow iCloud Photo Library	If enabled, allows the user to upload photos and videos to iCloud photo library.
Allow News	If enabled, users can subscribe to news services.
	Note: This feature is available only for supervised devices with iOS 9.0 and later versions.
Causes AirDrop to be considered an unmanaged drop target	If enabled, all targets specified for the AirDrop feature will be considered as unmanaged drop targets.
	Note: This feature is available for iOS 9.0 and later versions.
Enable the App Store on the home screen	If enabled, displays the AppStore icon on the home screen of the device.
Allow keyboard shortcuts	If enabled, allows the user to create and use keyboard shortcuts for typing snippets.
	Note: This feature is available only for Supervised devices with iOS 9.0 and later versions.
Allow pairing with an Apple Watch	If enabled, allows the user to pair the device with an Apple Watch.
	Note: This feature is available only for Supervised devices with iOS 9.0 and later versions.
Allow device passcode from being added, changed, or removed	If enabled, users can create and modify screenlock passcodes for the device.
	Note: This feature is available only for supervised devices with iOS 9.0 and later versions.
Allow device name modification	If enabled, allows users to change the device name.
	Note: This feature is available for only Supervised devices with iOS 9.0 and later versions.
Allow wallpaper modification	If enabled, allows user to change wallpaper displayed on the device.
	Note: This feature is available only for supervised devices with iOS 9.0 and later versions.
Allow automatic download applications	If enabled, allows applications in the device to automatically download and install apps and updates.
	Note: This feature is available only for supervised devices with iOS 9.0 and later versions.
Allow enterprise application trust	If enabled, 'Trusted' status is automatically applied to enterprise applications.
	Note: This feature is available for iOS 9.0 and later versions.
Allow enterprise application trust modification	If enabled, users can manually change the Trust status of enterprise applications.
	Note: This feature is available only for Supervised devices with iOS 9.0 and later versions.
Allow radio service	If enabled, users can use Radio services on their device.



	Note: This feature is available only for Supervised devices with iOS 9.3 and later versions.	
Allow notifications modification	If enabled, user can modify 'Apple Push Notifications' settings on the device.	
	Note: This feature is available only for Supervised devices with iOS 9.3 and later versions.	
Whitelisted application bundles	Add applications to the app whitelist. The applications in the whitelist will be skipped from security checks during installation and usage.	
	 Enter the App bundle ID of the application to be added to the whitelist. 	
	For more details on obtaining the App bundle ID, see the explanation at the end of this section.	
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.	
	Click the button to add more apps to the whitelist.	
	 Click beside an app to remove it from the list. 	
	Note: This feature is available only for supervised devices with iOS 9.3 and later versions.	
Blacklisted application bundles	Add applications to the app blacklist. The applications in the blacklist will not be allowed to be installed or used.	
	Enter the App bundle ID of the application to be added to the blacklist.	
	For more details on obtaining the App bundle ID, see the explanation at the end of this section.	
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.	
	Click the button to add more apps to the blacklist.	
	Click beside an app to remove it from the list.	
	Note: This feature is available only for Supervised devices with iOS 9.3 and later versions.	
	Security and privacy	
Allow diagnostic submission	If enabled, the device will be enabled to submit its iOS diagnostic information to Apple.	
Allow untrusted TLS prompt	If enabled, users will be prompted if they want to trust unverified certificates.	
	This setting applies to Calendar accounts, Contacts, Safari and to Mail.	
Force encrypted backup	If left unchecked, users can select whether or not to encrypt backups from the device to iTunes in a local computer.	
	If this option is enabled, the backup data from the device to iTunes in local computer will be automatically encrypted.	
Content ratings		
Allow explicit music and podcasts	Content providers of iTunes flag their explicit content for easy	



	identification.
	If enabled, explicit content including music and video will be displayed in iTunes store instead being hidden, in the device.
Allow iBookstore	If enabled, users can access iBookstore, an online bookstore from Apple.
	Note: This option is available only for supervised devices.
Allow iBookstore erotica	If enabled, users can download media tagged as erotica from iBooks.
	Note: This feature is available only for Supervised devices with versions prior to iOS 6.1.
Rating region	Select the region whose content ratings are to be followed, from the drop-down.
Rating movies	Choose the content rating to be allowed for watching movies.
Rating TV Shows	Choose the content rating to be allowed for watching the TV shows.
Rating apps	Choose the rating to be allowed for using apps.
	Applications
Allow use of iTunes Store	If enabled, users can access iTunes store. If left unchecked, iTune store is disabled and its icon will be removed from the home screen.
Allow Safari	If enabled, users can use Safari for browsing internet. If left unchecked, the Safari browser app will be disabled and its icon will be removed from the home screen.
Allow auto fill	If enabled, the 'auto-fill' feature will be enabled for Safari, to automatically fill details such as user name, password, credit card details and so on in web forms.
Allow java script	If enabled, java script features will be supported by Safari.
Allow popups	If enabled, popups will be allowed in Safari.
Force fraud warning	If enabled, Safari displays alerts to users when visiting websites that are identified as compromised or fraudulent.
Accept cookies	Select the option on when Safari can accept cookies, from the drop-down. The available options:
	Always
	Never
	From visited site
Allow app cellular data modification	If enabled, user can modify cellular data usage settings for individual apps on the device.
	Note: This feature is available only for Supervised devices with iOS 7 or later versions.
Allow open from Managed to Unmanaged	If enabled, users can send data from managed apps to unmanaged apps.
	Note: This feature is available for iOS 7 and later versions.
Allow open from Unmanaged to Managed	If enabled, users can send data from unmanaged apps to managed

ITarian Endpoint Manager - Administrator Guide



	apps.
	Note: This feature is available for iOS 7 and later versions.



Autonomous single app mode permitted app bundle IDs	iOS apps built with the functionality of single App Lock, can provoke App Lock for them under certain scenarios in Autonomous single app mode. Administrators can specify the apps for which the mode can be enabled, by entering their App bundle IDs. • Enter the App bundle ID of the application to be permitted for		
	autonomous single app mode.		
	For more details on obtaining the App bundle ID, see the explanation at the end of this section.		
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.		
	To add more apps, click button.		
	To remove an app, click the beside it.		
	Note: This feature is applicable only for Supervised devices with iOS 7 or later versions.		
	iCloud		
Allow cloud keychain sync	If enabled, the Apple Keychain data on the device will be synced to iCloud.		
	Note: This feature is applicable only for iOS 7 and later versions.		
Allow cloud backup	If enabled, users can backup their device data to iCloud.		
	Note: This feature is applicable only for iOS 7 and later versions.		
Allow cloud document sync	If enabled, users can synchronize documents on their device with iCloud.		
	Note: This feature is applicable only for iOS 7 and later versions.		
Allow photo stream	Users can use Photo Stream.		
	Note: This feature is applicable only for iOS 7 and later versions.		
<u></u>			
Allow shared stream	If enabled, users can share and view photos in Photo Stream.		




You can edit the settings or delete the section at any time. See Edit Configuration Profiles for more details.

Single Sign-On settings

These settings are used to configure Kerberos authentication and are applicable for iOS 7 or later versions only. You can add several Single Sign On accounts to a profile.

• Click 'Single Sign-On' from the 'Add Profile Section' drop-down




Form Element	Description
Name*	Enter a label for the account.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Principal name*	Enter the Kerberos principal name.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Realm*	Enter the Kerberos realm name with upper-case characters.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
URL prefix matches*	Enter the URL prefix, which must be matched in order to use this account for Kerberos authentication over HTTP.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.



Form Element	Description
	Click the button to add more 'URL prefix matches' fields. Click the button beside an item to remove it from the list.
App identifier matches	Enter the bundle IDs of apps that are allowed to use this Single Sign-On account for logging-in to respective account. If this field is left blank, this login matches all app bundle IDs.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Click the button to add more 'App identifier matches' fields. Click the button beside an item to remove it from the list.

The account will be added to the Single Sign-On section of the profile.



You can add several SSO accounts to the profile.


- Click 'Add Single Sign-On' and repeat the process to add more SSO accounts
- Click the name of an account to view and edit its details

This will add a 'Single Sign-On' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Subscribed Calendar settings

• Click 'Subscribed Calendars' from the 'Add Profile Section' drop-down






Form Element	Description
Description	Enter a description of the calendar subscription.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
URL*	Enter the URL of the calendar account to be subscribed.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Username	The user name for the subscription.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Password	The password for the subscription. Leave the field blank. The user will be prompted to enter the password while configuring the account for the first time. After it is validated, the users can access the account without entering the credentials.
Use SSL	If enabled, SSL connection will be established with the calendar server, if available.

Click the 'Save' button.

The calendar account will be added.






You can add several calendar accounts for a profile.

- Click 'Add Subscribed Calendars' and repeat the process to add more calendar accounts.
- Click the host name of a calendar account to view and edit its details.

This will add a 'Subscribed Calendar' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

VPN settings

Click 'Add Profile Section' > 'VPN'





Form Element	Description
User name	Enter a label for the connection. This is shown on the device.
	Click the variables button to insert dynamic values here. See Create and Manage Custom Variables.
Connection type*	Options available are: L2TP PPTP IPSec Cisco Any Connection Juniper SSL F5 SSL Open VPN The connection parameters for each type are explained in the table below.
Proxy	This drop-down shows any proxies you added to the proxy settings section of the profile. • Choose the proxy you want the device to use. See Proxy settings if you want help to add a new proxy.

VPN Connection Type settings

Connection Type	Description
L2TP	Override primary - Force VPN for all connections, including those to external domains:
	Enabled - All traffic to and from the device passes through the VPN.
	 Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection.
	Server - Enter IP address or host name of the VPN server. Click the variables button to insert dynamic values here.
	Account - Enter the VPN account user name. Click the variables button to insert dynamic values here.
	User authentication protocol - Select the authorization type the device uses to connect to the VPN server. The available options are 'Password' and 'RSA SecurID'.
	Password - If 'Password' is selected in 'User authentication protocol', enter the VPN account password. Click the variables button to insert dynamic values.
	Token Card - Select this if you have chosen 'RSA SecurID' in "User authentication protocol'.
	Auth EAP plugins - Applies only if RSA SecurID is being used. Enter the 'EAP-RSA' value. Click the variables button to insert dynamic values here
	Shared secret - Applies only i if RSA SecurID is being used. Click the variables button to insert dynamic values here



Connection Type	Description
	For more details on variables, see Create and Manage Custom Variables.
PPTP	Override primary- Force VPN for all connections, including those to external domains: Enabled - All traffic to and from the device passes through the VPN. Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection. Server - Enter the IP address or host name of the VPN server. Click the variables button to insert dynamic values here. Account - Enter the VPN account user name. Click the variables button to insert dynamic values here User authentication protocol - Select the authorization type the device uses to connect to the VPN server. The available options are 'Password' and 'RSA SecurID' Password - If 'Password' is selected, enter the VPN account password. Click the variables button Token Card - Select this if you have chosen 'RSA SecurID' in 'Auth Protocol'. Authentication EAP plugins - Applies only if RSA SecurID is being used. Enter the 'EAP-RSA' value. Click the variables button Token Card - Select the encryption level you want to use for the VPN connection. The available options are: None Automatic Maximum 128 bit encryption Shared secret - Applies only if RSA SecurID is used. Enter the shared secret string. Click the variables button to insert dynamic values here
15.050	For more details on variables, see Create and Manage Custom Variables.
IP SEC	Override primary - Force VPN for all connections, including those to external domains: • Enabled - All traffic to and from the device passes through the VPN. • Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection. Server - Enter the IP address or host name of the VPN server. Click the variables button • Variables to insert dynamic values here Account - Enter the VPN account name. Click the variables button • Variables to insert dynamic values here Password - Enter the password for the account. Click the variables button • Variables to insert dynamic values here Authentication Method - Select the authorization type the device uses to connect to the VPN server. • Shared secret / Group name - Enter the shared secret string or the group



Connection Type	Description
	name.
	Certificate - If you want client certificate type authentication, choose this option and configure the parameters as given below:
	 Password encryption - Enter a password to be used as key to encrypt the communication.
	 Prompt for VPN PIN - The user needs to enter the VPN PIN while connecting.
	 On demand enabled - Create rules for auto-establish the VPN connection based on the domains accessed. You can create a list of domains and specify the VPN connection establishment type for each domain.
	 Certificate - Shows certificates uploaded for the profile. Select the client certificate you want to use for authentication. See the explanation of adding certificates to the profile for more details. Click 'Add New' to upload the a new certificate.
	 Domain and Type fields - Add a list of domains and specify VPN connection type for each domain, if 'On demand enabled' is selected.
	 Enter a domain name in the domain field and choose the connection type:
	Always establish - Initiates a VPN connection for the domain.
	Never establish - No VPN connection is created for the domain.
	Establish if needed - A VPN connection is created if domain name resolution fails.
	Click 'Add' to add the domain to the list
	Repeat the process to add more domains
	For more details on variables, see Create and Manage Custom Variables.
Cisco Any Connection and F5 SSL	Override primary- Force VPN for all connections, including those to external domains:
	Enabled - All traffic to and from the device passes through the VPN.
	 Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection.
	Remote Address - Enter the IP address or host name of the VPN server. Click the
	variables button to insert dynamic values here
	Auth name - Enter the VPN account name. Click the variables button to insert dynamic values here
	Authentication method - Select the authorization type the device uses to connect to the VPN server.
	Shared secret / Group name - Enter the shared secret string or the group name.
	Certificate -
	Id Certificate - Shows certificates uploaded for the profile. Select the client certificate you want to use for authentication. See the explanation of adding certificates to the profile for more details.
	On demand enabled - Create rules to auto-establish the VPN connection based on the domains accessed. You can create a list of domains and specify the VPN connection establishment type for each



Connection Type	Description
	 Domain and Type fields - Add a list of domains and specify VPN connection type for each domain, if 'On demand enabled' is selected. Enter a domain name in the domain field and choose the connection type: Always establish - Initiates a VPN connection for the domain. Never establish - No VPN connection is created for the domain. Establish if needed - A VPN connection is created if domain name resolution fails. Click 'Add' to add the domain to the list Repeat the process to add more domains. For more details on variables, see Create and Manage Custom Variables.
Juniper SSL	Override primary - Force VPN for all connections, including those to external domains: • Enabled - All traffic to and from the device passes through the VPN. • Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection. Remote Address - Enter the IP address or host name of the VPN server. Click the variables button • Variables Variables to insert dynamic values here. Auth name - Enter the VPN account user name. Click the variables button • Variables to insert dynamic values here Realm - Enter the name of the authentication server. Click the variables button • Variables to insert dynamic values here Role - Enter the role of the user. Click the variables button • Variables to insert dynamic values here Authentication method - Select the authorization type the device uses to connect to the VPN server. • Shared secret / Group name - Enter the shared secret string or the group name. • Certificate - • Certificate ID - Shows certificates uploaded for the profile. Select the client certificate you want to use for authentication. See the explanation of adding certificates to the profile for more details. • On demand enabled - Create rules to auto-establish the VPN connection based on the domains accessed. You can create a list of domains and specify the VPN connection establishment type for each domain. • Domain and Type fields - Add a list of domains and specify VPN connection type for each domain, if 'On demand enabled' is selected. • Enter a domain name in the domain field and choose the connection type: Always establish - Initiates a VPN connection for the domain. Never establish - No VPN connection is created if domain name



Connection Type	Description
	resolution fails.
	Click 'Add' to add the domain to the list
	Repeat the process to add more domains
	For more details on variables, see Create and Manage Custom Variables.
Open VPN	Override primary- Force VPN for all connections, including those to external domains:
	Enabled - All traffic to and from the device passes through the VPN.
	Disabled - The device accesses internal resources and intranet sites over the VPN, and external domains through a direct connection.
	Remote Address - Enter the IP address or host name of the VPN server. Click the
	variables button ** Variables** to insert dynamic values here.
	Certificate ID - The drop-down shows certificates uploaded for the profile. Select the client certificate you want to use for authentication. See the explanation of adding certificates to the profile for more details. Click 'Add New' to upload the a new certificate
	 Tip - You can extract the certificate in .p12 format, from the Open VPN configuration file (in .ovpn format) in the VPN server.
	Use the command "sh split-ovpn.sh config.ovpn"
	Upload the certificate to the profile
	On demand enabled - Create rules to auto-establish the VPN connection based on the domains accessed. You can create a list of domains and specify the VPN connection establishment type for each domain.
	 Domain and Type fields - Add a list of domains and specify VPN connection type for each domain, if 'On demand enabled' is selected.
	Enter a domain name in the domain field and choose the connection type:
	Always establish - Initiates a VPN connection for the domain.
	Never establish - No VPN connection is created for the domain.
	Establish if needed - A VPN connection is created if domain name resolution fails.
	Click 'Add' to add the domain to the list
	Repeat the process to add more domains
	Vendor config
	Key - The 'Key' string in the Open VPN server configuration file (in .ovpn format).
	Open the .ovpn file in a text editor like Notepad
	 Copy the content between the <key> tags, excluding 'BEGIN PRIVATE KEY' and 'END PRIVATE KEY', and paste into the 'Key' field</key>
	Value - The 'Value' string in the Open VPN configuration file
	 Copy the content from between the <value> tags, if present in the configuration file and paste into the 'Value' field similar to above. Else, leave this field blank.</value>
	Click 'Add' to add the vendor config to the list
	Repeat the process to add more vendor configurations.
	For more details on variables, see Create and Manage Custom Variables.



Click the 'Save' button.

The VPN connection will be added to the profile.



You can add several VPN accounts to the profile.


- Click 'Add VPN' and repeat the process to add more VPN accounts.
- Click the name of a VPN account to view and edit its settings

This will add a 'VPN' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Per-App VPN settings

Note: If you would like to connect only certain apps to VPN, then this feature allows you to configure the settings. This feature is available for iOS 7 and later versions.

Click 'VPN Per App' from the 'Add Profile Section' drop-down



- On Demand Match App Enabled Select this checkbox to enable per-app VPN connection.
- Safari domains Domains for which a VPN connection is established when visited through Safari browser.
 - Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.




- Click the button to add more domains in the field.
- Click the button to remove a domain from the list

For details on other settings please see 'VPN settings'.

Click the 'Save' button.

The VPN per App settings for the specified VPN server will be saved and added to the list.




You can add multiple VPN servers for the profile.

- Click 'Add VPN per App' and repeat the process to add more VPN accounts
- · Click on a VPN account name to view and edit its settings

This will add a 'Per-App VPN' section to the profile. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Web Clip settings

Click 'Web Clip' from the 'Add Profile Section' drop-down





Form Element	Description
Label*	Enter a name for the web clip.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
URL*	The website address visited when the clip is opened.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Is removable	If enabled, users can remove the Web Clip from their devices.
Pre composed	If enabled, the Web Clip icon will be displayed with no added visual effects.
Full screen	If enabled, the user can choose to view the Web Clip full screen mode.
Icon	Upload the image to be used as icon for the Web Clip.

· Click the 'Save' button.

The WebClip will be added to the list.



You can add multiple web clips for a profile.


- · Click 'Add Web Clip' and repeat the process to add more webclips
- · Click the name of a web clip to view and edit its settings

The settings will be saved and shown under the 'Web Clip' tab. You can add more web clips and edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

Wi-Fi settings

Click 'Wi-Fi' from the 'Add Profile Section' drop-down





Form Element	Description
SSID*	Enter a unique identifier (Service Set Identifier) of the wireless network that the device should connect to.
	Note: In iOS 7 and later versions, this is optional if the 'Domain Name' value is set.
Auto join	The device will automatically connect to the configured wireless network.
Hidden network	Select this option if the specified wireless network is hidden and not visible to Wi-Fi scans.
Encryption type	Select the type of encryption used by the wireless network from the drop-down. The available options are:
	None
	• WEP
	WPA / WPA2
	• Any
	WEP Enterprise
	WPA / WPA2 Enterprise
	Any (Enterprise)
	The Password field will appear if any of the options, 'WEP', 'WPA / WPA2' and 'Any' are chosen.
	If any of the Enterprise encryption type is chosen, then select the supported protocols and configure authentication. The options available are: TLS, LEAP,




	TTLS, PEAP, EAP-FAST, Use Pac, Provision pac and Provision Pac Anonymously, PAP, CHAP, MS CHAP ans MS CHAP V2
Password	Enter the password to connect to the Wi-Fi network. If left blank, the user will be prompted to enter the password when the device attempts to connect to the network.
Proxy	The proxy servers you added to the proxy settings section of the profile are available for selection in the 'Proxy' drop-down
	 Choose the proxy to be used by the device for connecting to internet through the Wi-Fi connection.
	You can also add new proxy servers:
	 Click the 'Add New' and specify the proxy server settings.
	Repeat the process to add more proxies
	See 'Proxy settings' for more help with this.
Is hotspot	If enabled, the network is treated as a hotspot.
Service provider roaming enabled	If enabled, devices can connect to roaming service providers.
Domain name	Enter the domain name of the Wi-Fi network to which the device has to connect.
	This is optional and can be provided instead of SSID.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Note: This feature is available for iOS 7 and later versions.
Displayed operator name	Enter the name of the Wi-Fi network provider, to be shown on the device to the user.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Note: This feature is available for iOS 7 and later versions.
Roaming consortium Ols	Enter the Roaming Consortium Organization Identifier of the Wi-Fi network provider to which the devices will connect to.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Click the button to add more Roaming Consortium Ols fields.
	Click the — to remove a field.
	Note: This feature is available for iOS 7 and later versions.
NAI Realm Names	Enter the Network Access Identifier (NAI) realm names used for Wi-Fi hotspot 2.0.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Click the button to add more NAI Realm Names.
	Click the — to remove a field.
	Note: This feature is available for iOS 7 and later versions.
	I .



Click the 'Save' button.

The Wi-Fi network will be added to the list.



You can add multiple Wi-Fi networks to the profile.


- Click 'Add Wi-Fi' and repeat the process to add more Wi-Fi networks
- Click the SSID of a WiFi network to view and edit its settings

This will add a 'Wi-Fi' section to the profile. You can edit the settings, add or remove Wi-Fi networks or remove the Wi-Fi networks at anytime. See **Edit Configuration Profiles** for more details.

App Lock settings

The 'App Lock' section allows you to restrict the ability of specific applications to use device resources. You can add only one application with app restriction settings for a profile. If you want to impose restrictions on several applications, create a profile for each and apply those profiles to the managed devices, as required.

Click 'App Lock' from the 'Add Profile Section' drop-down



Form Element	Description
Identifier	Specify the app to be included. You can add an Apple iTunes Store App or



Form Element	Description
	Enterprise App.
	Enter the App bundle ID of the application
	For more details on getting the App bundle ID of an application, see the explanation given below this table.
	Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
	Note : This feature is available for iOS 7 and later versions only.
Disable touch	Touch screen inputs will be disabled for the app.
Disable device rotation	The app will not be able to change display orientation.
Disable volume buttons	The app will not be able to modify device volume.
Disable ringer switch	Inputs through the ringer switch will be disabled for the app.
Disable sleep wake button	Inputs through the power/lock/wake button will be disabled for the app.
Disable auto lock	The device will not auto-lock when this app is running.
Enable voice over	Allows the user to use the voice over feature on the device for this app.
Enable zoom	Allows the user to zoom-in/zoom-out the display for this app
Enable invert colors	Allows the user to invert the colors for the display screens of this app.
Enable assistive touch	Allows the user to use the 'Assistive Touch' feature on the device for this app.
Enable speak selection	Allows the user to use the 'Speak Selection' feature on the device for this app.
Enable mono audio	Allows the user to choose mono mode for audio output of this app.
VoiceOver	Automatically switches ON the 'Voice Over' feature for the app.
Zoom	Automatically switches ON the 'zoom-in' feature for the app.
Invert colors	Automatically switches ON the 'Invert Colors' feature when the app is used.
Assistive touch	Automatically switches ON the 'Voice Over' feature when the app is used.

· Click Save after configuring the parameters and options

The settings will be saved and shown under 'App Lock' tab. You can edit the settings or remove the 'App Lock' section from the profile at anytime See **Edit Configuration Profiles** for more details.

Obtain App Identifier

App Store Application:

- Find the iTunes Store download URL of the app. Example: https://itunes.apple.com/us/app/cmdm/id807480077?mt=8.
- 2. Copy the number after the id in the URL. (Here it is: 807480077).
- 3. Open https://itunes.apple.com/lookup?id=807480077 where you replace the ID with the one you looked up.




4. Search the output for "bundleID". In this example: "bundleId": "com.comodo.cmdm.client". So the Bundle ID is com.comodo.cmdm.client

Enterprise Application:

The App bundle ID can be viewed from the App Details screen of the App.

- · Click 'Application Store' from the left and choose 'iOS Store'
- Click on the app from the list displayed at the right



6.1.3. Profiles for Windows Devices

Windows profiles let you specify settings for Comodo Client Security (CCS) installed on managed Windows devices. There are two ways you can add a Windows profile:

- Create a profile in the EM interface. See Create Windows Profiles for more details.
- Import a profile from an endpoint which is running CCS, or import from a stored configuration profile (.cfg file). See Import Windows Profiles for more details.


6.1.3.1. Create Windows Profiles

- Click 'Configuration Templates' > 'Profiles'
- Click 'Create' then 'Create Windows Profile'
- Type a name and description for your profile then click 'Create'
- The new profile appears in 'Configuration Templates' > 'Profiles'. Click the profile name to open its configuration screen.
- New profiles have only one section 'General'. Click 'Add Profile Section' to add settings for other sections.
 Each section you add will appear as a new tab.
- After you have created your profile you can apply it to devices, users and device groups/user groups.
- You can make any profile a 'Default' profile by selecting the 'General' tab then clicking the 'Edit' button.
 - A 'default' profile is one that is applied automatically to any device which matches its operating system. You can have multiple 'default' profiles per operating system.
- The rest of this section explains the processes above in more detail, and includes descriptions of each profile section.



Create a new profile


Click 'Configuration Templates' > 'Profiles' > 'Create' > 'Create Windows Profile':



- Enter a name and description for the profile
- · Click the 'Create' button

Your profile will open at its configuration page:





- Click 'Edit' if you wish to modify basic profile settings:
 - 'Is Default?' A 'default' profile is one that is applied automatically to any device which matches its operating system. You can have multiple 'default' profiles per operating system.
- Click 'Save'.


The next step is to add profile sections.

- Each profile section contains a range of settings for a specific security or management feature.
- For example, there are profile sections for 'Antivirus', 'External Device Control', 'Firewall', 'Procedures' and so on.
- You can add as many different sections as you want when building your profile.


To get started:

- · Click 'Add Profile Section'
- Select the component that you want to add to the profile:






 Some sections require that target endpoints are restarted. You will see the following message if this is the case:



• Click 'Confirm' to continue.

The new section will be available as a tab in the profile configuration page:





Use the following links to learn more about each profile section:

- Antivirus
- Update Settings
- File Rating
- Firewall
- HIPS
- Containment
- Maintenance Window
- VirusScope
- Valkyrie
- Global Proxy
- Clients Proxy
- Agent Discovery Settings
- UI Settings
- Logging Settings
- Client Access Control
- External Devices Control
- Monitors
- Procedures
- Remote Control
- Remote Tools
- Miscellaneous



- Script Analysis Settings
- Data Loss Prevention
- Patch Management

6.1.3.1.1. Antivirus Settings


The antivirus settings screen lets you configure real-time monitoring, custom scans and scan exclusions.

 Tip. Add a 'Miscellaneous' section to the profile if you want to setup registry monitoring. See Miscellaneous Settings for more details.

Configure Antivirus settings

- Click 'Configuration Templates' > 'Profiles'
- Open the profile you want to work on
- Click 'Add Profile Section' > 'Antivirus'

You can use the default AV settings or import them from a predefined profile:




- The default settings differ slightly from those in the various profiles. For example, 'Show antivirus alerts' is
 disabled in the security level 1 profile but is enabled in the default settings.
- In either case, you can always modify the AV settings later as required.
- Make your selection then click 'Ok'.

The AV settings screen opens:

- Real Time Scan Configure the 'always-on' virus monitor. This is the core antivirus scanner that continuously protects your endpoints against malware.
- Scans Create a custom scan profile. Custom scan profiles let you choose which areas you want to scan. You can also create a scan schedule. You can add multiple scan profiles to a device profile.
- **Exclusions** Files and folders that should be skipped on devices to which the profile is applied. Items you add here are excluded from real-time scans and any custom scans.



Realtime Scan settings





Realtime Scan Settings - Table of Parameters		
Form Element	Description	
Enable Realtime Scan	The realtime scanner ensures your devices are constantly protected from malware. The scanner inspects files whenever they are created, opened or copied.	
	Choose whether of not to enable real time scanning.	
	(Default = Enabled)	
Enable Scanning Optimizations	Various techniques to improve antivirus scan performance and reduce resource use.	
	Choose whether or not to enable scan optimization.	
	(Default = Enabled)	
Do not show auto-scan alerts	Choose whether or not to show a notification to end-users when an external device is connected to the endpoint.	
	CCS can automatically scan external devices whenever they are connected. Example devices include external HDD's, USB sticks etc.	
	Show alerts - End user can choose whether or not to scan the device from the alert	
	Don't show alerts - You have a choice of default responses that CCS should take:	
	Ignore - The device will not be scanned	
	Scan - The device will be scanned for viruses	
	(Default = Enabled with 'Ignore' option)	
Run cache builder when computer is idle	The antivirus cache builder runs whenever the computer is idle to boost the speed of real-time scans.	
	(Default = Disabled)	
	Applies only to CCS versions 8.3 or lower.	
Scan computer memory after the computer starts	If enabled, CCS will scan system memory for threats after a re-boot. (Default = Disabled)	
Show antivirus alerts	Configure whether or not to show alerts on the endpoints when malware is discovered.	
	Disabling will minimize disturbance to the end-user but at some loss of user awareness.	
	If you choose not to show alerts then you have a choice of default responses that CCS should automatically take:	
	Quarantine threats - Moves detected threat(s) to quarantine for assessment.	
	Block threats - Prevents the file from running	
	(Default = Enabled with 'Quarantine threats' option)	
Decompress and scan archive files of extensions	The antivirus will open and scan archive files such as .jar, RAR, ZIP, ARJ, WinARJ and CAB.	
	If enabled, you can choose which types of archive should be decompressed and scanned. Click the 'Extensions' link to view existing extensions and add new extensions.	
	(Default = Disabled)	
Set new on-screen alert timeout to (secs)	Specify how long an alert should stay on the screen at an endpoint. (Default = 120 seconds)	



Set new maximum file size to (MB)	Specify the maximum file size that the antivirus should attempt to scan. Files larger than the size specified here will not be not scanned. (<i>Default = 40 MB</i>)
Set new maximum script size limit to (MB)	Specify the maximum size of a script that the antivirus should attempt to scan. Files larger than the size specified here are not scanned. (<i>Default = 4 MB</i>)
Use heuristic scanning	Enable or disable heuristics scanning and define the scan level.
·	The scan level determines how likely the scanner is to classify an unknown file as a threat.
	 Low - Lowest sensitivity to detecting unknown threats / generates fewest false positives. The 'low' setting combines an extremely high level of security and protection with a low rate of false positives. Comodo recommends this setting for most users. (<i>Default</i>)
	 Medium - Detects unknown threats with greater sensitivity than the 'Low' setting but with a corresponding rise in the possibility of false positives.
	 High- Highest sensitivity to detecting unknown threats / increased possibility of false positives.
	(Default = Enabled with 'Low ' option)
	Background Note: Heuristic techniques identify previously unknown viruses and Trojans. 'Heuristics' describes the method of analyzing a file to ascertain whether it contains code typical of a virus. It is about detecting attributes which resemble a virus, rather than looking for a signature that matches a signature on the virus blacklist. This allows the engine to predict the existence of new viruses - even if they are not in the current virus database.

· Click the 'Save' button at the bottom.

Custom Scans

The 'Scans' pane allows you to view, edit, create and run custom scan profiles. Each scan profile is a collection of scanner settings that tell CCS:

- Where to scan (which files, folders or drives should be covered by the scan)
- When to scan (you have the option to specify a schedule)
- How to scan (options that let you specify the behavior of the scan engine when running this profile
- You can add multiple scan-profiles to a device profile.

Endpoint Manager ships with four scan profiles:

- **Full Scan** CCS scans every drive, folder and file on the target device. External devices like USB drives and digital camera will also be scanned.
- Quick Scan CCS scans important areas which are most prone to attack from malware. Scanned areas include system memory, auto-run entries, hidden services, boot sectors and other significant areas.
- **Unrecognized Files Scan** CCS only scans files which have an 'unknown' trust rating. CCS will obtain the file's latest trust rating from the our master online database.
- Quarantined Files Scan CCS only scans files which are currently quarantined. CCS will obtain the file's latest trust rating from the our master online database.


Click the 'Edit' icon beside a profile name to modify which items are scanned, and to set up a scan schedule. For details on the parameters, see the **explanation** below.

Create a custom scan profile

Open the 'Antivirus' section of your profile.




- 'Configuration Templates' > 'Profiles' > open the target profile
- Open the 'Antivirus' section, or click 'Add Profile Section' > 'Antivirus'
- Click the 'Scans' tab.
- · Click the 'Add' button:



- Enter the name of the custom scan in the 'Scan name' field
- Choose the files, folder or regions you want to scan

Target items are shown as follows:






Next, choose your scan options:

- Click the 'Options' bar
- See the table below the screenshot for a description of each option:







Scan Options - Table of Parameters	
Form Element	Description
Enable scanning optimizations	The antivirus will employ various optimization techniques like running the scan in the background in order to speed-up the scanning process (<i>Default</i> = <i>Enabled</i>).
	Applies only to CCS versions 8.3 or lower.
Decompress and scan compressed files	The antivirus will open and scan archive files. Supported formats include RAR, WinRAR, ZIP, WinZIP ARJ, WinARJ and CAB archives (<i>Default = Enabled</i>).
Use cloud while scanning	Augments the local scan with a real-time look-up of Comodo's online signature database. The cloud database is the most up-to-date version of our virus database, so antivirus scans are more accurate.
	With 'Cloud Scanning' enabled, CCS is capable of detecting zero-day malware even if the local database is out-dated. (<i>Default = Enabled</i>).
Automatically clean threats	CCS will automatically take action against detected threats instead of showing the results screen with a list of threats. You can choose the action to be taken from the drop-down. The available options are:
	Disinfect
	Quarantine
	(Default = Enabled with Disinfect option)
Show scan results window	Displays a results window at the end of a virus scan. The results windows shows all threats identified by the scan. (Default = Disabled)
Use heuristic scanning	Enable or disable heuristics scanning and define the scan level.
	The scan level determines how likely the scanner is to classify an unknown file as a threat.
	 Low - Lowest sensitivity to detecting unknown threats / generates fewest false positives. The 'low' setting combines an extremely high level of security and protection with a low rate of false positives. Comodo recommends this setting for most users. (Default)
	 Medium - Detects unknown threats with greater sensitivity than the 'Low' setting but with a corresponding rise in the possibility of false positives.
	 High- Highest sensitivity to detecting unknown threats / increased possibility of false positives.
	(Default = Enabled with 'Low ' option)
	Background Note: Heuristic techniques identify previously unknown viruses and Trojans. 'Heuristics' describes the method of analyzing a file to ascertain whether it contains code typical of a virus. It is about detecting attributes which resemble a virus, rather than looking for a signature that matches a signature on the virus blacklist. This allows the engine to predict the existence of new viruses - even if they are not in the current virus database
Apply this action to suspicious autorun entries	CCS will inspect auto-run entries, Windows services, startup items and scheduled tasks during each scan.
	 You can apply one of the following actions to services started by unrecognized or malicious processes:

ITarian Endpoint Manager - Administrator Guide



•	Quarantine and Disable: The service will be stopped and
	permanently disabled. The file that started the service will be
	quarantined on the device.

- Terminate and Disable The service will be stopped and permanently disabled. If required, the service can be enabled manually. (*Default*)
- Terminate The service will be stopped for the current session.
- **Ignore** -The detection will be logged but the service allowed to run normally.

Applies only to CCS versions 10.7 or higher.

ITarian Endpoint Manager - Administrator Guide




Limit maximum file size to	Specify the maximum file size that the antivirus should attempt to scan.(Default = 40 MB).
Run this scan with	Set the Windows priority for the scan. Choices are high, medium, low and run in the background. (<i>Default = Enabled with Background option</i>)
Update virus database before running	Makes CCS to check for virus database updates before a scan. Available updates will be downloaded prior to the scan. (Default = Enabled).
Detect potentially unwanted applications	CCS also scans for applications that (i) a user may or may not be aware is installed on their computer and (ii) may functionality and objectives that are not clear to the user. Example PUA's include adware and browser toolbars. PUA's are often installed as an additional extra when the user is installing an unrelated piece of software. Unlike malware, many PUA's are 'legitimate' pieces of software with their own EULA agreements. However, the 'true' functionality of the software might not have been made clear to the end-user at the time of installation. For example, a browser toolbar may also contain code that tracks a user's activity on the Internet (<i>Default = Enabled</i>).

The next step is to schedule when the custom scan should run:

· Click 'Schedule'






Schedule Settings - Table of Parameters	
Form Element	Description
Frequency	Do not schedule this task - The scan is not run automatically at a set time. The scan is saved after you click 'Ok' and is available for manual, on-demand scans.
	 Every hour(s) - Run the scan once every n hours. For example, once every 3 hours.
	Enter the number of hours between scans in the box provided.
	Every Day - Runs the scan every day at the time specified
	Every Week - Runs the scan weekly on the days and time you specify.
	Every Month - Runs the scan monthly on the days and time you specify.
	Selected days of month - Run the scan on specific days and weeks in a month. Select the weeks and days from the menus.
Run only when computer is not running on battery	Runs the scan only if the computer is connected to the mains supply. This is useful if you are using a laptop or any other battery driven portable computer.
Run only when computer is idle	Scans will run only if the computer is in idle state. Select this if you do not want to be disturbed, or if you are running resource intensive programs and do not want the



Schedule Settings - Table of Parameters		
	scan to take processing power.	
	Powers down your computer if no threats are found during the scan. For example, this is useful if you have scans which are scheduled to run at night.	

Click 'OK' to save the custom scan settings



The added scan profile will be listed in the screen.

- Use the switches to enable or disable a scan-profile.
- To change the settings for the custom scan, click the edit button , edit the parameters and click 'OK'
- To remove a custom scan from the list, select it and click 'Remove'

Exclusions


The 'Exclusions' screen under the Antivirus setting has three sub sections that allow you to add a list of paths, list of applications/files and 'File Groups' which should be excluded from the antivirus scan.

Click 'Exclusions'




Add excluded paths

By default the 'Excluded Paths' screen will be displayed:



· Click 'Add'


The 'Add Excluded Path' dialog will appear:



• Enter the full path that should be excluded from scanning and click 'OK'.

The added excluded path will be added to the list.






- Repeat the process to include more paths
- To change the path, click the edit button
 , edit the parameters and click 'OK'
- To remove a path from the list, select it and click 'Remove'


To add excluded applications

Click 'Excluded Applications'




Click 'Add'





- Enter the full path including the application that should be excluded from scanning and click 'OK'
- Repeat the process to include more applications




- To change the application path, click the edit button
 , edit the parameters and click 'OK'
- To remove an application from the list, select it and click 'Remove'

Add Excluded Groups

File groups make it easy to exclude an entire class of file types. Click 'Settings' > 'System Templates' > 'File Group Variables' to view/edit/create file groups. See **File Groups** if you need more help.

· Click 'Excluded Groups'






• Click 'Add'.

The 'Add Group' dialog opens:






• Choose the group from the 'Group' drop-down and click 'OK'.

The group will be added to the exclusions.

ITarian Endpoint Manager - Administrator Guide





- Repeat the process to add more file groups
- Click the 'Save' button at the bottom to save the antivirus settings.
- Click 'Delete' to remove the antivirus settings section. See **Edit Configuration Profiles** for more details about editing the parameters.



6.1.3.1.2. Communication Client and Comodo Client - Security Application Update Settings

- The updates section of a Windows profile lets you configure how and when managed devices should check for client updates.
- You can enable automatic updates, specify which version to install, choose update frequency, and enable local updates.

Tip: Alternatively, you can manually update clients as follows:


Click 'Devices' > 'Device List' > select target devices > Click 'Install or Manage Packages' > 'Update Additional Packages'

See Remotely Install and Manage Packages on Windows Devices if you want to know more about this method.

Configure update settings

- Open a device profile
- Click 'Add Profile Section' > 'Updates'

The section opens at the update configuration screen:




There are three tabs:

- Communication Client Enable automatic program updates for CC and configure proxy server settings.
- Comodo Client Security Enable automatic program updates for CCS and configure a schedule.
- **Download Servers** Specify the server from which managed endpoints should collect updates.

Communication Client




- Open the 'Updates' section of a profile
- Click the 'Communication Client' tab:



- Enable auto-updating Communication Client Forces the endpoint to check for and install CC program
 updates at the selected frequency. You can set the location of the download server in the 'Download
 Servers' tab. Deselect if you want to disable auto updates.
- Use default Communication Client version Choose whether or not to always update to the 'default' version.
 - Enabled = The client will always update to the default version (Default)
 - **Disabled** = You can choose the version to which the client updates. Make sure you choose a higher version than already installed.
 - Note 1. You can configure the default version in 'Settings' > 'Portal Set-up' > 'Client Settings' > 'Windows' > 'Communication Client'.
 - Note 2. You can only change the version if 'Change of version while updating' is enabled in 'Settings' > 'Portal Set-up' > 'Client Settings' > 'Windows' > 'Communication Client'. If it is not enabled then the default version is automatically deployed.
- Update Frequency Choose how often CC should check for updates. The available options are:
 - Daily (Default) The client checks for updates everyday at 6:00 am.
 - Daily (custom) The client checks for updates everyday at the time you specify
 - Weekly Select the days and times that you want the client to check for updates
 - On selected days Choose one or more days in a month to check for updates. For example, you might want to update on the first and third Wednesdays of every month.
 - Monthly Select the date and time in a month to check for updates





• Enable Communication Client to distribute updates to clients in the same network - Download updates to a managed endpoint, then use that endpoint as the source from which other endpoints collect their updates.

This saves internet bandwidth usage and accelerates updates in large networks.

If enabled, your endpoint clients will follow this process at update time:

- The endpoint first checks other endpoints to see if the update is installed on them
- If available, the client fetches the update from the local endpoint
- If not available, the client downloads the update from the server set in the 'Download Servers' tab
- This endpoint then becomes the source from which other endpoints collect their updates.


You can also choose the types of updates that use this mechanism:

- Communication Client updates (Version 6.29 or higher)
- Comodo Client Security updates (Version 11.4 or higher)
- Antivirus Database updates (Version 11.4 or higher)



Enable Communication Client to distribute update packages among the clients in the same network to reduce network inbound traffic
Communication Client packages
☐ Comodo Client - Security packages
☐ Comodo Client - Security Antivirus Database packages
Settings
Select specific devices to be proxy for distributing packages This will allow you to select specified devices that you want to use as a source to distribute packages
Enable Network traffic limitation This setting enables you to define maximum amount of network traffic to be used for distribution of packages
Less than or equal to, %
30
Enable device count limitation This setting enables you to define maximum number of devices to be used for distribution of packages Less than or equal to
10
Use download servers directly in case of any communication issue This option enables you to use download servers that is listed in Download Servers Tab in profiles under Updates section in case of any communication issue with ditribution mechanism. Please note that if this is not selected, in any communication issue, the clients will not update selected packages above until communication is restored

- Select specific devices to be proxy for distributing packages Choose specific devices from which endpoints should collect updates. If you do not enable this option then any device in the local network can act as the source.
 - Enter the names of the target devices in the field provided.
 - You can add multiple devices as sources. Endpoints will collect from the first source they find which has the update.



- Enable Network traffic limitation The maximum % of network bandwidth that can be used to share updates. (Default = 30%)
- Enable device count limitation The maximum number of devices with which the client is allowed to simultaneously share updates. (*Default* = 10, *Maximum* = 20).



- Use download servers directly in case of any communication issue If the endpoint cannot contact other endpoints it will instead collect the update from the server in the Download Servers tab.
- Click 'Save'.

The following table shows how clients will collect updates in different scenarios:

	Option			
	Enable Communication Client to distribute	Select specific devices to be proxy	Use download servers directly in case	Client fetches update from:
Scenario 1	✓	\$c	×	Any local device which already has the update
Scenario 2	✓	✓	×	Only from selected devices
Scenario 3	✓	*	✓	Any device in the local network Download servers
Scenario 4	✓	✓	✓	Selected devices Download servers


Additional Notes:

- You can also configure some 'global' settings for client updates at 'Settings' > 'Portal Set-up' > 'Client Settings' > 'Windows'.
- There is one overlapping item in global settings 'Enable the communication client to distribute packages to other clients in the network'
- Endpoint Manager prioritizes this setting as follows:
 - If you do not add an update section to the profile, then the global settings apply
 - If you do add an update section, then Endpoint Manager will ignore the '...distribute...' settings in global settings
- See Configure Communication Client Settings for more on global settings.

Comodo Client - Security

- · Open the 'Updates' section of a profile
- Click the 'Communication Client Security' tab:





- Enable auto-updating Comodo Client Security Forces the endpoint to check for and install CCS program updates at the selected frequency. You can set the location of the download server in the 'Download Servers' tab. Deselect if you want to disable auto updates.
- Use default Comodo Client Security version Choose whether or not to always update to the 'default' version.
 - Enabled = The client will always update to the default version (Default)
 - Disabled = You can choose the version to which the client updates. Make sure you choose a
 higher version than already installed. You cannot install a lower version than the current version.
 Note 1. You can configure the default version in 'Settings' > 'Portal Set-up' > 'Client Settings' >
 'Windows' > 'Comodo Client Security'.



Note 2. You can only change the version if 'Change of version while updating' is enabled in 'Settings' > 'Portal Set-up' > 'Client Settings' > 'Windows' > 'Comodo Client - Security'.

If it is not enabled then the default version is automatically deployed.

- **Update Frequency** Choose how often CCS should check for updates. The available options are:
 - Daily (Default) The client checks for updates everyday at 6:00 am.
 - Daily (custom) The client checks for updates everyday at the time you specify
 - Weekly Select the days and times that you want the client to check for updates
 - On selected days Choose one or more days in a month to check for updates. For example, you might want to update on the first and third Wednesdays of every month.
 - Monthly Select the date and time in a month to check for updates
- Skip updates if the device is offline Updates will not be installed if the endpoint is not connected to EM.
- Reboot Options Configure how the endpoint should restart after the update is installed:
 - Force the reboot in Restart the end-point a certain period of time after installation.
 - Choice of 5, 10, 15 or 30 minutes
 - Enter a message in the 'Reboot message' field to inform users about the reboot.
 - Suppress the reboot Do not restart the machine after the updates. CCS will only become fully functional after the device is restarted.
 - Warn about the reboot and let users postpone it Show an alert to the user which advises them that their computer needs to be restarted.
 - Enter a custom message which is shown to the user.
 - Users can restart the endpoint immediately by clicking 'Reboot now', or postpone it by picking a time in the 'Remind me in' drop-down.
- **Virus database Updates** Configure when the endpoint should automatically check for virus signature database updates and apply them
 - Check for database update every Specify how often CCS should check for, and automatically install, virus updates.
 - **Do not check for updates if running on battery** Only check for updates if the computer is connected to the mains supply. Useful for laptops or other battery driven devices.
 - Check for updates during Windows Automatic Maintenance CCS will check for virus updates
 when Windows enters maintenance mode. The update check will run at maintenance time in
 addition to the configured schedule. Only applies to Windows 8 and later.
- Click 'Save'.

Download Servers


- The 'Download Servers' tab lets you add and select the servers from which endpoints should collect updates.
- You may wish to first download updates to a proxy/staging server and have endpoints collect updates from there. This helps conserve overall bandwidth consumption and accelerates the update process when large number of endpoints are involved.
- You can configure different proxy servers for Comodo Client Security and the Communication Client.

Note: You need to install the 'ESM Update Mirror' utility on the proxy servers in order to get regular updates from Comodo.

- Download the setup file from https://drive.google.com/file/d/0B4qKr5xfENWBS0FOUHM2VDFQMnc/view.
- Run the setup file on a Windows server and follow the wizard to install the application.
- Ensure that the service has started:




- 'Run' > Enter 'services.msc' > locate 'Apache2.2'.
- Click the 'Start' link on the left if the service is not running.
- Click the 'Download Servers' tab



By default, EM is set to download updates from the Comodo servers. You can add your local servers here, edit, reorder the list of servers and remove servers if required.

Click 'Add' to add a server


The 'Add Server' dialog will be displayed.



- Transfer Protocol Select HTTP or HTTPS
- Host Enter the server details in the 'Host' field, either IP or the host name.
- Client Select the item for which the update proxy server should be configured:



- Communication Client Endpoints will collect communication client (CC) updates from the proxy server.
- **Client Security** Endpoints will collect security client (CCS) updates from the proxy server, including virus database updates.
- Communication Client + Client Security Endpoints will collect CC, CCS, and virus database updates from the proxy.
- Click 'Add'. Repeat the process to add more servers.



Use the 'on-off' switch to enable or disable a server. You need to enable the server in order for endpoints to
use it

You can edit, remove or reorder the list of servers.

- To edit a server details, select it and click the 'Edit' button at the top.
 - · Update the details as required and click the 'Set' button
- To remove a server, select it and click 'Remove' at the top

The updates are checked from the server at the top and moves down the list. You can reorder the list of servers.

- To reorder the server list, select the server(s) and click 'Move Up' or 'Move Down'
- Click 'Save' for the changes to updated in the profile.

6.1.3.1.3. File Rating Settings

- A file's trust rating determines how Comodo Client Security (CCS) handles the file on the endpoint.
- The ratings are obtained from Comodo's online file database, from the local CCS vendor list, and from the local CCS file list.
- Whenever a file is accessed, CCS does a lookup on the online database, and also consults the two local lists

The file is classed as trusted if:

- The app is from a vendor who has a 'Trusted' status in the local vendor list in CCS.
- The app is trusted in the online file database (aka, it is whitelisted).
- The application/file is trusted in the local CCS 'File List'



Note: CCS uses Ports 4446 and 4447 of the endpoint computers for TCP and UDP connections to the cloud. If this option is enabled, we advise you keep these ports free and do not assign them to other applications.


The interface lets you configure the overall behavior of the file rating system on Windows devices to which the profile is applied. You can also choose whether or not local file ratings should be consulted.

Configure File rating settings

- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Windows profile to open it's details page
 - Click the 'File Rating' tab, if it has already been added to the profile OR
 - Click 'Add Profile Section' > 'File Rating" if it hasn't yet been added

The file rating screen has two tabs:

- File Rating Enable file rating and configure overall behavior.
- Local Verdict Server Settings Choose whether CCS should obey or ignore admin trust ratings which
 have been assigned to a file. Admins can assign a trust rating to a file in Endpoint Manager at 'Security
 Sub-Systems' > 'Application Control'. If disabled, file rating scans will only consider the local and Comodo
 rating.






File Rating Configuration - Table of Parameters		
Form Element	Description	
Enable Cloud Lookup	CCS automatically checks the reputation of files on Comodo's file lookup service (FLS). • Disable this option if you do not want CCS to use the cloud rating. (Default = Enabled)	
Enable upload metadata of unknown files to the cloud	CCS uploads anonymized information about unknown files to Comodo servers. This allows us to analyze and whitelist/blacklist files more effectively. • Disable this option if you do not want CCS to send metadata to Comodo servers. (Default = Enabled)	
Show Cloud Alert	CCS can show an alert on the device when malware is found during a file rating scan. Users can block or allow the malware from the alert. • Disable this option if you don't want users to see an alert. If disabled, CCS will automatically block and delete any discovered malware. (Default = Disabled)	
Detect potentially unwanted applications Auto-Purge is enabled	A potentially unwanted application (PUA) is an app that: • A user may or may not be aware is installed on their computer. • May have functionality and objectives that are not clear to the user. PUAs include adware and browser toolbars. They are often installed as an extra when the user is installing an unrelated piece of software. Unlike malware, many PUA's are legitimate pieces of software with their own EULA agreements. However, the true functionality of the software may not have been made clear to the end-user at the time of installation. For example, a browser toolbar may also contain code that tracks a user's activity on the Internet. CCS will show an alert on the endpoint if it detects a PUA and a log entry is created. (Default = Disabled) CCS checks the file list and removes invalid and obsolete entries. You can specify the	
Auto-Purge is enabled	interval at which the check should take place. (Default = Enabled)	
Auto Purge Period	The time interval at which auto-purge operations are performed. • Enter the time interval in hours. (Default = Four hours)	
Custom FLS access ports	Define custom ports through which the file lookup service will connect. • Select the protocol(s) and enter the port details for UDP or TCP connections. (Default = Disabled)	
Enable report for non- executable files	If enabled, CCS sends a report on files identified as non-executable to EM on each file rating scan. (Default = Enabled)	
Show non-executable files	If enabled, non-executable files will also be added to the 'File List' interface of CCS on the endpoint. To access the file list in CCS, click 'Tasks' > 'Advanced Tasks' > 'Advanced settings' >	



File Rating Configuration - Table of Parameters	
	'Security settings' > 'File Rating' > 'File list'.
	(Default = Enabled)

• Click 'Save' to apply your file rating settings.

Local Verdict Server Settings



Local Verdict Server Settings - Table of Parameters		
Form Element	Description	
Enable Local Verdict Server	Choose whether CCS should consider the admin trust rating assigned to a file. (Default = Enabled)	
	Admins can change the trust rating of a file in Endpoint Manager at 'Security Sub-Systems' > 'Application Control'.	
Timeout for Unknown Files	How often CCS should check Endpoint Manager for new ratings on files that are currently have no rating at all.	
	(Default = 2 Minutes)	
Timeout for known files (Trusted, malware and Unrecognized)	How often CCS should check Endpoint Manager for new ratings on files that are currently rated as 'Trusted', 'Malware' or 'Unrecognized'.	
	(Default = 1 Hour)	

• Click 'Save' to apply your changes.



6.1.3.1.4. Firewall Settings

The Firewall Settings area lets you configure the behavior of the CCS firewall on endpoints to which the profile is applied. You can also configure network zones, portsets and traffic filtering rules.


Configure Firewall Settings and Traffic Filtering Rules

· Click 'Firewall' from the 'Add Profile Section' drop-down

The Firewall settings screen is displayed. It has six tabs:

- Firewall Settings Configure the general firewall behavior
- Application Rules Define rules that determine the network access privileges of individual applications or specific types of applications at the endpoint
- Global Rules Define rules that apply to all traffic flowing in and out of the endpoint
- Rulesets Create and manage predefined collections of firewall rules that can be applied, out-of-the-box, to Internet capable applications such as browsers, email clients and FTP clients.
- Network Zones Create named grouping of one or more IP addresses. Once created, you can specify a
 zone as the target of firewall rule.
- Portsets Define groups of regularly used ports that can used and reused when creating traffic filtering rules.

Firewall Settings





Firewall Configuration - Table of Parameters		
Form Element	Description	
Enable Firewall	Enable or disable Firewall protection at the endpoint. If enabled the following options are available:	
	 Custom Ruleset - The firewall applies ONLY the custom security configurations and network traffic policies specified by the administrator. New users may want to think of this as the 'Do Not Learn' setting because the firewall does not attempt to learn the behavior of any applications. Nor does it automatically create network traffic rules for those applications. The user will receive alerts every time there is a connection attempt by an application - even for applications on the Comodo Safe list (unless, of course, the administrator has specified rules and policies that instruct the firewall to trust the application's connection attempt). 	
	If any application tries to make a connection to the outside, the firewall audits all the loaded components and checks each against the list of components already allowed or blocked. If a component is found to be blocked, the entire application is denied Internet access and an alert is generated. This setting is advised for experienced firewall users that wish to maximize the visibility and control over traffic in and out of their computer.	
	 Safe Mode - While filtering network traffic, the firewall automatically creates rules that allow all traffic for the components of applications certified as 'Safe' by Comodo, if the checkbox Create rules for safe applications is selected. For non-certified new applications, the user will receive an alert whenever that application attempts to access the network. The administrator can choose to grant that application Internet access by selecting 'Treat this application as a Trusted Application' at the alert. This deploys the predefined firewall policy 'Trusted Application' onto the application. 	
	'Safe Mode' is the recommended setting for most users - combining the highest levels of security with an easy-to-manage number of connection alerts.	
	 Training Mode - The firewall monitors network traffic and create automatic allow rules for all new applications until the security level is adjusted. The user will not receive any alerts in 'Training Mode' mode. If you choose the 'Training Mode' setting, we advise that you are 100% sure that all applications installed on endpoints are assigned the correct network access rights. 	
	 Note - If required you can enable training mode to work temporarily. To do that, select 'Temporarily switch Firewall to training mode' option and set the days / hours. 	
	Safe mode ~	
	Temporarily switch Firewall to training mode CC v 6.27 and higher This option switches Firewall to training mode for the selected time period and starts the timer. When the time elapses, Firewall will be automatically switched to the mode set above. Period Days Hours 1	
	☐ Show popup alerts	



	Firewall Configuration - Table of Parameters
	After the countdown is over, CCS will switch back to previous mode. For more details on the Firewall Settings, see the of CCS - Firewall Settings online help page at https://community.itarian.com/help/topic-459-1-1002-15148-Firewall-Configuration.html.
Show popup alerts	Whether or not firewall alerts are to be displayed at the endpoint whenever the firewall encounters a request for network access, for the user to respond. If you choose not to show the alerts, you can select the default responses from the 'Auto Action' drop-down. The available options are: Block Requests Allow Requests
Turn traffic animation effects on	The CCS tray icon can display a small animation whenever traffic moves to or from your computer. You can enable or disable the animation to be displayed at the endpoint.
Create rules for safe applications	Comodo Firewall trusts the application if: • The app is from a vendor who has a 'Trusted' status in the local vendor list in CCS • The app is trusted in the online file database (aka, it is whitelisted) • The app is trusted in the local CCS 'File List' See File Rating Settings for more details. By default, CCS does not automatically create 'allow' rules for safe applications. This saves resource usage and simplifies the rules interface by reducing the number of rules created. Enabling this option instructs CCS to learn the behavior of safe applications so it can auto-create 'Allow' rules for them. These rules are listed in 'Settings' > 'Firewall Settings' > 'Application Rules'. Advanced users can edit/modify the rules as they wish. (Default = Disabled).
Set alert frequency level	Enabling this option allows you to configure the amount of alerts that Comodo Firewall generates, from the drop-down at the endpoint. It should be noted that this does not affect your security, which is determined by the rules you have configured (for example, in 'Application Rules' and 'Global Rules'). For the majority of users, the default setting of 'Low' is the perfect level - ensuring you are kept informed of connection attempts and suspicious behaviors whilst not overwhelming you with alert messages. (<i>Default=Disabled</i>) The options available are: • Very High: The firewall shows separate alerts for outgoing and incoming connection requests for both TCP and UDP protocols on specific ports and for specific IP addresses, for an application. This setting provides the highest degree of visibility to inbound and outbound connection attempts but leads to a proliferation of firewall alerts. For example, using a browser to connect to your Internet home-page may generate as many as 5 separate alerts for an outgoing TCP connection alone. • High: The firewall shows separate alerts for outgoing and incoming connection requests for both TCP and UDP protocols on specific ports for an application.




Firewall Configuration - Table of Parameters		
	Medium: The firewall shows alerts for outgoing and incoming connection requests for both TCP and UDP protocols for an application.	
	 Low: The firewall shows alerts for outgoing and incoming connection requests for an application. This is the setting recommended by Comodo and is suitable for the majority of users. 	
	 Very Low: The firewall shows only one alert for an application. 	
	The Alert Frequency settings refer only to connection attempts by applications or from IP addresses that you have not (yet) decided to trust.	
Set new on-screen alert timeout to:	How long the Firewall shows an alert for, without any user intervention at the endpoint. By default, the timeout is set at 120 seconds. You may adjust this setting to your own preference by selecting this option and choosing the period from the drop-down combo-box.	
Filter IPv6 traffic	If enabled, the firewall component of CCS at the endpoint will filter IPv6 network traffic in addition to IPv4 traffic.	
	Background Note: IPv6 stands for Internet Protocol Version 6 and is intended to replace Internet Protocol Version 4 (IPv4). The move is primarily driven by the anticipated exhaustion of available IP addresses. IPv4 was developed in 1981 and is still the most widely deployed version - accounting for almost all of today's Internet traffic. However, because IPv4 uses 32 bits for IP addresses, there is a physical upper limit of around 4.3 billion possible IP addresses - a figure widely viewed as inadequate to cope with the further expansion of the Internet. In simple terms, the number of devices requiring IP addresses is in danger of exceeding the number of IP addresses that are available. This hard limit has already led to the development of 'work-around' solutions such as Network Address Translation (NAT), which enable multiple hosts on private networks to access the Internet using a single IP address.	
	IPv6 on the other hand, uses 128 bits per address (delivering 3.4×1038 unique addresses) and is viewed as the only realistic, long term solution to IP address exhaustion. IPv6 also implements numerous enhancements that are not present in IPv4 - including greater security, improved support for mobile devices and more efficient routing of data packets.	
Filter loopback traffic	Loopback connections refer to the internal communications within your PC. Any data transmitted by your computer through a loopback connection is immediately received by it. This involves no connection outside your computer to the Internet or a local network. The IP address of the loopback network is 127.0.0.1, which you might have heard referred to, under its domain name of 'http://localhost', i.e. the address of your computer.	
	Loopback channel attacks can be used to flood your computer with TCP and/or UDP requests which can smash your IP stack or crash your computer. Leaving this option enabled means the firewall will filter traffic sent through this channel at the endpoints. (<i>Default = Enabled</i>).	
Block fragmented IP traffic	When a connection is opened between two computers, they must agree on a Maximum Transmission Unit (MTU). IP Datagram fragmentation occurs when data passes through a router with an MTU less than the MTU you are using i.e when a datagram is larger than the MTU of the network over which it must be sent, it is divided into smaller 'fragments' which are each sent separately.	
	Fragmented IP packets can create threats similar to a DOS attack. Moreover, these fragmentations can double the amount of time it takes to send a single packet and slow down your download time.	



Firewall Configuration - Table of Parameters		
	If you want the firewall component of CCS at the endpoint to block the fragmented datagrams, enable this option. (Default = Enabled 0.	
Do Protocol Analysis	Protocol Analysis is key to the detection of fake packets used in denial of service (DOS) attacks.	
	If you want firewall at the endpoint to check whether every packet conforms to that protocols standards, select this option. If not, then the packets are blocked (<i>Default = Enabled</i>).	
Enable anti-ARP spoofing	A gratuitous Address Resolution Protocol (ARP) frame is an ARP Reply that is broadcast to all machines in a network and is not in response to any ARP Request. When an ARP Reply is broadcast, all hosts are required to update their local ARP caches, whether or not the ARP Reply was in response to an ARP Request they had issued. Gratuitous ARP frames are important as they update the machine's ARP cache whenever there is a change to another machine on the network (for example, if a network card is replaced in another machine on the network, then a gratuitous ARP frame informs your machine of this change and requests to update its ARP cache so that data can be correctly routed). However, while ARP calls might be relevant to an ever shifting office network comprising many machines that need to keep each other updated, it is of far less relevance to, say, a single computer in a small network. Enabling this setting helps to block such requests at the endpoints to which the profile is applied - protecting the ARP cache from potentially malicious updates (<i>Default = Enabled</i>).	


Application Rules

Whenever an application makes a request for Internet or network access, Comodo Firewall allows or denies this request based upon the Firewall Ruleset that has been specified for that application. Firewall Rulesets are, in turn, made up from one or more individual network access rules. Each individual network access rule contains instructions that determine whether the application should be allowed or blocked; which protocols it is allowed to use; which ports it is allowed to use and so forth.



The 'Application Rules' interface allows you to create and manage application rules for regulating network access to individual applications at the endpoints to which the profile is applied.





Although each ruleset can be defined from the ground up by individually configuring its constituent rules, this practice would be time consuming if it had to be performed for every single program on your system. For this reason, Comodo Firewall contains a selection of predefined rulesets according to broad application category. For example, you may choose to apply the ruleset 'Web Browser' to the applications like 'Internet Explorer', 'Firefox' and 'Opera'. Each predefined ruleset has been specifically designed by Comodo Firewall to optimize the security level of a certain type of application. Administrators can, of course, modify these predefined rulesets to suit their environment and requirements. For more details, see **Predefined Rule Sets**.


- See Application Rule interface for an introduction to the rule setting interface
- See Create and Modify Firewall Rulesets to learn how to create and edit Firewall rulesets
- See Understanding Firewall Rules for an overview of the meaning, construction and importance of individual rules



See Add and Edit a Firewall Rule for an explanation of individual rule configuration.

Application Rule interface

- Click the 'Add' button or 'Edit' icon beside a ruleset in 'Application Rules' interface to open the 'Application Rule' interface.
- The rules in a Firewall ruleset can be added/modified/removed and re-ordered through the 'Application Rule' interface.
- You can also create new rules or edit existing rules in the ruleset in the 'Firewall Rule' interface (Click the 'Add' button or 'Edit' icon beside a rule in 'Application Rules' interface). See Add and Edit a Firewall Rule for guidance on this.



Comodo Firewall applies rules on a per packet basis and applies the first rule that matches that packet type to be filtered (see **Understanding Firewall Rules** for more information). If there are a number of rules in the list relating to a packet type then one nearer the top of the list is applied. Administrators can re-prioritize rules by uisng the 'Move Up' or 'Move Down' buttons.

Create and Modify Firewall Rulesets

To begin defining an application's Firewall ruleset, you need take two basic steps.

- Step 1 Select the application that you wish the ruleset is to be applied.
- Step 2 Configure the rules for this application's ruleset.

Step 1 - Select the application that you wish the ruleset is to be applied


• To define a ruleset for a new application (i.e. one that is not already listed), click the 'Add' button

+ Add

at the top of the list in the 'Application Rules' interface.

The 'Application Rule' interface will open as shown below:





Because this is a new application, the 'Name' field is blank. (If you are modifying an existing ruleset, then this interface shows the individual rules for that application's ruleset).


You can enter the application(s) to which the rule set is to be applied in two ways:

• Enter the installation path of the application with the application file name in the Name field (For example, 'C:\Program Files\Mozilla Firefox\firefox\exec').

Or

• Open the drop-down beside the 'Name' field and choose the application group to which the ruleset is to be applied. Choosing a 'File Group' allows you to create firewall ruleset for a category of pre-set files or folders. For example, selecting 'Executables' would enable you to create a Firewall Ruleset for any file that attempts to connect to the Internet with the extensions .exe .dll .sys .ocx .bat .pif .scr .cpl . Other such categories available include 'Windows System Applications' , 'Windows Updater Applications' , 'Start Up Folders' etc -each of which provide a fast and convenient way to apply a generic ruleset to important files and folders. Endpoint Manager ships with a set of predefined 'File Groups'. If required you can add new file groups and edit existing groups ('Settings' > 'System Templates' > 'File Groups Variables'). See Create and Manage File Groups for guidance on this.






Step 2 - Configure the rules for this application's ruleset

There are two broad options available for creating a ruleset that applies to an application - **Use a Predefined Ruleset** or **Use a Custom Ruleset**.


• Use a Predefined Ruleset - Allows you to quickly deploy an existing ruleset on to the target application. Choose the ruleset you wish to use from the drop-down menu. In the example below, we have chosen 'Web Browser' because we are creating a ruleset for the 'Firefox' browser. The name of the predefined ruleset you choose is displayed in the 'Treat As' column for that application in the 'Application Rules' interface (Default = Disabled).





Note: Predefined Rulesets, once chosen, cannot be modified *directly* from this interface - they can only be modified and defined using the **Application Rule** interface. If you require the ability to add or modify rules for an application then you are effectively creating a new, custom ruleset and should choose the more flexible **Use Custom Ruleset** option instead.

Use a Custom Ruleset - Designed for more experienced administrators, the Custom Ruleset option
enables full control over the configuration of Firewall Ruleset and the parameters of each rule within that
ruleset (*Default = Enabled*).



You can create an entirely new ruleset or use a predefined ruleset as a starting point by:

Clicking 'Add' from the top to add individual Firewall rules. See 'Add and Edit a Firewall Rule' for an
overview of the process.



- Use the 'Copy From' button to populate the list with the Firewall rules of a Predefined Firewall Rule.
- Use the 'Copy From' button to populate the list with the Firewall rules of another application's ruleset.

General Tips:

- If you wish to create a reusable ruleset for deployment on multiple applications, we advise you add a
 new Predefined Firewall Rules (or modify one of the existing ones to suit your needs) then come
 back to this section and use the 'Ruleset' option to roll it out.
- If you want to build a bespoke ruleset for maybe one or two specific applications, then we advise you choose the 'Use a Custom Ruleset' option and create your ruleset either from scratch by adding individual rules or by using one of the built-in rulesets as a starting point.

Understanding Firewall Rules

At their core, each Firewall rule can be thought of as a simple **IF THEN** trigger - a set of **conditions** (or attributes) pertaining to a packet of data from a particular application and an **action** it that is enforced if those conditions are met.

As a packet filtering firewall, Comodo Firewall analyzes the attributes of every single packet of data that attempts to enter or leave the computer. Attributes of a packet include the application that is sending or receiving the packet, the protocol it is using, the direction in which it is traveling, the source and destination IP addresses and the ports it is attempting to traverse. The firewall then tries to find a Firewall rule that matches all the conditional attributes of this packet in order to determine whether or not it should be allowed to proceed. If there is no corresponding Firewall rule, then the connection is automatically blocked until a rule is created.

The actual **conditions** (attributes) you see * on a particular Firewall Rule are determined by the protocol chosen in the 'Firewall Rule' interface. See **Add and Edit a Firewall Rule** for more details.

If you chose 'TCP', 'UDP' or 'TCP and 'UDP', then the rule has the form: Action | Protocol | Direction | Source Address | Destination Address | Source Port | Destination Port

If you chose 'ICMP', then the rule has the form: Action | Protocol | Direction | Source Address | Destination Address | ICMP Details

If you chose 'IP', then the rule has the form: Action | Protocol | Direction | Source Address | Destination Address | IP Details

- Action: The action the firewall takes when the conditions of the rule are met. The rule shows 'Allow',
 'Block' or 'Ask'.**
- Protocol: States the protocol that the target application must be attempting to use when sending or receiving packets of data. The rule shows 'TCP', 'UDP', 'TCP or UDP', 'ICMP' or 'IP'
- **Direction**: States the direction of traffic that the data packet must be attempting to negotiate. The rule shows 'In'. 'Out' or 'In/Out'
- Source Address: States the source address of the connection attempt. The rule shows 'From' followed by one of the following: IP , IP range, IP Mask , Network Zone, Host Name or Mac Address
- Destination Address: States the address of the connection attempt. The rule shows 'To' followed by one of the following: IP, IP range, IP Mask, Network Zone, Host Name or Mac Address
- Source Port: States the port(s) that the application must be attempting to send packets of data through.
 Shows 'Where Source Port Is' followed by one of the following: 'Any', 'Port #', 'Port Range' or 'Port Set'
- **Destination Port**: States the port(s) on the remote entity that the application must be attempting to send to. Shows 'Where Source Port Is' followed by one of the following: 'Any', 'Port #', 'Port Range' or 'Port Set'
- ICMP Details: States the ICMP message that must be detected to trigger the action. See Add and Edit a Firewall Rule for details of available messages that can be displayed.
- IP Details: States the type of IP protocol that must be detected to trigger the action: See Add and Edit a Firewall Rule to see the list of available IP protocols that can be displayed here.




Once a rule is applied, Comodo Firewall monitors all network traffic relating to the chosen application and take the specified action if the conditions are met. Users should also see the section 'Global Rules' to understand the interaction between Application Rules and Global Rules.

- * If you chose to add a descriptive name when creating the rule then this name is displayed here rather than it's full parameters. See the next section, 'Add and Edit a Firewall Rule', for more details.
- ** If you selected 'Log as a firewall event if this rule is fired' then the action is postfixed with 'Log'. (e.g. Block & Log)

Add and Edit a Firewall Rule

The Firewall Rule Interface is used to configure the actions and conditions of an individual Firewall rule. If you are not an experienced firewall user or are unsure about the settings in this area, we advise you first gain some background knowledge by reading the sections 'Understanding Firewall Rules', 'Overview of Rules and Policies' and 'Create and Modify Firewall Rulesets'.



General Settings

- Action: Define the action the firewall takes when the conditions of the rule are met. Options available via the drop down menu are 'Allow' (*Default*), 'Block' or 'Ask'.
- Protocol: Allows the user to specify which protocol the data packet should be using. Options available via
 the drop down menu are 'TCP', 'UDP', 'TCP or UDP' (Default), 'ICMP' or 'IP'.

Note: Your choice here alters the choices available to you in the tab structure on the lower half of the interface.

- **Direction:** Allows the user to define which direction the packets should be traveling. Options available via the drop down menu are 'In', 'Out' or 'In/Out' (*Default*).
- Log as a firewall event if this rule is fired: Checking this option creates an entry in the firewall event log viewer whenever this rule is called into operation. (i.e. when ALL conditions have been met) (Default = Disabled).
- **Description**: Allows you to type a friendly name for the rule. Some users find it more intuitive to name a rule by it's intended purpose. ('Allow Outgoing HTTP requests'). If you create a friendly name, then this is




displayed to represent instead of the full actions/conditions in the main **Application Rules interface** and the **Application Rule interface**.

Protocol

i. 'TCP,' 'UDP' or 'TCP or UDP'

If you select 'TCP', 'UDP' or 'TCP or UDP' as the Protocol for your network, then you have to define the source and destination IP addresses and ports receiving and sending the information



Source Address and Destination Address:


- 1. You can choose any IP Address by selecting Any Address in the Type drop-down box. This menu defaults to an IP range of 0.0.0.0- 255.255.255.255 to allow connection from all IP addresses.
- 2. You can choose a named host by selecting a Host Name which denotes your IP address.
- 3. You can choose an IPv4 Range by selecting IPv4 Address Range for example the range in your private network and entering the IP addresses in the Start Range and End Range text boxes.
- 4. You can choose a Single IPv4 address by selecting IPv4 Single Address and entering the IP address in the IP address text box, e.g., 192.168.200.113.
- You can choose IPv4 Mask by selecting IPv4 Subnet Mask. IP networks can be divided into smaller networks called sub-networks (or subnets). An IP address/ Mask is a subnet defined by IP address and mask of the network. Enter the IP address and Mask of the network.
- 6. You can choose a Single IPv6 address by selecting IPv6 Single Address and entering the IP address in the IP address text box, e.g., 3ffe:1900:4545:3:200:f8ff:fe21:67cf.
- 7. You can choose IPv6 Mask by selecting IPv6 Subnet Mask. IP networks can be divided into smaller networks called sub-networks (or subnets). An IP address/ Mask is a subnet defined by IP address and mask of the network. Enter the IP address and Mask of the network.
- You can choose a MAC Address by selecting MAC Address and entering the address in the address text box.



- 9. You can choose an entire network zone by selecting Zone .This menu defaults to Local Area Network. But you can also define your own zone by first creating a Zone through the 'Network Zones' area.
- Exclude (i.e. NOT the choice below): The opposite of what you specify is applicable. For example,
 if you are creating an Allow rule and you check the Exclude box in the Source IP tab and enter
 values for the IP range, then that IP range is excluded. You have to create a separate Allow rule for
 the range of IP addresses that you DO want to use.

Source Port and Destination Port:

Enter the source and destination Port in the text box.



- 1. You can choose any port number by selecting Any set by default, 0-65535.
- 2. You can choose a Single Port number by selecting Single Port and selecting the single port numbers from the list.
- 3. You can choose a Port Range by selecting Port Range and selecting the port numbers from the From and To list.
- 4. You can choose a predefined **Port Set** by choosing A Set of Ports. If you wish to create a custom port set then please see the section '**Port Sets**'.

ii. ICMP


When you select ICMP as the protocol in **General Settings**, you are shown a list of ICMP message types in the 'ICMP Details' tab alongside the **Destination Address** tabs. The last two tabs are configured identically to the **explanation above**. You cannot see the source and destination port tabs.

iii. ICMP Details


ICMP (Internet Control Message Protocol) packets contain error and control information which is used to announce network errors, network congestion, timeouts, and to assist in troubleshooting. It is used mainly for performing traces and pings. Pinging is frequently used to perform a quick test before attempting to initiate communications. If you are using or have used a peer-to-peer file-sharing program, you might find yourself being pinged a lot. So you can create rules to allow / block specific types of ping requests. With Comodo Firewall you can create rules to allow/ deny inbound ICMP packets that provide you with information and minimize security risk.

 Type in the source/ destination IP address. Source IP is the IP address from which the traffic originated and destination IP is the IP address of the computer that is receiving packets of information.





- 2. Under the 'ICMP Details' tab, choose the ICMP version from the 'Type' drop-down.
- 3. Specify ICMP Message, Types and Codes. An ICMP message includes a Message that specifies the type, that is, the format of the ICMP message.




When you select a particular ICMP message, the menu defaults to set its code and type as well. If you select the ICMP message type 'Custom' then you are asked to specify the code and type.

iv. IP


When you select IP as the protocol in **General Settings**, you are shown a list of IP message type in the 'IP Details' tab alongside the **Source Address** and **Destination Address** tabs. The last two tabs are configured identically to the **explanation above**. You cannot see the source and destination port tabs.





v. IP Details

Select the types of IP protocol that you wish to allow, from the ones that are listed.



· Click 'OK' to save the firewall rule.




Global Rules

Unlike Application rules, which are applied to and triggered by traffic relating to a specific application, Global Rules are applied to all traffic traveling in and out of the computers applied with this profile.

Comodo Firewall analyzes every packet of data in and out of the computer using combination of Application and Global Rules.

- For Outgoing connection attempts, the application rules are consulted first and then the global rules second.
- For Incoming connection attempts, the global rules are consulted first and then the application rules second.




Therefore, outgoing traffic has to 'pass' both the application rule then any global rules before it is allowed out of your system. Similarly, incoming traffic has to 'pass' any global rules first then application specific rules that may apply to the packet.

Global Rules are mainly, but not exclusively, used to filter incoming traffic for protocols other than TCP or UDP.

The 'Global Rules' panel in the under 'Firewall' tab allows you to view create and manage the global firewall rules.





The configuration of Global Rules is identical to that for application rules. To add a global rule, click the 'Add' button on the top. To edit an existing global rule, click the edit icon beside it.

- See Application Rules for an introduction to the rule setting interface.
- See Understanding Firewall Rules for an overview of the meaning, construction and importance of individual rules.
- See Add and Edit a Firewall Rule for an explanation of individual rule configuration.


Rulesets

As the name suggests, a firewall Ruleset is a set of one or more individual Firewall rules that have been saved and which can be re-deployed on multiple applications. Endpoint Manager ships with six predefined rulesets and allows you to create and manage custom rulesets as required. This section contains advice on the following:

- Predefined Rulesets
- Creating a new ruleset

The 'Rulesets' panel under the 'Firewall' tab allows you to view, create and manage the firewall rulesets.





The Rulesets panel displays a list of pre-defined and custom Firewall Rulesets.

Although each application's firewall ruleset *could* be defined from the ground up by individually configuring its constituent rules, this practice may prove time consuming if it had to be performed for every single program on your system. For this reason, Comodo Firewall contains a selection of predefined rulesets according to broad application category. For example, you may choose to apply the ruleset 'Web Browser' to the applications 'Internet Explorer', 'Firefox' and 'Opera'. Each predefined ruleset has been specifically designed by Comodo to optimize the security level of a certain type of application. Users can, of course, modify these predefined policies to suit their environment and requirements. (for example, you may wish to keep the 'Web Browsers' name but wish to redefine the parameters of it rules).

Endpoint Manager ships with six predefined firewall rulesets for different categories of applications:

- Web Browser
- Email Client
- FTP Client
- Allowed Application
- Blocked Application
- Outgoing Only

These rulesets can be edited by adding new rules or reconfiguring the existing rules. For more details see the explanation of **adding and editing firewall rules** in the section 'Application Rules'.

Create a new ruleset

You can create new rulesets with network access control rules customized as per your requirements and can roll out them to required applications while **creating firewall ruleset** for the applications individually.


To add a new Ruleset

Click the 'Add Ruleset' button panel

Add Ruleset from the top of the list of rulesets in the 'Rulesets'



The 'Firewall Ruleset' interface will open.



As this is a new ruleset, you need to name it in the 'Name' field at the top. It is advised that you choose
a name that accurately describes the category/type of application you wish to define the ruleset for.
Next you should add and configure the individual rules for this ruleset. See 'Add and Edit a Firewall
Rule' for more advice on this.

Once created, this ruleset can be quickly called from 'Use Ruleset' when **creating or modifying a Firewall ruleset**.

To view or edit an existing predefined Ruleset

- Click on the 'Edit' icon beside Ruleset Name in the list.
- Details of the process from this point on can be found under 'Use Custom Rule Set.'.


Network Zones

The 'Network Zones' panel under the 'Firewall' tab allows you to:

ITarian Endpoint Manager - Administrator Guide



- Configure to detect any new network (wired or wireless) that the computer applied with this profile is trying to connect and provide alerts for the same
- Define network zones that are trusted, and to specify access privileges to them
- · Define network zones that are untrusted, and to block access to them




The 'Network Zones' panel contains options for configuring the general network monitoring settings and lists of 'Allowed Network Zones' and 'Blocked Network Zones' under respective tabs. You can add and manage network zones to be allowed and blocked from this interface.

Network Monitoring Settings:

- Enable automatic detection of private networks Instructs Comodo Firewall to keep monitoring whether the computer applied with this security profile is connected to any new wired or wireless network (*Default* = *Enabled*). Deselect this option if you do not want the new connection attempts is to be detected and/or wish to manually set-up their own trusted networks (this can be done in 'Network Zones'.
- **Do Not show popup alerts** By default, an alert will be displayed at the computer, if the computer attempts to connect to a new network, for the end-user to select the type of network. CCS will optimize its firewall settings for the new network, based on the selection. An example is shown below.





If you do not want the alert to be displayed to the end-user and wish the CCS at the computer to decide on the type of network by default, deselect this option and choose the network type from the drop-down under Location Treatment. The available options are:

- Home
- Work
- Public



The panel has two tabs:

- Network Zones Allows you to define network zones and to allow access to them for applications, with the
 access privileges specified through Application Rule interface. Refer to 'Creating or Modifying Firewall
 Rules' for more details.
- Blocked Zones Allows you to define trusted networks that are not trustworthy and to block access to them.



Network Zones


A 'Network Zone' can consist of an individual machine (including a single home computer connected to Internet) or a network of thousands of machines to which access can be granted or denied.

The 'Network Zones' tab in the 'Network Zones' panel displays a list of defined network zones and allows you to define network zones, to which the computer applied with this profile can connect, with access rights as defined by the firewall rules or blocked access to.


To define a new Network Zone

Click the 'Add'
 button at the top of the list.

The 'Network Zone' dialog will open.



- Enter a name for the new network zone in the 'Name' field.
- Select the checkbox 'Public Network' if you are defining a network zone for a network in a public place, for
 example, when you are connecting to a Wi-Fi network at an airport, restaurant etc., so that Comodo Firewall
 will optimize the configuration accordingly.
- Click 'Add' to add the computers in the new network zone



The 'Address' dialog allows you to select an address from the 'Type' drop-down box shown below (*Default = Any Address*). The 'Exclude' check box will be enabled only if any other choice is selected from the drop-down box.

ITarian Endpoint Manager - Administrator Guide




Address Types:

- i. Any Address Adds all the IP addresses (0.0.0.0- 255.255.255.255) to the zone.
- ii. Host Name- Enter a named host which denotes an address on your network.
- iii. IPv4 Range Will include all the IPv4 addresses between the values you specify in the 'Start Range' and 'End Range' text boxes.
- iv. IPv4 Single Address Enter a single IP address to be added to the zone e.g. 192.168.200.113.
- v. IPv4 Subnet Mask A subnet mask allows administrators to divide a network into two or more networks by splitting the host part of an IP address into subnet and host numbers. Enter the IP address and Mask of the network you wish to add to the defined zone.
- vi. IPv6 Single Address -Enter a single address to be added to the zone e.g. 3ffe:1900:4545:3:200:f8ff:fe21:67cf.
- vii. IPv6 Subnet Mask. Ipv6 networks can be divided into smaller networks called sub-networks (or subnets). An IP address/ Mask is a subnet defined by IP address and mask of the network. Enter the IP address and Mask of the network.
- viii. MAC Address Enter a specific MAC address to be added to the zone.
- Select/enter the Addresses to be included in the new network zone
- If you want to select all the other addresses to be included in the network zone, excluding those selected under the Type drop-down, select the 'Exclude' option.
- Click 'OK' in the 'Address' dialog.
- Click 'OK' in the 'Network Zone' dialog

The network zone will be added under Network Zones list and will be available to be quickly called as 'Zone' when creating or modifying a Firewall Ruleset. Or when defining a Blocked Zone.





To edit a network zone, click the 'Edit' icon beside the network zone name. The 'Network Zone' dialog will appear populated with the name and the addresses of the network zone. Edit the details as required. The process is similar to **defining a new network zone** as explained above.


Blocked Zones

A computer network enables users to share information and devices between computers and other users within the network. There are certain networks that you'll want to 'trust' and grant access to - for example your work network. Conversely, there may be other networks that you do not trust and want to restrict communication with - or even block entirely.

The 'Blocked Zones' section allows you to configure restrictions on network zones that you do not wish to trust and the computers applied with this profile will be blocked access to them.

The 'Blocked Zones' tab allows you to view the list of blocked network zones and add new blocked zones.





The 'Blocked Zones' tab displays a list of zones that are currently blocked and allows you to:

- Deny access to an existing network zone
- Deny access to a network by manually defining a new blocked zone

Note 1: You must create a zone before you can block it. There are two ways to do this;


- 1. Using 'Network Zones' to name and specify the network you want to block.
- 2. Directly from this interface using 'New blocked address...'

Note 2: You cannot reconfigure *existing* zones from this interface (e.g. to add or modify IP addresses). You need to use '**Network Zones**' if you want to change the settings of existing zones.

Deny access to an existing network zone

- Click 'Add from Network Zone' button from the top
- Choose the particular zone you wish to block from the 'Network Zone' drop-down.






- Click 'Add'
- · Repeat the process to add more blocked network zones for the profile

To deny access to a network by manually defining a new blocked zone

Click the 'Add' button from the top.





• Select the address type you wish to block from the 'Type' drop-down. Select 'Exclude' if you want to block all IP addresses except for the ones you specify using the drop-down.

Address Types:


- i. Any Address Will block connections from all IP addresses (0.0.0.0- 255.255.255.255)
- ii. Host Name- Enter a named host which denotes an address on your network.
- IPv4 Range Will block access to the IPv4 addresses you specify in the 'Start Range' and 'End Range' text boxes.
- iv. IPv4 Single Address Block access to a single address e.g. 192.168.200.113.
- v. IPv4 Subnet Mask A subnet mask allows administrators to divide a network into two or more networks by splitting the host part of an IP address into subnet and host numbers. Enter the IP address and Mask of the network you wish to block.
- vi. IPv6 Single Address -Block access to a single address e.g. 3ffe:1900:4545:3:200:f8ff:fe21:67cf.
- vii. IPv6 Subnet Mask. Ipv6 networks can be divided into smaller networks called sub-networks (or subnets). An IP address/ Mask is a subnet defined by IP address and mask of the network. Enter the IP address and Mask of the network.
- viii. MAC Address Block access to a specific MAC address.
- Select the address to be blocked and click 'OK'




- The address(es) you block will appear in the 'Blocked Zones' tab. You can modify these addresses at any time by selecting the entry and clicking 'Edit'.
- 3. Click 'OK' in 'Network Zones' interface to confirm your choice. All traffic intended for and originating from computer or devices in this zone are now blocked.

Portsets

Port Sets are handy, predefined groupings of one or more ports that can be re-used and deployed across multiple **Application Rules** and **Global Rules**. The 'Port Sets' panel under the 'Firewall' tab allows you to view and manage pre-defined port sets and to add new port sets for the profile. The name of the port set is listed above the actual port numbers that belong to that set.



The panel lists all portsets that are defined for the profile. Clicking the 'Edit' icon
beside a name reveals the ports included in the set.



Endpoint Manager ships with three default portsets:



- **HTTP Ports**: 80, 443 and 8080. These are the default ports for http traffic. Your internet browser uses these ports to connect to the internet and other networks.
- **POP3/SMTP Ports**: 110, 25, 143, 995, 465 and 587. These ports are typically used for email communication by mail clients like Outlook and Thunderbird.
- Privileged Ports: 0-1023. This set can be deployed if you wish to create a rule that allows or blocks
 access to the privileged port range of 0-1023. Privileged ports are so called because it is usually
 desirable to prevent users from running services on these ports. Network admins usually reserve or
 prohibit the use of these ports.


Define a new Port Set

You can create new portsets and allow access to them for applications, with the access privileges specified through **Application Rule** interface. See 'Create or Modify Firewall Rules' for more details.

To add a new portset

Click the 'Add' button from the top.

The 'Portset' dialog will open.




- Enter a name for the new portset in the 'Name' field.
- To add ports to the new portset, click the 'Add' button above the list of ports.
- Specify the ports to be included in the new portset:



- Any to choose all ports;
- A single port Define the port number in the combo box beside;
- A port range Enter the start and end port numbers in the respective combo boxes.
- Exclude (i.e. NOT the choice below): The opposite of what you specify is applicable.
- Click 'OK' in the 'Port' dialog. The ports will be added to the new portset in the 'Edit Portset' interface.
- Click 'OK' in the 'Portset' dialog to create the new portset.

Once created, a Portset can be:

Quickly called as 'A Set of Ports' when creating or modifying a Firewall Ruleset





To edit an existing port set

- Click the 'Edit' icon beside the name of the portset. The 'Portset' dialog will appear with a list of port numbers in the port set.
- The editing procedure is similar to adding the portset explained above.
- Click the 'Save' button at the top of 'Firewall' interface to sane your settings for the profile.

The saved 'Firewall' settings screen will be displayed with options to edit the settings or delete the section. See **Edit Configuration Profiles** for more details.


6.1.3.1.5. HIPS Settings

- The host intrusion prevention system (HIPS) constantly monitors system activity. It only allows processes to run if they comply with the security rules in the profile on the endpoint.
- For example, HIPS protects system-critical files and registry keys from unauthorized modification by malware.
- Comodo Client Security (CCS) ships with a default HIPS ruleset that provides extremely high levels of protection 'out of the box'. You can also create custom rulesets as required.
- You can configure the feature by adding a HIPS section to a Windows profile.

Configure HIPS

- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Windows profile to open it's details page
 - Click the 'HIPS' tab, if it has already been added to the profile OR
 - Click 'Add Profile Section' > 'HIPS' if it hasn't yet been added

You can use the default HIPS settings or import them from a predefined profile:



- The default settings differ slightly from those in the various profiles. For example, there are two HIPS rules in the security level 1 profile, but there are no rules in the default settings.
- In either case, you can always modify the HIPS settings later as required.
- Make your selection then click 'Ok'.



The HIPS settings screen contains four tabs:

- HIPS Settings Configure settings that govern the overall behavior of the HIPS component.
- HIPS Rules View and create rules that control the behavior of applications on the managed computer.
- Rulesets View predefined rulesets and create new rulesets. Rulesets can be applied to applications on managed computers.
- Protected Objects A protected object is a collection of items which can be referenced as the target of a
 HIPS rule. For example 'Registry Keys' and 'COM Classes'. This interface lets you view and create new
 protected objects.

HIPS Settings


HIPS Settings - Table of Parameters				
Form Element	Description			
Enable HIPS	Activate or deactivate HIPS protection on managed computers to which the profile is applied. If enabled, you can configure the HIPS security level and monitoring settings. (Default=Enabled in safe mode)			
Hips Security Level	If HIPS is enabled, you can choose the security level for the HIPS to provide at the managed computer from the drop-down below 'Enable HIPS'. Enable HIPS			
	Safe Mode: While monitoring critical system activity, HIPS automatically learns the activity of executables and applications certified as 'Safe' by Comodo. It also automatically creates 'Allow' rules for these activities, if the option 'Create rules for safe applications' is selected. For non-certified, unknown, applications, the end-user will receive an alert whenever that application attempts to run. Should you choose, the end-user can add that new application to the safe list by choosing 'Treat this application as a Trusted Application' at the alert. This instructs the HIPS not to generate an alert the next time it runs. If			



the endpoint is not new or known to be free of malware and other threats then 'Safe Mode' is recommended setting for most users - combining the highest levels of security with an easy-to-manage number of HIPS alerts. Training Mode: HIPS monitors and learn the activity of any and all executables and create automatic 'Allow' rules until the security level is adjusted. The enduser will not receive any HIPS alerts in 'Training Mode'. If you choose the 'Training Mode' setting, we advise that you are 100% sure that all applications and executables installed on the endpoints are safe to run. Note - If required you can enable training mode to work temporarily. To do that, select 'Temporarily switch HIPS to training mode' option and set the days / hours. itors critical operating system activities to protect the computer against malware actions. Monitoring settings Temporarily switch HIPS to training mode. CC v 6.27 and higher This option switches HIPS to training mode for the selected time period and starts the timer. When the time elapses, HIPS will be automatically switched to the mode set above Period Days 0 After the countdown is over, CCS will switch back to previous mode. If HIPS is enabled, you can configure the activities, entities and objects that should **Monitoring Settings**

monitored by it at the managed endpoint by clicking the 'Monitoring Settings' link.





Activities To Monitor:

- Interprocess Memory Access Malware programs use memory space modification to inject malicious code for numerous types of attacks. These include recording your keyboard strokes; modifying the behavior of applications and stealing data by sending confidential information from one process to another. One of the most serious aspects of memory-space breaches is the ability of the offending malware to take the identity of a compromised process to 'impersonate' the application under attack. This makes life harder for traditional virus scanning software and intrusion-detection systems. Leave this option selected, and HIPS generates alerts when an application attempts to modify the memory space allocated to another application (Default = Enabled)
- Windows/WinEvent Hooks In the Microsoft Windows® operating system, a hook is a mechanism by which a function can intercept events before they reach an application. Example intercepted events include messages, mouse actions and keystrokes. Hooks can react to these events and, in some cases, modify or discard them. Originally developed to allow legitimate software developers to develop more powerful and useful applications, hooks have also been exploited by hackers to create more powerful malware. Examples include malware that can record every stroke on your keyboard; record your mouse movements; monitor and modify all messages on your computer and take remote control of your computer. Leaving this option selected means that an alert is generated every time a hook is executed by an untrusted application (Default = Enabled).



- Device Driver Installations Device drivers are small programs that allow applications and/or operating systems to interact with hardware devices on the managed computer. Hardware devices include your disk drives, graphics card, wireless and LAN network cards, CPU, mouse, USB devices, monitor, DVD player etc. Even the installation of a perfectly well-intentioned device driver can lead to system instability if it conflicts with other drivers on the system. The installation of a malicious driver could, obviously, cause irreparable damage to the computer or even pass control of that device to a hacker. Leaving this option selected means HIPS generates alerts every time a device driver is installed on the computer by an untrusted application (Default = Enabled).
- **Processes' Terminations -** A process is a running instance of a program. Terminating a process, obviously, terminates the program. Viruses and Trojan horses often try to shut down the processes of any security software you have been running in order to bypass it. With this setting enabled, HIPS monitors and generates alerts for all attempts by an untrusted application to close down another application (*Default = Enabled*).
- Process Execution Malware such as rootkits and key-loggers often execute
 as background processes. With this setting enabled, HIPS monitors and
 generates alerts whenever a process is invoked by an untrusted application.
 (Default = Enabled).
- Windows Messages This setting means Comodo Client Security monitors and detects if one application attempts to send special Windows Messages to modify the behavior of another application (e.g. by using the WM_PASTE command) (Default = Enabled).
- DNS/RPC Client Service This setting generates alerts if an application attempts to access the 'Windows DNS service' possibly in order to launch a DNS recursion attack. A DNS recursion attack is a type of Distributed Denial of Service attack whereby a malicious entity sends several thousand spoofed requests to a DNS server. The requests are spoofed in that they appear to come from the target or 'victim' server but in fact come from different sources often a network of 'zombie' computers which send out the requests without the owners knowledge. The DNS servers are tricked into sending all their replies to the victim server overwhelming it with requests and causing it to crash. Leaving this setting enabled prevents malware from using the DNS Client Service to launch such an attack (Default = Enabled).

Objects To Monitor Against Modifications:

- Protected COM Interfaces enables monitoring of COM interfaces you specified from the COM Protection pane. (Default = Enabled)
- Protected Registry Keys enables monitoring of Registry keys you specified from the Registry Protection pane. (Default = Enabled).
- Protected Files/Folders enables monitoring of files and folders you specified from the File Protection pane. (Default = Enabled).

Objects To Monitor Against Direct Access:

Determines whether or not Comodo Client Security should monitor access to system critical objects on the managed computer. Using direct access methods, malicious applications can obtain data from a storage devices, modify or infect other executable software, record keystrokes and more. Comodo advises the average user to leave these settings enabled:

Physical Memory: Monitors your computer's memory for direct access by an
applications and processes. Malicious programs attempt to access physical
memory to run a wide range of exploits - the most famous being the 'Buffer
Overflow' exploit. Buffer overruns occur when an interface designed to store a



certain amount of data at a specific address in memory allows a malicious			
process to supply too much data to that address. This overwrites its internal structures and can be used by malware to force the system to execute its code (<i>Default = Enabled</i>).			
• Computer Monitor: Comodo Client Security raises an alert every time a process tries to directly access the computer monitor. Although legitimate applications sometimes require this access, spyware can also use such access to take screen shots of the current desktop, record browsing activities of the user and more (Default = Enabled).			
 Disks: Monitors the local disk drives at the managed computer, for direct access by running processes. This helps guard against malicious software that need this access to, for example, obtain data stored on the drives, destroy files on a hard disk, format the drive or corrupt the file system by writing junk data (Default = Enabled). 			
 Keyboard: Monitors the keyboard for access attempts. Malicious software, known as 'key loggers', can record every stroke made on keyboard and can be used to steal passwords, credit card numbers and other personal data typed through the keyboard. With this setting is enabled, Comodo Client Security generates alerts every time an application attempts to establish direct access to the keyboard (<i>Default = Enabled</i>). 			
Note : The settings you choose here are universally applied. If you disable monitoring of an activity, entity or object using this interface it completely switches off monitoring of that activity on a global basis - effectively creating a universal 'Allow' rule for that activity . This 'Allow' setting over-rules any Ruleset specific 'Block' or 'Ask' setting for that activity that you may have selected using the 'Access Rights' and 'Protection Settings' interface.			
Configure whether or not the HIPS alerts are to be displayed at the managed computer for the end-user to respond. Choosing 'Do NOT show popup alerts' will minimize disturbances but at some loss of user awareness (<i>Default = Enabled</i>).			
If you choose not to show alerts then you have a choice of default responses that CCS should automatically take - either 'Block Requests' or 'Allow Requests'.			
■ Do NOT show popup alerts Allow Requests ✓			
Cat popus alorts to verbose m. Allow Requests			
Block Requests			
Enabling this option instructs CCS to display HIPS alerts in verbose mode, providing more more informative alerts and more options for the user to allow or block the requests (<i>Default = Enabled</i>).			
CCS will auto-create allow rules for known-safe applications. (Default = Enabled)			
Note: HIPS trusts an application if:			
The app is from a vendor who has a 'Trusted' status in the local vendor list in CCS			
The app is trusted in the online file database (aka, it is whitelisted)			
The app is trusted in the local CCS 'File List'			
See File Rating Settings for more details.			
Determines how long the HIPS shows an alert for without any user intervention. By default, the timeout is set at 60 seconds. You may adjust this setting to your own preference.			




Enable adaptive mode under low system resources	Very rarely (and only in a heavily loaded system), low memory conditions might cause certain CCS functions to fail. With this option enabled, CCS will attempt to locate and utilize memory using adaptive techniques so that it can complete its pending tasks. However, the cost of enabling this option may be reduced performance in even lightly loaded systems (<i>Default = Enabled</i>).
Block unknown requests when the application is not running	Selecting this option blocks all unknown execution requests if Comodo Client Security is not running/has been shut down. This is option is very strict indeed and in most cases should only be enabled on seriously infested or compromised machines while the user is working to resolve these issues. If you know the managed computer machine is already 'clean' and are looking just to enable the highest CCS security settings then it is OK to leave this option disabled. (<i>Default = Disabled</i>)
Enable enhanced protection mode (Requires a system restart)	64 bit systems only. Activate additional protections which counteract sophisticated malware that tries to bypass regular HIPS protection. Because of limitations in Windows 7/8 x64 systems, some HIPS functions in previous versions of CCS could theoretically be bypassed by malware. Enhanced Protection Mode implements several patent-pending ways to improve HIPS. The endpoint requires a restart to enable enhanced protection mode. (<i>Default = Disabled</i>)

HIPS Rules

The 'HIPS Rules' screen allows you to view the list of active HIPS rulesets applied to different groups of or individual applications and to create and manage rules for the profile. You can change the ruleset applied to a selected application or application group.

Note: HIPS Rulesets are to be created before applying them to an individual application or an application group. Refer to the next section **Rulesets** for details on creating new rulesets.





HIPS Rules - Column Descriptions		
Column Header	Column Header Description	
Application	Name of the individual application or the application group to which the ruleset is applied	
Treat As	The ruleset applied. For more details on the rulesets, see the next section Rulesets.	
Actions	Contains control buttons to edit or remove the rule	

Create and Modify HIPS Rules


To begin defining an application's HIPS rule, you need take two basic steps.

- Step 1 Select the application that you wish the ruleset is to be applied.
- Step2 Configure the rules for this application's ruleset.

Step 1 - Select the application that you wish the ruleset is to be applied

• To define a ruleset for a new application (i.e. one that is not already listed), click the 'Add Rule' button at the top of the list in the 'HIPS Rules' interface.


The 'HIPS Rule' interface will open as shown below:





Because this is a new application, the 'Name' field is blank. (If you are modifying an existing rule, then this interface shows the individual rules for that application's ruleset).

- To create a rule for a single application enter the file name of it in the 'Name' field
- To create a rule for an application group, select 'Use Group' and choose the file group from the drop-down




Note: Endpoint Manager ships with a set of predefined file groups containing collections of files under respective categories. Admins can also create custom file groups with required applications. All the pre-defined and the custom file groups will be available in the drop-down. The custom file groups can be created under 'Settings' > 'System Templates' > 'File Groups Variables' interface. See **Create and Manage File Groups** for more details.

Step 2 - Configure the rules for this application's ruleset

There are two broad options available for creating a ruleset that applies to an application - **Use a Predefined Ruleset** or **Use a Custom Ruleset**.

Use a Predefined Ruleset - Allows you to quickly deploy an existing HIPS ruleset on to the target
application. Choose the ruleset you wish to use from the drop-down menu. The name of the predefined
ruleset you choose is displayed in the 'Treat As' column for that application in the 'HIPS Rules'
interface.








Note: Predefined Rulesets, once chosen, cannot be modified *directly* from this interface - they can only be modified and defined using the **Ruleset** interface. If you require the ability to modify components of the rule set, then you are effectively creating a new, custom ruleset and should choose the more flexible **Use Custom Ruleset** option instead.

Use a Custom Ruleset - Designed for more experienced administrators, the 'Custom Ruleset' option
grants full control over the configuration of each rule within that ruleset. The custom ruleset has two main
configuration areas - Access Rights and Protection Settings. (Default = Enabled)



In simplistic terms 'Access Rights' determine what the application *can do to other processes and objects* whereas 'Protection Settings' determine what the application *can have done to it by other processes*.

 Access Rights - The 'Process Access Rights' area allows you to determine what activities can be performed by the applications in your custom ruleset.


ITarian Endpoint Manager - Administrator Guide






See HIPS Settings > Activities to Monitor to view a list of definitions of the Action Names listed above and the implications of choosing the action from 'Ask', 'Allow' or 'Block' for each setting as shown below:

- Exceptions to your choice of 'Ask', 'Allow' or 'Block' can be specified for the ruleset by clicking the 'Modify' link on the right.
- Select the 'Allowed Files/Folders' or 'Blocked Files/Folders' tab depending on the type of exception you wish to create.



- Click the 'Add' button at the top to choose which applications or file groups you wish this exception to apply to. (click here for an explanation of available options).
- ii. **Protection Settings -** Protection Settings determine how protected the application or file group in your ruleset is *against* activities by other processes. These protections are called 'Protection Types'.





• Select 'Active' to enable monitoring and protect the application or file group against the process listed in the 'Protection State' column. Select 'Inactive' to disable such protection.

Click here to view a list of definitions of the 'Protection Types' listed above and the implications of activating each setting.


Exceptions to your choice of 'Active' or 'Inactive' can be specified in the application's Ruleset by clicking the 'Modify' link on the right.

Click 'OK' to confirm your settings.

Rulesets

A Pre-defined ruleset is a set of access rights and protection settings that has been saved and can be re-used and deployed on multiple applications or groups. Each ruleset is comprised of a number of rules and each of these rules is defined by a set of conditions/settings/parameters. Rulesets concern an application's access rights to memory, other programs, the registry etc.

The Rulesets screen under the 'HIPS' tab displays the list of rulesets and allows you to add and manage new rulesets.






Add a new ruleset

Click the 'Add Ruleset' button

Add Ruleset

above the list of rulesets.

The 'HIPS Ruleset' dialog will appear.




- Enter a name for the ruleset
- Configure the Actions, states and exclusions for 'Access Rights' and 'Protection Settings' as explained
 above. Any changes you make here are automatically rolled out to all applications that are covered by the
 ruleset. The new ruleset will be available for deployment to HIPS rule for applications/application groups
 from the HIPS Rules interface.
- To edit a ruleset, click the Edit button under the Actions in the Rulesets interface. The Editing process is similar to the Ruleset creation process explained above.



Protected Objects

The 'Protected Objects' panel under 'HIPS' tab lets you specify items at the managed computers to be protected against access or modification by unauthorized processes and services. These include files and folders, system critical registry keys and COM interfaces.



The 'Show' drop-down allows you to choose the category of protected objects to be displayed in the list and add and manage the protected objects of that category. You can add following categories of protected objects:

- Protected Files Allows you to view and specify programs, applications, files an file groups that are to be protected from changes
- Registry Keys Allows you to view and specify registry keys that are to be protected from changes
- COM Interfaces Allows you to view and specify COM interfaces that are to be protected from changes

Protected Files


The 'Protected Files' list under 'Protected Objects' interface allows you to view and manage list of files and file groups that are to be protected from access by other programs, especially malicious programs such as virus, Trojans and spyware at the managed computer. It is also useful for safeguarding very valuable files (spreadsheets, databases, documents) by denying any user and any program the ability to modify the file - avoiding the possibility of accidental or deliberate sabotage. If a file is 'Protected' it can still be accessed and read by users, but not altered. A good example of a file that ought to be protected is your 'hosts' file (c:\windows\system32\drivers\etc\hosts). Placing this in the 'Protected Files and Folders' area would allow web browsers to access and read from the file as per normal. However, should any process attempt to modify it then Comodo Client Security blocks this attempt and produces a 'Protected File Access' pop-up alert.


If you add a file to 'Protected Files', but want to allow trusted application to access it, then rules can be defined in HIPS Rulesets. Refer to the explanation of **adding 'Exceptions' at the end of this section** for more details about how to allow access to files placed in Protected Files.

 To view the list of Protected Files, choose 'Protected Files' from the 'Show' drop-down in the 'Protected Objects' interface

The Protected File list is displayed under two categories, which can be selected from the drop-down at the right.







- To view the list of individual files, programs, applications added to the Protected Files list and manage them, choose 'File List'
- To view the File Groups added to the Protected File list, choose 'Group List'

You can add individual files, programs, applications or file/groups to 'Protected Files'.

Add an individual file, program or an application

Choose 'File List' from the drop-down at the right and click the 'Add File Path' button.






- Enter the installation/storage path with file name of the file to be protected, in the managed computers, in the 'Add Protected File Path' dialog and click 'OK'.
- · Repeat the process to add more files.
- To edit the path of an item in the list, click the Edit icon under the 'Actions' in the list.
- To remove an item from the list, click the trash can icon under 'Actions' in the list

Add an application/file group to the Protected Files list

• Choose 'Group List' from the drop-down at the right and click the 'Add Protected Group' button





Choose the file group from the drop-down and click 'OK'.

Note: Endpoint Manager ships with a set of predefined file groups containing collections of files under respective categories. You can also create custom file groups with required applications. All the pre-defined and the custom file groups will be available in the drop-down. The custom file groups can be created under 'Settings' > 'System Templates' > 'File Groups Variables' interface. See **Create and Manage File Groups** for more details.


- Repeat the process to add more file groups.
- To edit the path of an item in the list, click the Edit icon under the 'Actions' in the list.
- To remove an item from the list, click the trash can icon under 'Actions' in the list

Exceptions

You can choose to selectively allow another application (or file group) to modify a protected file by affording the appropriate 'Access Right' in 'HIPS Rules' interface. A simplistic example would be the imaginary file 'Accounts.ods'. You would want the 'Open Office Calc' program to be able to modify this file as you are working on it, but you would not want it to be accessed by a potential malicious program. You would first add the spreadsheet to the 'Protected Files' area. Once added to 'Protected Files', you would go into 'HIPS Rules' and create an exception for 'scalc' so that it alone could modify 'Accounts.ods'.

- First add Accounts.ods to 'Protected Files' area as explained above.
- Then go to 'HIPS Rules' interface and add it to the list of applications.
- In the 'HIPS Rule' interface, enter the file name as Accounts.ods, choose 'Use a Custom Ruleset' and select a ruleset from the 'Copy From' drop-down.
- Under 'Access Rights' tab, set all the rules to 'Ask'






- Click the 'Modify' beside 'Protected File/Folders'
- Under the 'Access Rights' section, click the link 'Modify' beside the entry 'Protected Files/Folders'.

The 'Protected Files/Folders' interface will appear.

 Under the 'Allowed Files/Folders' section, click 'Add' > 'Files' and add scalc.exe as exceptions to the 'Ask' or 'Block' rule in the 'Access Rights'.






Another example of where protected files should be given selective access is the Windows system directory at 'c:\windows\system32'. Files in this folder should be off-limits to modification by anything except certain, Trusted, applications like Windows Updater Applications. In this case, you would add the directory c:\windows\system32* to the 'Protected Files area (* = all files in this directory). Next go to 'HIPS Rules', locate the file group 'Windows Updater Applications' in the list and follow the same process outlined above to create an exception for that group of executables.

Registry Keys


The 'Registry Keys' list under 'Protected Objects' interface allows you to view and manage list of critical registry keys and registry groups to be protected against modification. Irreversible damage can be caused to the managed endpoint if important registry keys are corrupted or modified in any way. It is essential that the registry keys are protected against any type of attack.

To view the list of Protected Registry Keys, choose 'Registry Keys' from the 'Show' drop-down in the 'Protected Objects' interface





The Protected Registry Keys list is displayed under two categories, which can be selected from the drop-down at the right.




- To view the list of individual keys and values, and manage them, choose 'Key List'
- · To view the Registry Groups, choose 'Group List'

You can add individual registry keys and Registry groups to Protected Registry Keys list.

Add an individual key

• Choose 'Key List' from the drop-down at the right and click the 'Add Registry Key' button.




- Enter the key name to be protected in the 'Add Registry Key' dialog and click 'OK'.
- Repeat the process to add more keys.
- To edit an item in the list, click the 'Edit' icon under the 'Actions' in the list.
- To remove an item from the list, click the trash can icon under 'Actions' in the list

Add a Registry group to the Protected Registry Keys list

Choose 'Group List' from the drop-down at the right and click the 'Add Protected Files' button

ITarian Endpoint Manager - Administrator Guide





Choose the Registry group from the drop-down and click 'OK'.

Note: Endpoint Manager ships with a set of predefined Registry groups containing collections of registry keys under respective categories. You can also create custom Registry groups with required key values. All the predefined and the custom Registry groups will be available in the drop-down. The custom Registry groups can be created under 'Settings' > 'System Templates' > 'Registry Variables' interface. See **Create and Manage Registry Groups** for more details.

- Repeat the process to add more Registry groups.
- To edit the an item in the list, click the Edit icon under the 'Actions' in the list.
- To remove an item from the list, click the trash can icon under 'Actions' in the list

COM Interfaces


Component Object Model (COM) is Microsoft's object-oriented programming model that defines how objects interact within a single application or between applications - specifying how components work together and inter-operate. COM is used as the basis for Active X and OLE - two favorite targets of hackers and malicious programs to launch attacks on a computer. It is a critical part of any security system to restrict processes from accessing the Component Object Model - in other words, to protect the COM interfaces.

The 'COM Interfaces' list under 'Protected Objects' interface allows you to view and manage list of individual COM classes and COM groups that are to be protected by the Comodo Client Security at the managed computer against modification, corruption and manipulation by malicious processes.


View the list of Protected COM interfaces

Choose 'COM Interfaces' from the 'Show' drop-down in the 'Protected Objects' interface





The Protected COM Interfaces list is displayed under two categories, which can be selected from the drop-down at the right.




- To view the list of individual COM Interfaces/Classes and manage them, choose 'Classes List'
- To view the COM Groups and manage them, choose 'Group List'

You can add individual COM Interfaces/Classes and/or pre-defined COM groups to 'Protected COM Objects' list.

Add an individual COM object

Choose 'Classes List' from the drop-down at the right and click the 'Add COM Class' button






- Click 'Add'
- Repeat the process to add multiple procedures to the profile
- · Click 'Save' to add the procedures to the profile
- To remove an item from the list, click the trash can icon under 'Actions' in the list

Add a predefined COM Group to the Protected COM objects list

• Choose 'Group List' from the drop-down at the right and click the 'Add COM Group' button





Choose the file group from the drop-down and click 'OK'.

Note: Endpoint Manager ships with a set of predefined COM groups containing collections of COM interfaces under respective categories. You can also create custom COM groups with required COM objects. All the predefined and the custom file groups will be available in the drop-down. The custom COM groups can be created under 'Settings' > 'System Templates' > 'COM Variables' interface. See **Create and Manage COM Groups** for more details.

- Repeat the process to add more COM groups.
- To edit the an item in the list, click the Edit icon under the 'Actions' in the list.
- To remove an item from the list, click the trash can icon under 'Actions' in the list

6.1.3.1.6. Containment Settings

- Comodo Client Security (CCS) can run all unknown files in a security hardened environment known as the 'container'.
- Files in the container are prevented from causing damage because they are isolated from the OS, file system and user data.
- The containment settings area lets you configure the container and the virtual desktop.
- You can create rules to define what types of files should be contained and at what restriction level.
 Restriction levels include:
 - Run Virtually. The file is completely isolated from your operating system and files on your computer
 - Run Restricted. The file is contained but has limited access to operating system resources
 - Block. The file is completely prevented from running
 - **Ignore**. The file is run outside the container without restrictions
 - See Auto-Containment Rules for more information about rules.
- You can also block contained applications from accessing specific files, folders and registry keys.




- The virtual desktop is separate, sandbox environment in which you can run Windows programs and internet browsers. Programs in the virtual desktop are isolated from the rest of the host, preventing them from potentially causing damage.
- Modifications to containment settings are automatically logged. You can view the old and new values in the 'Dashboard' > 'Audit Logs' screen. See 'Audit Logs' in the 'Dashboard' section for more information.

Configure the container

- Click 'Configuration Templates' > 'Profiles'
- · Open the Windows profile you want to work on
- Click 'Add Profile Section' > 'Containment'


You can use the default settings or import them from a predefined profile:



- The default settings differ slightly from those in the various profiles. For example, auto-containment is enabled in the security level 1 profile but disabled in the default settings.
- In either case, you can always modify the containment settings later as required.
- Make your selection then click 'Ok'.

The containment settings screen opens:





The containment section has six tabs:


- Containment Settings
- Auto-Containment Rules
- Baseline Settings
- Virtual Desktop Settings
- Protected Data
- Protected Keys

Containment Settings

- · Open the 'Containment' section of a profile
- Click the 'Settings' tab:

ITarian Endpoint Manager - Administrator Guide





Containment Settings - Table of Parameters			
Form Element	Description		
Enable Auto-Containment	Activate or deactivate auto-containment on the endpoint. If enabled, CCS will automatically run unknown applications inside the container.		
	You can also create rules to fine-tune exactly which types of files are contained.		
	See Configure Rules for Auto-Containment if you want to read more on containment rules.		
	(Default = Disabled)		
Enable file source tracking	If enabled, CCS will consider the origin of a file when deciding whether to contain it or not.		
	For example, if you only want to auto-contain files downloaded from the internet, then 'internet' is your source.		
	If this setting is disabled then the source is disregarded. Only the reputation and location of the file itself are considered.		



Containment Settings - Table of Parameters		
	Applies only to CCS versions 8.3 or lower.	
(Default = Disabled)		
Do not virtualize access to the specified files/folders	By default, contained applications can access folders and files on the local system but cannot save changes to them. This setting lets you define exceptions to that rule. Contained applications will be able to access and save changes to the folders you specify.	
	 See exclusions for files/tolders (below this table) to find out how to add exclusions. 	
	Note - This setting determines whether or not a contained application can access specific files/folders on your local system. It does not determine whether or not an application should run in the container in the first place. If you wish to exclude applications in their entirety from the container, see 'Configure Rules for Auto-Containment' instead.	
Do not virtualize access to the specified registry keys/values	 Contained applications can access registry keys and values on the local system but cannot save any changes to them. This setting lets you define exceptions to that rule. Contained applications will be able to access and save changes to registry items. Click the 'Exclusions' link to choose registry keys/values which contained files are allowed to modify. (Default = Disabled) 	
	See exclusions for registry keys/values (below this table) to find out how to add exclusions.	
Do not virtualize access to the removable media	Allow contained applications to write to external storage devices like USB sticks and external hard disk drives. (<i>Default = Disabled</i>)	
	By default, applications in the container can only save data to a folder called 'Shared Space'. Users can save data to this folder if they want to access it from the host system.	
	This setting provides another way to export data from the container or virtual desktop.	
Do not restrict access to COM/DCOM for apps	By default, contained applications cannot access the COM and DCOM components running on a Windows device.	
	This setting lets you specify applications that can access COM / DCOM components, even if the app is in the container.	
	(Default = Disabled)	
	See Allow selected applications to access COM / DCOM components when run in container to find out how to add applications.	
Enable automatic startup for services installed in the Containment	By default, CCS does not permit contained services to run at Windows startup. Select this check-box to allow them to do so on target endpoints. (<i>Default = Disabled</i>)	
Show highlight frame for contained programs	Shows a green border around programs running in the container. (Default = Disabled)	



Containment Settings - Table of Parameters		
CCS proactively tracks programs that request A program that is allowed to run with eleval make changes to important areas of the eleval (Default = Disabled)	ated privileges is permitted to	
If 'Detect' is enabled (see setting above) end-user when a new or unrecognized pro elevated privileges to run. If you do not was select this option and choose the action to programs:	ogram requires admin or ant these alerts to be shown,	
Do not show privilege elevations alerts Do not show internal Containment service applications	Run contained Run contained Run unlimited Run unlimited and trust Block	
(Default = Disabled)		
Any processes started by CCC/CCS will no Process List' in CCS.	not be shown in the 'Active	
You can view contained processes in CCS	S by clicking:	
Tasks' > 'General Tasks' > 'View A	Active Processes'	
Right-click anywhere in the interf only'	face > select 'Show Contained	
(Default = Enabled)		
Info about Comodo client processes which not sent to Endpoint Manager. Client proc CCC or CCS themselves.		
Click 'Security Sub-Systems' > 'Containment history of contained applications and procedure (Default = Enabled)		
	CCS proactively tracks programs that requests a program that is allowed to run with eleval make changes to important areas of the elevated changes to important areas of the elevated. If 'Detect' is enabled (see setting above) end-user when a new or unrecognized programs are this option and choose the action to programs: Do not show privilege elevations alerts Do not show internal Containment services are tracked. (Default = Disabled) Any processes started by CCC/CCS will reprocess List' in CCS. You can view contained processes in CCS. Tasks' > 'General Tasks' > 'View are reproduced. Right-click anywhere in the interfonly' (Default = Enabled) Info about Comodo client processes which not sent to Endpoint Manager. Client processes to CCC or CCS themselves. Click 'Security Sub-Systems' > 'Containment istory of contained applications and processes of the contained applications and processes.	

Define exclusions for files and folders


Note. This section explains how to create an exclusion which allows an application in the container to access specific files and folders on the local system. If you want to entirely exclude an application from the container, then please see **'Configure Rules for Auto-Containment'** instead.

Contained applications write to a virtual file system, preventing them from potentially damaging files on the host. This setting lets you define exceptions to that rule. You can specify folders or files on the host system which contained applications are allowed to access.


Access scope if enabled:

- Data files (.doc, .txt etc) Read/Write/Rename/Delete. Useful, for example, if you want MS Word in the container to save changes to a .doc file on the host file system.
- Executable files (.exe, .msi etc) Rename/Delete only.
- Enable 'Do not virtualize access to the specified files/folders', then click 'Exclusions':






- Exclusion Paths Enter the location of an individual item that you want to exclude. Contained
 files can write to the files/folders you specify here. You can add multiple files by clicking 'Add'
 again.
- Exclusion Groups Allow contained apps to access the processes of apps in a particular group. A
 file group is a collection of file types which have similar attributes, scope, or functionality. For
 example, 'Executables', 'Metro Apps', or 'Windows System Applications'. Endpoint Manager ships
 with a set of pre-defined file groups. You can create custom file groups from the 'Settings' >
 'System Templates' > 'File Groups Variables' interface. See Create and Manage File Groups for
 more details.
- Click 'Add' then 'Path' or 'File Group' as required:








- Click 'OK' to save your settings.
- You can edit or remove the exclusions using the respective buttons in the 'Action' column in the File/Folders interface.


Define exclusions for specific Registry keys and values

- Contained applications can access registry keys and values on the local system but cannot save any
 changes to them. This setting lets you define exceptions to that rule. Contained applications will be able to
 access and save changes to registry items.
- Enable 'Do not virtualize access to specified registry keys/values' and click 'Exclusions' beside it:






- Exclusion Registry Keys Enter the location of an individual key that you want to exclude. Contained files can write to the keys you specify here. You can add multiple keys by clicking 'Add' again.
- Exclusion Registry Groups Allow contained applications to access all keys in a particular group. A registry group is a collection keys with similar scope or functionality. Endpoint Manager ships with a set of registry groups. You can create custom registry groups from the 'Settings' > 'System Templates' > 'Registry Variables' interface. See Create and Manage Registry Groups for more details.
- Click 'Add' then 'Registry Entry' or 'Registry Group' as required:







Click 'OK' to save your settings.


You can remove the exclusions using the trash can buttons in the 'Action' column in the 'Manage Exclusions' interface.

Allow selected applications to access COM / DCOM components when run in container

- Component Object Model (COM) is Microsoft's object-oriented programming model that defines how
 objects interact within a single application or between applications specifying how components work
 together and inter-operate. COM is used as the basis for Active X and OLE two favorite targets of hackers
 and malicious programs to launch attacks on a computer.
- By default, contained applications are prohibited from accessing the COM or Distributed COM (DCOM) components currently running on a device.
- If required, you can create a list of applications, that can access the COM and DCOM components, even if the application is run inside the container.
- Enable 'Do not restrict access to COM/DCOM for apps' and click 'Exclusions' beside it:


ITarian Endpoint Manager - Administrator Guide






- The 'Manage Exclusions' dialog will appear with a list of defined exclusions under two tabs:
 - **Exclusion Paths** Enter the location of an individual item that you want to add. The application you specify here can access COM / DCOM components, when run inside the containment.
 - Exclusion Groups Allow applications in a particular group to access COM / DCOM interfaces. A
 file group is a collection of file types which have similar attributes, scope, or functionality. For
 example, 'Executables', 'Metro Apps', or 'Windows System Applications'. Endpoint Manager ships
 with a set of pre-defined file groups. You can create custom file groups from the 'Settings' >
 'System Templates' > 'File Groups Variables' interface. See Create and Manage File Groups for
 more details.
- Click 'Add' then 'Path' or 'File Group' as required:







Click 'OK' to save your settings.



You can edit or remove the exclusions using the respective buttons in the 'Action' column in the Manage Exclusions interface.


Click the 'Save' button.

Configure Auto-Containment Rules

- Containment rules determine whether a program should run as normal, run with restrictions, or run in the virtual environment. CCS consults these rules every time a program is opened on the endpoint.
- A contained application has much less opportunity to damage the endpoint because it is isolated from the operating system, system files and personal data.
- CCS shows a green border around contained programs if so configured in **containment settings**.

Open the rules interface:

- Click 'Configuration Templates' > 'Profiles'
- Open the profile you wish to work on
- Click the 'Containment' tab (click 'Add Profile Section' > 'Containment' if you haven't added it yet)
- Click the 'Rules' tab to view and manage auto-containment rules:



- The table lists all rules configured for the profile.
- Rules at the top of the table have a higher priority than those at the bottom. The setting in the rule nearer
 the top will prevail in the event of a conflict between rules.

Containment Rules - Column Descriptions		
Column Heading	Description	
Target	The file, file group, or location on which the rule should run.	
Reputation	The trust status of the files to which the rule should apply. The possible values are: 'Any' 'Malicious' 'Trusted' 'Unrecognized'.	
Behavior	The action that will be taken on the targets if the rule criteria are met. Possible actions are:	



- Run virtually. File is sandboxed inside a fully virtual environment.
- Run restricted. File is sandboxed with limited access to device resources.
- Block. File is not allowed to run at all.
- **Ignore**. File is not sandboxed and is allowed to run on the host without restriction.
- Use the slider to enable/disable a rule.
- Click the trash icon to remove a rule.
- Click the edit icon to modify a rule.

Target(s) can be filtered by numerous criteria. These are, however, optional, so admins can create a very simple rule to run an application in the container just by specifying the action and the target application.

Example:


Run an application outside the container

- Open the containment tab and click 'Rules'
- Click 'Add Rule'
- Select 'Ignore' in the 'Action' drop-down
- · Click 'Edit' in the 'Criteria' section to choose the application(s) you wish to exclude
- Choose the file, folder, file group or hash you want to exclude
- Click 'OK'
- Move the new rule to the top of the rules list (you can drag and drop rules)

Add a new rule

- Open the profile you wish to add the rule to
- Click the 'Containment' tab. Click 'Add Profile Section' > 'Containment' if you haven't added it yet.
- Click the 'Rules' tab
 - Click the 'Add Rule' button
- The 'Manage Contained Program' dialog will open:





The dialog shows the action at the top and contains two tabs:

- Criteria Define conditions upon which the rule should be applied.
- Options Configure additional actions like logging, memory allowance and execution time restrictions.


Creating a new containment rule involves the following steps:

- Step 1 Choose the action
- Step 2 Select the target file/group and set the filter criteria for the target files
- Step 3 Select the options

Step 1 - Choose the action

• The setting in the 'Action' drop-down, and the restriction in the 'Options' tab, determine the privileges of an auto-contained application.





- Run Restricted The application is allowed to access very few operating system resources. The
 application is not allowed to execute more than 10 processes at a time and is run with very limited
 access rights. Some applications, like computer games, may not work properly under this setting.
- **Run Virtually** The application will be run in a virtual environment completely isolated from your operating system and files on the rest of your computer.
- Block The application is not allowed to run at all.
- **Ignore** The application will not be contained and allowed to run with all privileges.
- Choose the action from the options.

Step 2 - Select the target file/group and set the filter criteria

- The next step is to select the target files and configure filters.
- You can filter a rule so it applies to specific files.
 - For example, you can choose 'All executables' as the target, then add a filter so it only affects executables from the internet.
 - Another example is if you want to allow unrecognized files created by a certain user to run outside
 the container. You would create an 'Ignore' rule with 'All Applications' as the target, then add 'Files
 created by a specific user' as the filter.


Select the target and set filters

· Click the 'Criteria' tab.

The target and the filter criteria, if any, configured for the rule will be displayed.

Click the 'Edit' button at the far right to add new target and filter criteria





The 'File Criteria' dialog will open. The file criteria dialog allows you:



- Select the target
- · Configure the filter criteria

Select the target

- Select the type of target item from the 'Type' drop-down. You can choose an application, file group, hash, or folder as your target:
 - Files Apply the rule to a specific file.
 - Add an executable as the target by entering its installation path + file name.
 - File Groups Apply the rule to predefined file groups.
 - File groups are handy, predefined groupings of one or more file types.
 - For example, selecting 'Executables' would include all files with the extensions .exe .dll
 .sys .ocx .bat .pif .scr. Other predefined categories include 'Windows System Applications'
 , 'Windows Updater Applications' and 'Start Up Folders'.
 - You can also create custom file groups in 'Settings' > 'System Templates' > 'File Groups Variables'. See 'Create and Manage File Groups' for more details.
 - Select a predefined or custom file-group as required.
 - Folder Apply the rule to all files in a folder or drive
 - Enter the path to the folder that contains the target files in the field provided.
 - File Hash Apply the rule to all files that have a specific SHA1 hash value.
 - A hash value is a large number which is generated by passing the file through a hashing algorithm. The number uniquely identifies the file, and it is extremely unlikely that two files will ever generate the same hash value. The benefit of using a file hash is that the rule will still work even if the file name changes.
 - Enter the SHA1 hash value of the target executable file in the 'Target' field.
 - Process Hash Apply the rule to files whose processes have a specific SHA1 hash value. Please see description above if required.
 - Enter the SHA1 hash value of the process created by the target file in the 'Target' field.

Configure the Filter Criteria and File Rating

Filter criteria let you further refine which files are caught by the rule. The available filters are:

- By application that created the file
- By process that created the file
- By user that created the file
- By file origin
- By file rating
- By file age


Auto-contain a file if it was created by a specific application

- Create a filter to apply an action to a file based on its parent application.
- You can also specify the file rating of the source application. The rule will then only contain a file if its parent has a certain trust rating.

Specify source applications


• Click the 'Add' button in the 'File Created by applications' stripe.





The 'Action' you specified earlier will be applied to files matching the type and reputation you choose here:

- Type See target types above for more details.
- **Reputation** Choose the file rating of the source you specified in the 'Type' drop-down.



- Click 'OK' to save your settings
- Repeat the process to add more source applications




- To edit the source application items in the list, click the 'Edit' at the right of the item
- To remove an item, click 'Delete' at the right of the item

Auto-contain a file if it was created by a specific process

- Create a filter to apply an action to a file based on its parent process.
- Optionally, you can also specify:
 - The file rating of the source. The rule will then only contain a file if its parent process has a certain trust rating.
 - The number of levels in the process chain that should be inspected.

Specify source processes


Click the 'Add' button in the 'File Created by Process(es)' stripe:



The 'Action' you chose earlier will be applied to files matching the type and reputation you pick here:


- Type See target types above for more details.
- **Reputation** Choose the file rating of the source you specified in the 'Type' drop-down.





Click 'OK'

The source process type will be added.




- 'Limit number of parent processes in the process chain to' Specify how far up the process tree CCS should check when inspecting the file's sources. 1 = will only check the file's parent process. 2 = will check the parent process and the grand-parent process, etc., etc.
- · Repeat the process to add more source processes
- Click the 'Edit' if you want to modify the source process items.

Auto-contain a file created by specific user(s)

Click the 'Add' button in the 'File Created by User(s)' stripe.





- The 'Add Creator' dialog will appear.
- Choose the pre-defined user group from the 'Created by' drop-down


The User Group will be added to the list of creators.

- Repeat the process to add more user groups
- Click 'X' at the right end of the user name to remove a group

Auto-contain a file downloaded/copied from a specific source

- Click the 'Add' button in the 'File Origin(s)' stripe.
- · Choose the source from the options:






- Internet The rule will only apply to files that were downloaded from the internet.
- **Removable Media** The rule will only apply to items copied to the computer from removable devices. For example, from a USB drive, CD/DVD, or external storage.
- Intranet The rule will only apply to files that were downloaded from the local intranet.
- Repeat the process to add more sources
- To remove a source added by mistake or no longer needed in the list, click 'X' at the right end of the item

Select the file rating as filter criteria

· Click the 'Select' button in the 'File Rating' stripe




- This will apply the rule to files which match the trust rating you set. You can choose from the following trust ratings:
 - Trusted Applications are categorized as 'Trusted' if:
 - · The file is on the global whitelist of safe files
 - The file is signed by a trusted vendor
 - The file was installed by a trusted installer
 - The file was given a trusted rating by an admin ('Settings' > 'Application Control')
 - See Manage File Trust Ratings on Windows Devices for more information.
 - **Unrecognized** Files that do not have a current trust rating. The file is on neither the blacklist nor the safelist, so is given an 'unknown' trust rating.
 - Malicious Malware files those that are on the blacklist of known harmful files.



Set the file age as filter criteria


• Click the 'Select' button in the 'File age' stripe.



The 'File Age' dialog will appear. You can set the file age in two ways:

- **File Creation Date** To set a threshold date to include the files created before or after that date, choose this option, choose 'Before'/'After' from the first drop-down and set the threshold date and time in the respective combo-boxes.
- **File age** To select the files whose age is less than or more than a certain period, choose this option and specify the period.
 - Less Than CCS will check the reputation of a file if it is younger than the age you set here.
 - More Than CCS will check the reputation of a file ifit is older than the age you set here.
- Click 'OK' in the 'File Criteria' dialog after selecting the filters to save your settings to the rule. The list of criteria will be displayed under the Criteria tab in the 'Manage Contained Program' dialog.






Step 3 - Select options

The next step is to choose additional options and restrictions on items contained by the rule.

Click the 'Options' tab.





The options available depend on the 'Action' chosen in **Step 1**.

The 'Ignore' action has the following options:

- Log when this action is performed Creates a containment log in CCS on the endpoint when the rule is triggered.
- Don't apply the selected action to child processes Child processes are those started by the target application.
 - This option is disabled by default, so the ignore rule also applies to child processes.
 - If enabled, the ignore rule does not apply to child processes. Each child process will be inspected individually and all relevant rules applied.

The 'Run Restricted' and 'Run Virtually' actions have the following options:

- Log when this action is performed Creates a containment log in CCS on the endpoint when the rule is triggered.
- Set Restriction Level If the rule is triggered, CCS runs the file at the restriction level you set.

You can choose from the following levels:

- Partially Limited The application is allowed to access all operating system files and resources
 like the clipboard. Modification of protected files/registry keys is not allowed. Privileged operations
 like loading drivers or debugging other applications are also not allowed. (Default)
- Limited Only selected operating system resources can be accessed by the application. The
 application is not allowed to execute more than 10 processes at a time and is run without
 Administrator account privileges.



- Restricted The application is allowed to access very few operating system resources. The
 application is not allowed to execute more than 10 processes at a time and is run with very limited
 access rights. Some applications, like computer games, may not work properly under this setting.
- Untrusted The application is not allowed to access any operating system resources. The
 application is not allowed to execute more than 10 processes at a time and is run with very limited
 access rights. Some applications that require user interaction may not work properly under this
 setting.


Note. You must choose a restriction level if 'Run Restricted' is the action. However, you can disable 'Set Restriction Level' if the action is 'Run Virtually'.

- **Limit maximum memory consumption to** Enter the maximum amount of memory that the application is allowed to use (in MB).
- **Limit program execution time to** Specify how long the application is allowed to run. Enter the maximum time in seconds. The program is automatically terminated when the time limit expires.

The 'Block' action has the following options:

- Log when this action is performed Creates a containment log in CCS on the endpoint when the rule is triggered.
- Quarantine program Applications satisfying the rule will be automatically quarantined. See View and Manage Quarantined Items on Windows Devices if you want to read more about the quarantine area.

Click 'OK' to save your choices. The rule will be added to the list of rules.



- Repeat the process to add more rules
- You can drag-and-drop the rules to re-prioritize them. Rules at the top of the table have a higher priority
 than those at the bottom. The setting in the rule nearer the top will prevail in the event of a conflict between
 rules.
- You can edit or remove rules at any time using the options at the right.


Baseline Settings

- A baseline period is a window of time during which all unknown files are submitted to Valkyrie for analysis.
- Unknown files are not auto-contained during the baseline. This feature is best used during the initial setup period when, typically, many unknown files are discovered.
- You must enable 'Stop Baseline and enable...' if you want the baseline to last a specific length of time. If you don't then the baseline period runs indefinitely.

Configure baseline settings



- Open the 'Containment' section of a profile
- Click the 'Baseline' tab:



Baseline Settings - Table of Parameters		
Form Element	Description	
Enable Baseline	A baseline is a period of time during which unknown files discovered on your network are sent to Valkyrie. Unknown files are not run in the container during the baseline period.	
	This can be useful if you want to create a whitelist of existing files on your network.	
	(Default = Disabled)	
Stop Baseline and Enable Auto- Containment after countdown	Enabled - Baselining will last the length of time you set in the fields. Auto-containment will resume when this period expires.	
	Disabled - Baselining will continue until you disable it in the setting at the top.	
	The timer begins after you apply the profile to your network.	
	(Default = Disabled)	

Click 'Save' to apply your changes.

Virtual Desktop Settings


- The 'Virtual Desktop' is a sandbox environment in which users can run programs and browse the internet without fear those activities will damage their computer.
- Applications in the virtual desktop are isolated from other processes, write to a virtual file system, and cannot access user data.
- This makes it ideal for risk-free internet surfing, beta-software, and general computer use. From the users point-of-view, programs in the virtual desktop run exactly as they would under Windows.
- Virtual desktop settings let you configure the behavior of the feature on endpoints.

Configure virtual desktop settings

· Open the 'Containment' section of a profile



Click the 'Virtual Desktop' tab:




Automatically reset Virtual Desktop when session is terminated - All data saved in the virtual
desktop is deleted when the desktop is closed. All changes are reversed. This includes any files
downloaded from the internet and any system changes.

Please use the 'Shared Space' folder to store files you want to keep. You can also enable external storage devices for use with the virtual desktop in **Containment Settings**.



Protect paused Virtual Desktop session with PIN - Generates a session specific PIN number at
virtual desktop startup. The PIN is required to resume the session from a paused state. This is useful
on shared computers as it prevents other users from accessing the session.




- **Duration of paused Virtual Desktop session before its automatic termination** Set the maximum time that a virtual desktop session can be left in a paused state. The session gets automatically terminated when this period elapses.
- Request password when exiting Virtual Desktop Create an 'exit' password for the virtual desktop.

 Users need to enter the password in order to close the virtual desktop.
 - This prevent users from closing the virtual desktop and accessing the host, potentially exposing the computer to danger.
 - Type a password that cannot easily be guessed. Passwords must be 8-16 characters and contain a mix of upper case letters, lower case letters, numbers, and special characters.
 - Re-enter the password for confirmation.
- Show disclaimer upon Virtual Desktop startup Create a disclaimer which is shown when the virtual desktop starts. Users must accept the disclaimer before they can access the virtual desktop.

Note - This setting is only of value if you are **rebranding the Comodo clients**. You can safely ignore this setting if you do not plan to rebrand.

- Enter the disclaimer message
- The message is shown when the virtual desktop starts.
- Users should read the disclaimer and click 'Accept'. An example is shown below:






- Allow user to override Virtual Desktop settings Changes to virtual desktop settings at the endpoint are not reversed by Endpoint Manager.
 - By default, EM checks devices to see if the local CCS settings match those in the profile. It will reimplement the profile settings if it detects any deviation.
 - Enabling this option stops the process described above. The EM profile does not apply any virtual desktop settings. Only the virtual desktop settings in CCS on the endpoint are applied to the device.
 - Note 1. This option complements the existing override option in the 'Client Access Control' section
 of a profile, which allows local changes to *every* CCS setting. You can allow local override of just
 the virtual desktop settings, while preventing changes to other CCS settings. See Client Access
 Control for help with this.
 - Note 2. If you enable this option, you effectively cancel all Virtual Desktop settings that come from the profile. For example, 'Exit Password', 'Reset Virtual Desktop' and 'Duration' settings will not get applied.

Users


Specify user groups for whom the virtual desktop should start automatically after login. This means the virtual desktop is the users' default environment, instead of the host operating system. This setting is especially useful for guest users and for public computers in libraries / class-rooms etc.

Click 'Add' under the 'Users' section:






Select a user group from the 'Created by' drop-down and click 'OK'.



The selected user group is added to the list:






- Use 'ON/OFF' switches to enable or disable the feature for a particular group.
- Repeat the process to add more user groups
- Click 'Save' to apply your changes to the profile.

Protected Data

- The 'Protected Data' tab lets you define files, folders and files in a file group that are to be denied access to the contained applications on the managed devices.
- Items in 'Protected Data' cannot be seen, accessed or modified by applications running in the container.
- This fortifies files containing sensitive data from unrecognized and potentially malicious programs.




Protected Files and Protected Data

- Items in HIPS 'Protected Files' ('HIPS' > 'Protected Objects' > 'Protected Files') can be read by any program, but not modified by them. This contrasts to items in 'Protected Data' in containment settings, which are totally hidden to contained programs.
- If you want a file/folder to be read by other programs, but protected from modification, then add it to 'Protected Files' list.
- If you want to totally conceal an item from contained programs, but allow read/write access to trusted programs, then add it to 'Protected Data'.
- You can add the same item to both areas. This means trusted programs have read-only access to the file, and contained programs have no access rights.



Add and manage protected data

- Open the 'Containment' section of a profile
- Click the 'Protected Data' tab.
- Click 'Add'




You add items in two ways:

- File path Add individual files, applications, programs executables or folders
- File groups Add a pre-defined group of files so that all member files in the group are blocked form contained applications

Add files or folders

Choose 'File path' from the 'Add' drop-down






- Enter the installation path / storage location of the file to add an application or a file
- Enter the folder path to add a folder
- Click 'OK'
- · Repeat the process to add more items

Add file groups

A file group is a collection of file types which have similar attributes, scope, or functionality. For example, 'Executables', 'Metro Apps', or 'Windows System Applications'. Endpoint Manager ships with a set of pre-defined file groups. You can create custom file groups from the 'Settings' > 'System Templates' > 'File Groups Variables' interface. See **Create and Manage File Groups** for more details.


Choose 'File groups' from the 'Add' drop-down





- Select the file group from the drop-down
- · Repeat the process to add more file groups

The items added are shown as a list under the 'Protected Data' tab.




- You can edit or remove the items using the respective buttons in the 'Action' column in the 'Protected Data' interface.
- Click 'Save' for your settings to take effect.




Protected Keys

- The 'Protected Keys' tab lets you define Windows registry keys and key groups to be denied access to the contained applications on the managed devices.
- Adding important registry keys to this area will protect them from unknown and potentially malicious programs.



Add and manage protected registry keys

- Open the 'Containment' section of a profile
- Click the 'Protected Data' tab.
- Click 'Add'




You add items in two ways:

- Registry Entry Add individual keys
- Registry Groups Add a pre-defined group of registry keys so that all member keys in the group are blocked form contained applications

Add registry keys

· Choose 'Registry Entry' from the 'Add' drop-down






- Enter the location of an individual key that you want to protect and click 'OK'.
- Repeat the process to add more items

Add registry groups

A registry group is a collection keys with similar scope or functionality. Endpoint Manager ships with a set of registry groups. You can create custom registry groups from the 'Settings' > 'System Templates' > Registry Variables' interface. See **Create and Manage Registry Groups** for more details.


Choose 'Registry Group' from the 'Ádd' drop-down





- Choose a group to be protected
- Repeat the process to add more groups

The items added are shown as a list under the 'Protected Keys' tab.



 You can edit or remove the items using the respective buttons in the 'Action' column in the 'Protected Keys' interface.

Click 'Save' for your settings to take effect.

6.1.3.1.7. Maintenance Window Settings

- A maintenance window is a scheduled time-slot when your Endpoint Manager procedures will run. You can create them by adding a 'Maintenance Window' section to a Windows profile.
- Once created, you can assign the maintenance window to a procedure in the procedure settings. You can
 assign multiple procedures to the same maintenance window.




- You can also add multiple maintenance windows to a profile. This lets you assign different procedures to different time-slots.
- You have the option to pause all running monitors while the maintenance window runs, and to randomize task start times to avoid system congestion.
- You can block certain tasks from running outside of a maintenance window. Example tasks include remote control sessions, patch installation and more.
 - Alternatively, you can show a warning to the admin which asks if they want to move the task to the maintenance window instead.
- You can define times when maintenance windows should not run. For example, holidays, weekends or other occasions.

Create a maintenance window

- Click 'Configuration Templates' > 'Profiles'
- · Click the name of a Windows profile
- Click 'Add Profile Section' > 'Maintenance Window'

The maintenance windows screen opens:




Click the following links for more info on each tab:

- Maintenance Window (MW) Configure the time-slot and settings you want to use.
- General Settings Choose whether to randomize tasks and/or define no-maintenance times.

Create a Maintenance Window

Click 'Add Window' (or 'Edit' then 'Add Window')






You can define a time-slot and additional settings for each maintenance window.

- General Configure when the maintenance window should run.
 - Name Create a label for the window. For example, 'Maintenance Window 11 PM to 1 AM'
 - Scheduled Choose how often you want to run the maintenance:
 - Daily Select the start and end time of the window. The window runs every day at the time you set.
 - Weekly Select the start and end times, and the days of the week that the window should run.
 - Monthly Select the start and end times, and the days of the month that the window should run.
 - Week of Month Select the start and end times, the week number, and the days that the window should run. Use this, for example, if you want to run the window once every two weeks.
 - **Enable after submitting** Make the window available for use after clicking 'OK'. Only enabled windows are available for selection with procedures.
- MW Settings Configure additional settings for the MW. Click the 'Settings' tab.






- Stop monitors during maintenance window Pause all monitors on a device for the duration of the maintenance window.
- Skip procedures for offline device during maintenance windows:
 - Run procedure as soon as device became online The procedure is executed when the device is next connects to Endpoint Manager.
 - Run procedure during the nearest maintenance window The procedure is executed in the
 next available window after the device comes online.
- On-demand maintenance tasks out of Maintenance Window Endpoint Manager can block or show a
 warning if someone tries to run tasks outside of a maintenance window. You can warn/block the following
 tasks:
 - Remote control
 - Remote tools
 - · On-demand patch installation
 - Other MSI package installation
 - On-demand running script procedures
 - On-demand running patch procedures
 - Reboot system

Example block/warn messages are shown below:





Click 'OK'

Repeat the procedure to add more maintenance windows.

Edit a MW

Select a MW and click 'Edit' at the top. The procedure is similar to adding explained above.

Enable / Disable

• Select a MW and click 'Enable / Disable' at the top. Note - Only active MWs are available for selection.

Delete

Select a MW and click 'Delete' at the top. Note - You cannot delete MWs that are in use.

Configure MW General Settings


These settings apply to all maintenance windows in the profile.

Click the 'General Settings' tab




- Randomize task starting times for each device within the maintenance window to minimize the load on the network and systems - Staggers task start-times to prevent several procedures running at the same time on each device. This can ease congestion and lead to a smoother roll-out of your procedures.
- **Define no-maintenance window for stopping all maintenance tasks** Configure periods during which maintenance windows should not run. For example, during holidays.





Click 'Add No-Maintenance Window'



- Name Provide an appropriate label for the no-MW. For example, 'New year holiday'.
- Start and Finish dates Select from the calendar or enter the start and end period.
- Click 'Ok'

Repeat the process to add more no-maintenance windows.

Edit a no-MW

Select an item, click 'Edit' and update as explained above

Delete a no-MW

- · Select an item and click 'Delete'
- Click 'Save' to apply your changes

6.1.3.1.8. VirusScope Settings

- 'VirusScope' is a CCS feature which closely monitors the activities of running processes and generates alerts if they take threatening actions.
- The feature uses a system of 'recognizers' to detect malicious behavior and thus identify brand-new malware.
- VirusScope alerts offer the choice to quarantine the process & undo its changes, or let the process go ahead.



You can choose whether VirusScope should monitor all processes, or only contained processes.

To configure VirusScope settings

- Click 'Configuration Templates' > 'Profiles'
- · Click the name of a Windows profile
- Click 'Add Profile Section' > 'VirusScope'


The VirusScope settings screen will open:



VirusScope Configuration - Table of Parameters		
Form Element	Description	
Enable Viruscope	Enable or disable Viruscope. If enabled, Viruscope monitors the activities of all running processes and generates alerts on suspicious activities	
Show popup alerts	Configure whether or not alerts are shown to end-users when suspicious activity is detected.	
	 Disabling alerts will minimize disturbances but at some loss of user awareness. If you disable alerts then threats are automatically quarantined and their activities are reversed. 	
Monitor contained applications only	Choose whether VirusScope should track every process on the host, or only processes which are running in the container.	

· Click the 'Save' button.

The VirusScope component will be added to the Windows profile.





The saved 'VirusScope' settings screen will be displayed with options to edit the settings or delete the section. See **Edit Configuration Profiles** for more details.

6.1.3.1.9. Valkyrie Settings

- Valkyrie is a cloud-based file verdict service that subjects unknown files to a range of tests in order to identify those that are malicious.
- Comodo Client Security can automatically submit unknown files to Valkyrie for analysis. When the tests are complete, Valkyrie will award a trust verdict to the file.
- You can view the verdicts at 'Security Sub-Systems' > 'Valkyrie'
 - See View list of Valkyrie Analyzed Files for more details.
- Click 'Dashboard' > 'Valkyrie' to view summary of all Valkyrie results.


Note: The Valkyrie that comes with the free version of Endpoint Manager will only run automated tests on an unknown file. The Premium version also includes manual testing by ITarian research technicians.

You can configure general Valkyrie settings and create an analysis schedule in the Valkyrie component of a Windows profile.

Configure Valkyrie Settings

Click 'Valkyrie' from the 'Add Profile Section' drop-down in the Windows Profile interface

The 'Valkyrie' settings screen will be displayed.





Valkyrie Settings - Table of Parameters		
Form Element	Description	
Lookup and Submit Files with Valkyrie	Choose this option if you want the files to be submitted to the cloud file lookup service	
Check Manual Analysis Interval (sec)*	How often CCS should contact Valkyrie for the verdicts on files submitted for manual analysis. (Default=60)	
Check Auto Analysis Interval (sec)*	How often CCS should contact Valkyrie for the verdicts on files submitted for automatic analysis. (Default=60)	
Submit for	Choose the type of Valkyrie analysis. Submit for Automatic analysis Automatic analysis Automatic and human-expert analysis • Automatic analysis - Unknown files are only tested by Valkyrie's automatic testing service. • Automatic and human-expert analysis - Unknown files are tested by Valkyrie's automatic testing service, and then by Comodo research lab technicians. Available only for premium license holders.	
Enable Auto Whitelisting if NO suspicious activities detected by Automatic and/or Human-Expert analysis	Choose this option if you wish the files identified as harmless by Valkyrie to be added to your local whitelist.	
Do NOT lookup and submit files to Valkyrie if File Lookup Service returns error	Choose this option, if you don't want Valkyrie file analysis in case file look up service (FLS) failed.	
Submit Metadata	Choose this option if you wish the unknown file is to be submitted to Valkyrie, along with their metadata. Metadata gives information about the file source, author, date of creation and so forth.	
Submit When	Choose when the unknown files are to be submitted. The options available are: Immediately - CCS uploads the file to Valkyrie as soon as it encounters an Unknown file Schedule Analysis - CCS accumulates the unknown files and uploads them as per the set schedule. See Valkyrie Analysis Schedule about how to set analysis schedule.	

Fields marked * are mandatory.


• The 'Valkyrie Premium License' link takes to Valkyrie signup page for a full subscription.

Valkyrie Analysis Schedule

The Valkyrie allows you to create a schedule for CCS to upload unknown files.



Select 'Schedule Analysis' from the 'Submit When' drop-down.



- To upload the unknown files daily choose 'Daily' from the drop-down at the top and set the time for upload in HH:MM format in the combo boxes under 'Time'.
- To upload the unknown files once per week, choose 'Every Week' from the drop-down at the top. Choose
 the day of the week from the 'Day of Week' options and set the time for upload in HH:MM format in the
 combo boxes under 'Time'.
- To upload the unknown files monthly, choose 'Every Month' from the drop-down at the top, choose the day
 of the month from the 'Day of month' options and set the time for upload in HH:MM format in the combo
 boxes under 'Time'.


6.1.3.1.10. Global Proxy Settings

The Global Proxy settings allows you to specify a proxy server through which applications in endpoints using this profile should connect to external network such as the internet. Please note the setting done here will not affect how Comodo Client Security (CCS) and the Communication Client (CC) in the endpoints connect to Endpoint Manager and Comodo servers. The proxy setting for CCS and CC are done in the Client Proxy section.

onfigure Global Proxy Settings

Click 'Global Proxy' from the 'Add Profile Section' drop-down in the Windows Profile interface





Global Proxy Settings - Table of Parameters		
Form Element	Description	
Type *	Select the kind of the proxy setting. Choice = automatic or manual.	
Pac Url*	This field is shown if 'Auto' is selected in the 'Type' field. Enter the path to your proxy auto-config file.	
Server *	This field is shown if 'Manual' is selected in the 'Type' field. Enter the address of your proxy server.	
Port *	This field is shown if 'Manual' is selected in the 'Type' field. Enter the port number of the proxy. If you do not have a set port number, port 8080 will work in many cases.	

^{* -} options are mandatory.

• Click 'Save' in the title bar to save your update settings to the profile.

6.1.3.1.11. Client Proxy Settings

- The client proxy section lets you choose a proxy through which Comodo clients should connect to Endpoint
 Manager and other ITarian services. If you do not set a proxy then CCS and CC will use a direct
 connection.
- The proxy you set here only affects the connections of Endpoint Manager clients. It does not affect how
 other applications on the endpoint connect to the internet. If required, you can set a proxy for all other
 applications in the Global Proxy section of a profile.
- You can specify different proxies for CC and CCS if required.
- **Note**. If you use the **bulk enrollment wizard** to create an installer, make sure you specify the same proxy during the enrollment wizard. If the proxy settings used in the installer differ to those in the profile, then the connection to EM will be lost after first successful connection.


Configure Client Proxy Settings

- Click 'Configuration Templates' > 'Profiles'
- Open the profile you want to work on
- Click the 'Clients Proxy' tab



OR

- Click 'Add Profile Section' > 'Clients Proxy', if it hasn't yet been added
- Click 'Clients Proxy' from the 'Add Profile Section' drop-down in the Windows Profile interface




The settings screen has two tabs:

- Communication client Specify the proxy for the communication client (CC). CC will use this proxy to connect to Endpoint Manager and other ITarian services.
- Security client Specify the proxy server for Comodo Client Security (CCS). CCS will use this proxy to connect to Comodo servers for program and database updates.

Communication Client:






- Use Proxy The communication client will connect to EM and other ITarian services through a proxy server (Default = Disabled)
 - Use same configurations also on Security Clients Proxy CCS will use the same proxy you
 configure for the communication client. (*Default = Disabled*)
- Server Enter the IP address or hostname of your proxy server
- Port The port on your proxy that CC should connect to. If you do not have a set port number, port 8080 will work in many cases.
- Username/Password If your proxy requires authentication, enter the admin credentials here.
- Use direct connection when communication over a proxy is unavailable Allow CC to fallback to a
 direct internet connection if the proxy fails.
 - If you specify a proxy BUT disable direct connections, then your endpoints will not be able to connect to EM if the proxy fails.
 - Leave the direct connection option enabled to ensure your devices are managed at all times.

Security Client:






- Use Proxy Comodo Client Security (CCS) will connect to Endpoint Manager and update servers through a proxy.
- Server Enter the IP address or hostname the proxy server
- Port The port on your proxy that CCS should connect to. If you do not have a set port number, port 8080 will work in many cases.
- Username/Password If your proxy requires authentication, enter the admin credentials here.
- Use direct connection when communication over a proxy is unavailable Allow CCS to fallback to a direct internet connection if the proxy fails.
 - If you specify a proxy BUT disable direct connections, then CCS will not be able to connect if the proxy fails
 - Leave the direct connection option enabled to ensure CCS is connected and up-to-date at all times.

Click 'Save' to apply your changes to the profile. The new settings will be automatically deployed to all endpoints on which the profile is active.

6.1.3.1.12. Agent Discovery Settings

The Agent Discovery Settings allows you to specify whether or not CCS should log antivirus and contained events on the endpoint.






- Antivirus Log Select this option if antivirus log is to be enabled
- Containment Log Select this option if containment log is to be enabled
- Click 'Save' to apply your changes.

6.1.3.1.13. Communication Client and Comodo Client - Security Application UI Settings

- The UI settings screen lets you configure the appearance of Communication Client (CC), Comodo Client Security (CCS) and the Virtual Desktop.
- You can re-brand these items with your own company name, logo, product name and product logo. In addition, you can:
 - Add your support website, phone number and email to the GUI
 - Select which parts of CCS should be visible to end-users

Configure UI settings

- Click 'Configuration Templates' > 'Profiles'
- Click the Windows profile in which you want to configure UI appearance
- Click 'Add Profile Section' > 'UI Settings'






The UI settings screen has three tabs:

- General Settings Select GUI language and which components/shortcuts are shown in the interface to the end-user.
- Communication Client Rebranding Customize CC with your own brand name, company logo and more.
- Comodo Client Security Rebranding Customize CCS and VD with your own brand name, company logo and more.

General Settings

- Open the 'UI Settings' section of a profile
- Click the 'General Settings' tab:



Form Element	Description
Language	The language which should be used in the Comodo Client Security interface. (Default = English (United States))
Show messages from Comodo Message Center	Message Center notifications appear as pop-ups at the bottom right-hand corner of the screen.



	They contain news about updates, offers and other items of interest. • Select whether or not the messages should be displayed to end-users
	(Default = Disabled)
Show notification messages	Notifications inform end-users about actions and status updates.
	CCS notices appear in the bottom-right corner of the screen (just above the tray icons).
	Select whether or not notifications should be shown to end-users.
	(Default = Disabled)
Show desktop widget	The widget contains shortcuts to important CCS tasks and information about security levels, traffic and background tasks.
	 Select whether or not the widget should be shown on endpoint desktops.
	(Default = Disabled)
Show information messages when tasks are minimized/sent to background	These messages inform end-users of the effects of minimizing or moving a running task to the background. For example, when a virus scan task is moved to the background.
	 Select whether or not information messages should be displayed to end- users.
	(Default = Disabled)
Play sound when an alert is	If selected, CCS plays a chime whenever it raises a security alert.
shown	(Default = Disabled)
Show shared space shortcut on the desktop	'Shared Space' is the special folder on an endpoint where contained applications are allowed to save files. The shared space shortcut provides access to this folder.
	Select whether or not the shortcut should be shown to end-users.
	(Default = Disabled)
Show security client tray icon	Choose whether or not the CCS icon is shown in the system tray. (Default = Enabled)
Show security client desktop shortcut icon	Select whether or not a CCS shortcut is placed on endpoint desktops. (Default = Disabled)
Show communication client	Select whether or not the CCC icon is shown in the system tray.
tray icon	 The tray icon lets end-users submit support tickets to Service Desk should they need assistance with their devices. If enabled, you can also let users submit tickets to specific departments. See Configure Service Desk departments available to end-user for help with this. (Default = Enabled)
Show file list	CCS can show a list of files on a device along with their trust ratings ('Trusted', 'Unrecognized' or 'Malicious'). This is available in 'Advanced Settings' > 'Security Settings' > 'File Rating' > 'File List'.
	See https://community.itarian.com/help/topic-459-1-1002-15223-File-List.html if you want to read more
	Select whether or not the file list should be available to end-users. (<i>Default = Disabled</i>)
Show vendor list	Allow local users to open the vendor list area of Comodo Client Security on an



	endpoint.
	CCS ships with a list of trusted vendors who have a reputation of creating legitimate, safe software. CCS allows unknown files which are digitally signed by one of these vendors to run.
	Users can also add new vendors, and change the rating of existing vendors.
	Click 'Advanced Settings' > 'Security Settings' > 'File Rating' > 'Vendors List' in CCS to view the vendor list.
	See https://community.itarian.com/help/topic-459-1-1002-15225-Vendor-List.html if you want to read more.
Show Virtual Desktop settings	If enabled:
only in security client interface	 The CCS tray icon and the widget are hidden on the endpoint.
	 The CCS desktop and start menu shortcuts only show virtual desktop options:
	 Run Virtual Desktop - Opens the virtual desktop
	 Open Virtual Desktop Settings - Opens the virtual desktop settings area in CCS ('Settings' > 'Containment' > 'Virtual Desktop')
	End-users cannot access any other area of CCS. (<i>Default = Disabled</i>)

Configure Service Desk departments available to end-user


• If enabled, users can right-click on the CCS system tray icon to send support tickets to Service Desk.

in Containment Settings for more details.

You have the option to add specific departments to this menu. Users can then submit their ticket to the
appropriate department for their request.

Note: This setting only works if 'Allow user to override Virtual Desktop settings' is disabled in the 'Containment' section of the profile. See **Virtual Desktop Settings**






- The 'Department' drop-down shows departments you have marked as 'Public' in Service Desk.
 - See https://community.itarian.com/help/topic-452-1-949-13154-Departments.html if you want more help with departments
- Click 'UI Settings' > 'General Settings' > 'Show communication client tray icon' to choose your departments

Select departments available to user

- Open the 'UI Settings' section of a profile
- · Click the 'General Settings' tab
- Enable 'Show communication client tray icon'
- Enable 'Configure Departments for Ticket Submission'






- The left pane shows all departments added to your Service Desk instance
 - Click the 'Synchronize' button to instantly import any new departments
- The right pane shows departments visible to end-users when they right-click the CCS tray icon
- Select a department on the left then click 'Add' to enable it for the end user
- Repeat the process to add more departments
- Select a department on the right then click 'Remove' to disable it for the end user
- · Click 'Save' to apply your changes

Communication Client Rebranding

The rebranding tab lets you change the appearance and interface texts of the communication client. This is especially useful for customers who wish to white-label the endpoint clients.

- You can change the company name, support website, phone number and email.
- You can upload replacement images for company logo, header logo, product icons and product logo.
- The online editor lets you preview your changes in real-time.





- Start typing in the fields to see your changes reflected in the example image
- Make sure all images you upload are the correct size and file format (.png).



	Communication Client Rebranding - Table of Parameters
Form Element	Description
Client Name	Enter a custom name for the application. You can use alphabetical, numeral and special characters. Maximum = 20 characters.
Company Name	Your company name.
Support Website	The URL of your support website. The URL will be shown in the 'About' dialog of the CC application.
Support Phone	Your customer support phone number. This number will be shown in the 'About' dialog of the CC application.
Support Email	Your customer support email address. This address will be shown in the 'About' dialog of the CC application.
Company Header Logo	Logo shown at the top-left corner of the application window. Accepted image size = 113 x 17 pixels Accepted image file format = .png
Company Logo	Logo shown at the top of the CC 'About' dialog. Accepted image size = 180 x 43 pixels Accepted image file format = .png
Product Logo	Logo shown at the left of the CC 'About' dialog. Accepted image size = 98 x 98 pixels Accepted image file format = .png
Icon	Windows start menu and shortcut icon. Accepted image sizes = 16 x 16, 20 x 20, 32 x 32, 40 x 40, 48 x 48 and 64 x 64 pixels Accepted image format = .ico. http://www.dihav.com/view.php?id=png2icon is a free tool to convert .png files to .ico files.'
Tray Icon (normal mode)	Tray icon shown when the communication client is connected to Endpoint Manager. Accepted image sizes = 16 x 16 pixels Accepted image file format = .png
Tray Icon (offline mode)	Tray icon shown when the communication client is not connected to Endpoint Manager. Accepted image sizes = 16 x 16 pixels Accepted image file format = .png

• Click 'Save' to apply your new design to the profile.


Comodo Client Security Rebranding

- The rebranding tab lets you change the appearance of CCS and the Virtual Desktop. You can add you own company logos and texts to reinforce your brand in the eyes of your customers.
- Related. You can also create a disclaimer message which is shown to users when they start the virtual desktop. This is configured in the 'Containment' section of a profile. See Virtual Desktop in Containment Settings if you want to read more about this.



Rebrand CCS interfaces

- · Open the 'UI settings' section of a profile
- Click the 'Comodo Client Security Rebranding' tab



ITarian Endpoint Manager - Administrator Guide



- Start typing in the fields to see your changes reflected in the example images.
- Make sure all images you upload are the correct size and file format (.png)
- The changes you make here will be rolled out to all interfaces in CCS.
- You cannot modify the UI in a default profile.



Comodo Client Security Rebranding - Table of Parameters		
Form Element	ent Description	
Company Header Logo	Logo shown at the top-left corner of the application window. Accepted image size = 122 x 24 pixels Accepted image file format = .png	
Company Logo	Logo shown in various CCS interfaces. Accepted image size = 150 x 24 pixels Accepted image file format = .png	
Product Logo	Logo shown on the left side of the CCS 'About' dialog. Accepted image size = 106 x 106 pixels Accepted image file format = .png	
Widget Caption	Logo shown on the header of the CCS desktop widget. Accepted image size = 189 x 28 pixels Accepted image file format = .png	
Icon	Windows start menu and shortcut icon. Also shown in various other interfaces of the application. Accepted image sizes = 16 x 16, 20 x 20, 32 x 32, 40 x 40, 48 x 48 and 64 x 64 pixels Accepted image format = .ico. http://www.dihav.com/view.php?id=png2icon is a free tool to convert .png files to .ico files.'	
Client Name	Enter a custom name for the application. This will be shown in the interface and will be used as the product name in the Windows 'Start' menu. You can use letters, numbers and special characters. Maximum = 20 characters.	
Comodo Virtual Desktop	· · · · · · · · · · · · · · · · · · ·	
Client Name	Enter a custom name for the application. This will be shown in the interface and will be used as the product name in the Windows 'Start' menu. You can use letters, numbers and special characters. Maximum = 25 characters.	
Wallpaper icon	Shown on the virtual desktop main screen. Accepted image size = 128 x 128 pixels Accepted image file format = .png	
Wallpaper image	Virtual desktop background image. Accepted image size = 1920 x 1200 pixels Accepted image file format = .png	
Start menu icon	Windows start menu and shortcut icon. Accepted image size = 32 x 32 pixels Accepted image file format = .png	
Widget icon	Logo shown on the header of the virtual desktop widget. Accepted image size = 24 x 24 pixels Accepted image file format = .png	

ITarian Endpoint Manager - Administrator Guide



- Click 'Save' to apply your settings to the profile.
- Click the 'Edit' button if you wish to modify a design that you have saved.

6.1.3.1.14. Logging Settings

- This area lets you specify how logs should be collected by the communication client (CC) and security client (CCS).
- For example, you can choose max. log size, log format and location, and extended log options.

Configure 'Logging' settings


- Click 'Configuration Templates' > 'Profiles'
- Open the Windows profile that you want to configure
- Click 'Add Profile Section' > 'Logging Settings'

The settings screen contains two tabs:

- Communication Client (CC) Configure CC log collection settings
- Comodo Client Security (CCS) Configure CCS log collection settings

Communication Client






Form Element	Description
Write to Local Log Database (COMODO Format)	The log is saved in native Comodo format on the local endpoint.



Form Element	Description
	You can select the events for which logs are collected and stored: • Monitoring logs • Script logs • OS patch logs • Third party application update logs • Application installation logs • Uninstall logs • Event Detection and Response (EDR) agent communication logs • Comodo Client - Security (CCS) communication logs • Remote Control Communication Logs
Write to Syslog Server	Operational Logs CC logs are written to a remote syslog server. If enabled, specify the hostname/IP address and port of the server.
Host *	The host name or IP address of the syslog server.
Port *	The port number on the syslog server to which CC should forward the logs.
Log file size (MB)	Specify the maximum limit for the size of the log file (Default = 100 MB)
Action when file log size reaches limit:	Specify behavior when the log file reaches a certain size.
Keep on updating it removing the oldest records	When the max. log size is reached, CC will remove the oldest entries to make way for new entries.
Move it to	CC will save the log file to a specific folder when it reaches the maximum size. CC will then start a new log file.
The path to the folder for old log files *	If 'Move it to' is enabled, type a destination path for the log file.
Crash dump collection	Endpoint Manager creates a dump file if the communication client crashes on an endpoint. The file contains details about the crash which can help our technicians diagnose and fix the issue. This file is automatically forwarded to Comodo servers. If enabled, you can choose the log type:
	Log Type - Choose the type of dump file you want. The options are:
	 Mini - The file only contains enough data to identify the conditions of the crash.
	 Full - A detailed log of all information related to the crash. Full logs let you analyze the crash in greater detail, but may take longer to generate than mini reports.
	No confidential or user data is included in either 'Full' or 'Mini' logs. (<i>Default = Disabled</i>)

Comodo Client - Security





Logging Settings - Comodo Client Security - Table of Parameters		
Form Element	Description	
Write to Local Log Database (COMODO Format)	The log is saved in native Comodo format on the local endpoint.	
Tomay	You can enable extended logging for the following additional items:	



	Process creation events
	CCS components are enabled/disabled by CC
	Changes to CCS configuration made by CC
	Submitting files to CAMAS or Valkyrie
Write to Syslog Server	EM log events are written to a remote syslog server. If enabled you have to specify the hostname/IP address and port number settings for the server.
Host *	The host name or IP address of the syslog server.
Port *	The port number of the syslog server.
Write to Log File (CEF Format)	Logs are saved locally on the endpoint in Common Event Format (CEF) file format. If enabled, please specify the location of the CEF file.
Path	Enter the storage location path of the CEF file.
Write to remote server (JSON format)	Logs are saved in JavaScript Object Notation (JSON) format on a remote server. If enabled, please specify the hostname/IP address of the server, its connection port and the security token.
Host *	Enter the host name or IP address of the remote server.
Port *	Type the port number of the remote sever for EM to connect to.
Token*	Enter the security token to access the remote server.
Log file size (MB)	Specify the maximum limit for the size of the log file (Default = 100 MB).
Action when file log size reaches limit:	Specify behavior when the log file reaches a certain size.
Keep on updating it removing the oldest records	Once the log file reaches the maximum size, the file will be appended with the new log entries and the oldest entries will be deleted depending on the size of the new entries.
Move it to	Choose this option if you wish to move and save the log file when it reaches the maximum size.
The path to the folder for old log files *	If 'Move it to' is enabled, type a destination path for the log file.
Send anonymous program statistics to Comodo	If enabled, select the types of statistics sent from the following options:
Crash dumps	CCS sends dump files to Comodo if the application crashes or there is a BSOD (blue screen of death) on the endpoint.
	This is useful for analysis and troubleshooting.
Telemetry Reports	Will send to Comodo a daily log about the files you scan with CCS. We use this data to improve EM and CCS.
	The reports contain the following details:
	The hash value and path of the file
	The hash value(s) and path of the parent file that executed the file



Size, certificate information, and attributes of the file

Fields marked * are mandatory.


- Click the 'Save' button to apply your changes.
- Click 'Delete' or 'Edit' to remove / edit the logging settings section. See 'Edit Configuration Profiles' for more details about editing the parameters

6.1.3.1.15. Client Access Control

- Client access control lets you password-protect Comodo Client Security (CCS) and the communication client (CC) on managed endpoints.
- Once set, users will need to enter a password to access important areas of the client interface.
- This stops users from opening the clients locally and making changes to important tasks and settings. Without password protection, the endpoint user can access the client interface and make changes.

Implement access control

- Click 'Configuration Templates' > 'Profiles'
- Click the name of the profile to which you want to add the section.
- Click 'Add Profile Section' > 'Client Access Control':



- Apply password protection settings for Specify which clients you want to password protect.
 - Comodo Client Security Password protects the settings interface and the 'Task' interfaces for antivirus, firewall, HIPS and containment.



Users can still run some limited tasks, including on-demand virus scans, open the virtual desktop, and run programs in the container.

- Communication Client Password protects important settings, including the ability to configure a
 proxy for the client to connect to the EM console.
 - Users can still submit support tickets to Service Desk from the tray icon without requiring the password.
- Require Password select the type of password required to access CCS and/or CC:
 - Computer administrator admins can access the local interfaces by providing their admin password.
 If the admin is already logged into the machine then they can open the interfaces without providing a password.
 - Custom password specify a unique key to access the CCS / CC interfaces. The password will timeout and need to be re-entered after 15 minutes.
 - If you select 'Custom password' but not 'Computer administrator', then even admins will need to enter the custom password to access the clients.

The tables below summarize how the passwords work together for admins and regular users:

Admin logged-in				
Admin password enabled	Yes	No	Yes	
Custom password enabled	Yes	Yes	No	
Requirements	No password needed	Custom password required	No password needed	

Admin not logged-in / Standard user logged-in				
Admin password enabled	Yes	No	Yes	
Custom password enabled	Yes	Yes	No	
Requirements	Either password	Custom password required	Admin password required	

Enable local user to override profile configuration - Endpoint Manager will not reverse local settings that are different to those in the endpoint's profile. You must enable password protection if you want to use this option.

Background - Endpoint Manager periodically checks devices to see if the local CCS settings match those in the device's profile. It will undo any local changes unless you enable this setting.

This is useful if you need to implement specific settings on a certain device.

Click 'Save' to apply your changes to the profile.

While you're here

The following is a list of other settings you should consider if you want to lock-down CCS on endpoints:

User Interface settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'UI Settings'

- Hide the CCC and CCS tray icons
- Manage the visibility of other UI items

Antivirus settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'Antivirus'



- Disable 'Show Antivirus alerts' *
- Enable 'Do not show auto-scan alerts' *
- Enable 'Automatically clean threats' (when you create a scheduled scan) *
- Disable 'Show scan results' (when you create a scheduled scan) *

Firewall settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'Firewall'

• Disable 'Show popup alerts' *

HIPS settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'HIPS'

Enable 'Do not show popup alerts' *

Containment setttings - 'Configuration Templates' > 'Profiles' > Add profile section > 'Containment'

Enable 'Do not show privilege elevations alerts' *

VirusScope settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'VirusScope'

Disable 'Show popup alerts' *

File rating Settings - 'Configuration Templates' > 'Profiles' > Add profile section > 'File Rating'

Disable 'Show cloud alert' *

External device control: - 'Configuration Templates' > 'Profiles' > Add profile section > 'External Device Control'

• Disable 'Show notifications when devices disabled or enabled' *

6.1.3.1.16. External Devices Control Settings

Lets you to define a list of devices that should be blocked on endpoints using this profile.

For example, you can block access to USB storage devices, human interface devices, Bluetooth devices, infrared devices, IDE ATA/ATAPI controllers.


- Endpoint Manager blocks access to devices connected through both serial and parallel ports and creates a log of their connection activities.
- You can create exclusions for external devices which you want to allow to connect to managed endpoints.
 Devices can be added as exclusion by specifying their Device Ids. You can use wildcard characters in the device ID if you want to include a series of devices with similar device IDs.

To configure External Devices Control Settings

- Click 'Configuration Templates' > 'Profiles' then click the name of the profile to which you want to add the section
- Click 'Add Profile Section' > 'External Devices Control'

^{*} This setting is already enforced in the 'Default' Windows profile that ships with Endpoint Manager.





- Enable Device Control Enable or disable the external device control feature. This is useful if you want to configure external device control settings for a profile during its creation and enable it at a later time
- Log detected devices Enable or disable logging of external device connection attempts on endpoints that
 use this profile. The logs can be viewed from 'Security Sub Systems' > 'Device Control' interface. See View
 History of External Device Connection Attempts for more details.
- Show notifications when devices disabled or enabled Select whether or not a notification is to be shown to end-user when a connected device is blocked or allowed.

The 'External Devices Control' settings interface contains two tabs:


- Blocked Device Classes Define the list of types of external devices to be blocked at the endpoints
- Exclusions Specify the devices that should be excluded from blocking and allowed access at the endpoints

Blocked Device Classes

The 'Blocked Device Classes' tab displays a list of types of device that are blocked as per the profile and allows you to add/remove new device types.

ITarian Endpoint Manager - Administrator Guide





Blocked Device Classes - Column Descriptions		
Column Header	Description	
Device Class	The device type as per global hardware classification	
Class ID	The Globally Unique Identifier (GUID) of the device class	


Tip. Block 'Portable Devices' in addition to 'USB storage devices' if you want to stop users connecting their phones to access the phone's memory card

To add device types to be blocked

Click 'Add' at the top of the list

The 'Add Device Class' dialog appears with a list of device types.






- Select the device types to be added to the block list and click 'Ok'.
- Repeat the process to add more device types.



To remove a device type from the list

· Select the device type from the list and click 'Delete'



Click 'Confirm' to remove the device type from the blocked list.

Exclusions

The 'Exclusions' tab displays a list of external devices that are exempt from the block rule and so allowed access to the endpoint(s).

ITarian Endpoint Manager - Administrator Guide






Exclusions - Column Descriptions			
Column Header	Description		
Device Custom Name	Displays the name of the device.		
Device ID	Displays the unique device identifier of the device.		

To add a device to be excluded

· Click 'Add' at the top of the list

The 'Add Device Class' dialog will appear with a list of device types.





- Enter a label for the device in the 'Device Custom Name' field (optional)
- Enter the unique device identifier in the 'Device ID' field

Tip: You can use a wildcard character '*' in the Device ID if you want to cover a range of devices with similar IDs. For example, to include all USB storage devices whose device IDs start with "4C5310", you could enter:

USBSTOR\DISK&VEN_SANDISK\4C5310*


Click 'Add'

The device will be added to the exclusions list and will be allowed access at the endpoint(s).

To remove a device from exclusions

Select the device and click 'Delete'





- Click 'Confirm' to remove the item from the list
- Click the 'Save' button save the 'External Devices Control' settings.
- Click 'Delete' to remove the 'External Devices Control' section from the profile. See Edit Configuration
 Profiles for more details about editing the parameters.

6.1.3.1.17. Monitors


- The monitors settings section lets you add performance and event monitors to a profile.
- A monitor is a script which tracks events on a managed endpoint and takes specific actions if its conditions are met.
 - For example, 'Alert me when a USB removable disk is connected to the system', or 'Create a log entry if CPU usage goes above 75% for a certain length of time'.
- You can also configure a monitor to run a procedure if its conditions are met.
- There are two types of monitor:
 - 'Predefined Monitors' A collection of monitors from Comodo which perform a range of useful monitoring tasks. These can be used in custom profiles, but cannot be edited.
 - 'My Monitors' Custom monitors that you create. You can configure custom monitors in the 'Monitors' inventory ('Configuration Templates' > 'Monitors'). See 'Manage Monitors' for more details.
- Monitors added to the inventory can be added to a profile. You can add multiple monitors to a single profile.

Add a monitor section to a profile


Click 'Configuration Templates' > 'Profiles'



- Open the Windows profile you want to configure
- Click 'Add Profile Section' > 'Monitors'




Click 'Add Monitor'



- Choose Monitor(s) Lets you add monitors to the profile
 - Start typing the first few letters of a monitor name then select from the suggestions
 - · Repeat the process to add more monitors to the profile
 - See Manage Monitors for help to configure a monitor
- Click 'OK' to save your settings


The list of monitors included in the profile will be displayed:





Monitors - Column Descriptions		
Column Heading	Description	
Monitor Name	The monitor label. • Click the name of a monitor view and edit it. See View and Edit Monitors for more details.	
Туре	Whether the monitor is custom or predefined.	
Created by	The administrator who created the custom monitor. • Click the admin name to view their details. See View User Details if you need help with this.	
Created On	Date and time the monitor was created.	
Last Modified By	The admin who most recently edited the monitor.	
Updated On	Date and time the monitor was last edited.	
Controls		
Add Monitor	Add a monitor to the profile. See the explanation above for help with this.	
Remove Monitor	Delete monitors from the profile Use the check-boxes to select the monitors you want to remove.	

- Click any column header to sort the items based on alphabetical or ascending/descending order of entries in the respective column.
- Click the funnel button at the right end to open the filter options.




6.1.3.1.18. Procedure Settings

- You can run task scripts and patch scripts on Windows devices by adding a 'Procedures' section to a profile.
- Note This section lets you *manage* the procedures on a specific profile. The procedures themselves are actually created at 'Configuration Templates' > 'Procedures'. Click here for help to configure a procedure.
- Note also Make sure **patch management** isn't disabled. You check this by looking in the 'Patch Management' section of the profile. If the profile doesn't have such a section, then patching is enabled.

Add procedures to a profile

- Click 'Configuration Templates' > 'Profiles'
- · Open a Windows profile in the list
- Click 'Add Profile Section' > 'Procedures'






Add a procedure

• Choose 'Procedures' from the 'Add Profile Section drop down' and click 'Add'.






Add Existing Procedure to a Profile - Form Parameters		
Parameter	Description	
Procedure Name	Choose an existing procedure by typing the first few characters of the procedure name. Make sure you have already approved the procedure.	
	See View and Manage Procedures if you want help to create procedures.	
Schedule Settings	Two options are available - 'Schedule on a maintenance window' and 'Custom schedule'.	
	Custom Schedule	
	Set a time-slot for the procedure to run on devices which use this profile (optional).	
	Start date - Choose the date of the procedure's first run time.	
	Schedule - Set the frequency at which the procedure should run. The available options are:	



	 Never - The procedure will run only once at the time in the 'Start Date'. Daily - The procedure will run every day at your 'Scheduled Time'. Weekly - Select the days of the week that the procedure should run. Monthly - Select the dates of a month that the procedure should run. Scheduled Time - Set the time at which the procedure should run. End-Time Settings (for daily, weekly or monthly frequencies) No end settings - All procedures will run to completion. Run until - Chose a cut-off time from the calendar. Run no more than - Specify how long the procedure should run. Run until the end of the closest maintenance window - The procedure will start at the time you set, and must finish by the end of the first maintenance window after schedule start. For the last three settings, any procedure that does not finish by the cut-off
	time is aborted and all changes undone.
	Schedule on a maintenance window
	 Maintenance Window Type - Choice of 'Daily', 'Weekly', 'Monthly' and 'Week of month'. This is the frequency you selected when you created the maintenance window. See 'Maintenance Window' if you have not yet created a maintenance window.
	Maintenance Window Name - Shows a list of maintenance windows which have the frequency you chose in the 'Window Type' box above. Select the window you want to add to the procedure.
	End Time Settings:
	No end settings - All procedures will run to completion.
	Run until - Chose a cut-off time from the calendar.
	Run no more than - Specify how long the procedure should run.
	 For the last two settings, any procedure that does not finish by the cut-off time is aborted and all changes undone.
User Account Options	Choose 'Run as system user' or 'Run as logged in user' based on the access rights required for the procedure to run at the endpoint.
Execution Options	Run this procedure immediately when the profile is assigned to a new device
	The procedure will run on target devices as soon as the profile is applied to the device, in addition to any schedule.
	Skip procedure if the device is offline
	The procedure will be aborted is the device is not connected to EM at the time of execution.
	By default, procedures are queued for later deployment if the device is not connected to EM. The task will be executed as soon as it comes online.
	Select this option If you do not want the task to be added to the queue.
Report Options	Script procedures only
	 Send to current user - Procedure results are sent to the admin who is currently logged into Endpoint Manager.
	Send to the following email addresses - Add email addresses to whom log results should be sent.
Configure parameters	Only for script procedures with variable parameters.
L	




Click 'Configure parameters'



- Use the default values or choose a new value.
- · Click 'Apply'
- Click 'Add'
- · Repeat the process to add multiple procedures to the profile
- · Click 'Save' to add the procedures to the profile

Edit a procedure:

- Click 'Configuration Templates' > 'Profiles'
- · Open the Windows profile containing the procedures component to be edited
- Click the 'Procedures' tab
- Click 'Edit' and select the procedure that needs to be modified.
- Modify the procedure as required and save it



• Then click either 'Add', 'Move Up', 'Move down', or 'Remove' based on the changes that need to take effect.

ITarian Endpoint Manager - Administrator Guide



- · Click 'Add' to add another procedure to the existing list
- Click 'Move Up' to increase the priority of the procedure.
- Click 'Move Down' to decrease the priority of the procedure.
- Click 'Remove' to delete the procedure.
- Click 'Save'.


6.1.3.1.19. Remote Control Settings

- 'Remote Control' settings let you choose the protocol and ports used for remote connections.
- · You can also configure takeover requests, endpoint notifications, and file transfer operations

Configure Remote Control Settings

- Click 'Configuration Templates' > 'Profiles'
- Open the profile that you want to configure (click the profile name to do this)
- Click 'Add Profile Section' > choose 'Remote Control' from the drop-down.
 - If 'Remote Control' is not available then it has already been added to the profile.
- Click the 'Remote Control' tab on the profile file-menu:





There are two tabs, 'Device Takeover' and 'File Transfer'. These two are independent of each other. You can disable device takeover and still enable file transfer operations.

- Configure device takeover
- Configure file transfer

Device Takeover Options:

- Click the 'Device Takeover' tab if not already open.
 - Apply to all Master switch to control the options below. The 'On/Off' switch currently only applies
 to the device takeover option.




- Device Takeover Enable or disable the ability to take remote control of endpoints
- Establish Remote Control sessions without asking user permission The remote connection is established without showing a request to the user.
- Ask user, wait and allow access (waiting time is shown below) A message is shown to the
 user which requests them to accept the connection. The connection is established if the user does
 not respond within the timeout period.
 - Enter the timeout period (in seconds) in the text box
- Ask user, wait and deny access (waiting time is shown below) A message is shown to the
 user which requests them to accept the connection. The connection attempt is abandoned if the
 user does not respond within the timeout period.
 - Enter the timeout period (in seconds) in the text box

Message to device user

- Enter the text of the request message. For example, 'Your administrator would like to take control of your desktop. Click 'Allow' to accept the connection request.'
- Please note that you can enter the message only on choosing the second or third notification options from the remote control settings.

Client Notification Options

This area lets you configure the notification box which is shown on the endpoint when a remote session is active:



- Show notification to device user about who... Enable or disable the notification box
 - Allow endpoint user to terminate the connection Choose whether or not the 'End Session' button is shown in the notification box. If enabled, the end-user will be able to close the connection.
 - **Keep notification windows open upon termination** The notification box will stay open on the endpoint even after the session is over. Users can close the box at their discretion.

Protocol Options

These options let you configure the protocol used for the remote session.

- These settings apply to RC version 6.17 and above.
- You can also specify custom ports to be used by the protocol for an additional layer of safety. This allows
 you to keep only the specified ports open and block other ports for security.

Note: Please make sure you do not assign well-known special ports. We recommend the following port range for custom use: 49152-65535.


- Use WebRTC RC uses WebRTC protocol to connect to the device. This option is mandatory and cannot be deselected.
- Ports Select the port type to be used by WebRTC protocol and specify the ports. The available options are:
 - Default WebRTC will use port range 1025 5000 for Windows XP and port range 49152 -65535 for Windows 7 and later versions
 - Custom Allows you to specify a single custom port to be used by WebRTC
 - Custom Range Allows you to specify a port range to be used by WebRTC
- Use Chromoting Chromoting provides a better quality of remote control and experience and is supported only by Windows 7 and later.



- If selected, RC uses Chromoting to connecting to devices Windows 7 and later and use WebRTC for Windows XP devices.
- If not selected, RC will use only WebRTC to connect to devices with any Windows version.
- Ports Select the port type to be used by Chromoting protocol and specify the ports. The available options are:
 - Default Chromoting will use the port range 49152 65535
 - Custom Range Allows you to specify a port range to be used by Chromoting. Enter a range covering at least 4 ports.
- Click 'Save' to apply your changes to the profile.

File Transfer Options

Click the 'File Transfer' tab



ITarian Endpoint Manager - Administrator Guide



- Apply to all Master switch to the control options below.
- **File Transfer** Allows admins to view files/folders on remote devices. You can enable this setting in isolation if you only want admins to have read-access to the remote device.
- You must enable this setting in order to enable the two more powerful settings below:
- Send & Receive Folders & Files Enable admins to transfer files/folders between the admin computer and the remote computer.
- Create, Delete, Rename actions Enable admins to perform file operations on the remote computer.

The user permission settings are the same, or very similar, to those described in the 'Device Takeover' section above.

Click 'Save' to apply your changes to the profile.


6.1.3.1.20. Remote Tools Settings

- Remote tool settings let you configure how you connect to managed endpoints
- There are two ways you can remotely connect:
 - Remote Tools View and manage remote computers via the EM console. Click 'Devices' > 'Device List' > select a running Windows device > click 'Remote Tools' > 'File Explorer' / 'Process Explorer' / 'Service Explorer'.
- The endpoint must have communication client v. 6.25 or higher installed to configure remote tool settings.

Configure Remote Tools Settings

- Click 'Configuration Templates' > 'Profiles'
- Open the profile that you want to configure (click the profile name to do this)
- Click 'Add Profile Section' and choose 'Remote Tools' from the drop-down.
 - If 'Remote Tools' is not in the 'Add...' menu then it has already been added to the profile.
 - Click the 'Remote Tools' tab on the profile file-menu:






Remote Tools Options:

- File Explorer Enable the ability to view files on the remote system.
- Perform actions Enable the ability to create / rename / move / delete files on the remote system.
- File / Folder Transfer Enable the ability to copy files to and from the remote system.



- **Process Explorer** Enable the ability to view and manage running processes and services on the remote system.
- **Commands Interface** If enabled, you can run command lines and power shell commands on remote devices' command prompt.
 - Alternatively, use the 'Apply to all' switch at the top to enable or disable all at-once.
- Establish Remote Tools sessions without asking user permission The remote connection will be established without showing a request to the user.
- Ask user, wait and allow access A message is shown to the user which requests them to accept the
 connection. The connection is established if the user does not respond within the timeout period.
 - Enter the timeout period (in seconds) in the text box
 - An example request message is shown below:




- Ask user, wait and deny access A message is shown to the user which requests them to accept the
 connection. The connection attempt is abandoned if the user does not respond within the timeout period.
 - Enter the timeout period (in seconds) in the text box

Message to Device User

- Enter the text of the request message. For example, 'Your administrator needs to remotely access vour device to perform routine maintenance. Please click "Allow" to start the remote connection.'
- Note You can only enter a message if you choose one of the 'Ask...' settings.

Client Notification Options


This area lets you configure the notification box which is shown on the endpoint when a remote session is active. An example is shown below:



The end-user can view the actions taken on the endpoint by clicking the down arrow at the right of the notification box.

- Show notification to device user about who connected to his/her workstation Enable or disable the notification box
 - Allow endpoint user to terminate the connection Choose whether or not the 'End Session' button is shown in the notification box. If enabled, the end-user will be able to close the connection.
 - **Keep notification windows open upon remote session termination** Choose whether or the notification box should be shown on the endpoint after the session is completed.






6.1.3.1.21. Miscellaneous Settings

- Click 'Configuration Templates' > 'Profiles'
- Click the name of a Windows profile
- Click 'Add Profile Section' > 'Miscellaneous'

The 'Miscellaneous' settings screen opens:





Apply the selected action to...' - CCS will monitor registry entries related to Windows services, auto-run
items and scheduled tasks. If any entries are created or modified by unrecognized files/scripts, they will
handled per the action chosen. (*Default = Enabled*)



Detect shellcode injections:


- A shellcode injection is an attack which exploits software vulnerabilities to give attackers control of a compromised machine.
- For example, shellcode attacks are often used to create buffer-overflows on victim machines. Enable this setting to turn-on buffer overflow protection.
- By default, Comodo Client Security (CCS) monitors all applications to make sure they do not suffer shellcode attacks.
- However, you may want to omit certain applications from protection for compatibility reasons. Click the 'Exclusions' link to do this.
- The process to add exclusions is similar to that explained in Containment Settings.

Background: A buffer overflow is an anomalous condition where a process/executable attempts to store data beyond the boundaries of a fixed-length buffer. The result is that the extra data overwrites adjacent memory locations. The overwritten data may include other buffers, variables and program flow data, and may cause a process to crash or produce incorrect results. As such, buffer overflows cause many software vulnerabilities and are the basis of many exploits.

Comodo recommends this setting is left enabled (*Default = Enabled*).

- Monitor DLL files being loaded by running processes CCS monitors the DLL files loaded to system
 memory, by processes that are currently running on the endpoint (*Default = Disabled*).
 - If enabled, CCS runs a file rating scan on each DLL loaded to identify its trust rating.
 - The trust rating is reported to Endpoint Manager. Files with an Unrecognized' rating are submitted to Valkyrie for analysis.
 - You can view these details at 'Security Sub-Systems' > 'Application Control'. See **Manage File Trust Ratings on Windows Devices** for more details.
- Apply the selected signature level while.... CCS identifies untrusted DLLs, apps, portable executables
 (PE) and autoruns launched before CCS starts on the endpoint. These may expose the endpoint to a
 danger if those items turn to be malicious. (Default = Disabled)
 - CCS checks whether startup items are signed by a trusted authority and marks them as trusted or untrusted. The flag is used at next restart to allow or block the item.
 - You can choose how strict the certificate check should be:





- Windows Only items signed by Microsoft certificates are marked as trusted
- Antimalware Trusts files signed by either Microsoft or Antimalware certificates
- Authenticode Flags all signed files as trusted
- Click 'Save' to apply your changes to the profile.

6.1.3.1.22. Script Analysis Settings

- CCS can analyze code in executable files in two ways:
 - Heuristic command line analysis
 - · Embedded Code Detection
- You can enable these features and select the programs you want to monitor by adding a 'Script Analysis' section to a profile.
- You can also monitor programs which try to make changes to auto-run entries, Windows services and scheduled tasks

Background:

Heuristic command line analysis:

- Heuristic techniques identify previously unknown viruses and Trojans.
- Files are analyzed to ascertain whether they contain code typical of a virus.
- In other words, heuristics identifies files which have virus-like attributes, instead of looking for a signature that matches a signature on the blacklist.
- This allows the engine to predict the existence of new viruses even if they are not in the current virus database.

Embedded code detection:


- Embedded code detection protects you against file-less malware attacks.
- File-less malware attacks allow malicious actors to directly execute powershell commands on your system.
- These commands can be used to take control of endpoints, install ransomware, steal confidential data and more.
- File-less scripts reside in memory so no trace of them remains after the computer is restarted.
- Example programs affected by this option are wscript.exe, cmd.exe, java.exe and javaw.exe.
 - For example, the program wscript.exe can be made to execute visual basic scripts (.vbs file extension) via a command similar to 'wscript.exe c:/tests/test.vbs'. If this option is selected, CCS detects c:/tests/test.vbs from the command-line and applies all security checks to this file.
 - Enabled If test.vbs attempts to connect to the internet, the alert will state 'test.vbs' is attempting
 to connect to the internet



• Disabled - The alert will only state 'wscript.exe' is trying to connect to the internet'.

Configure 'Script Analysis' Settings


- Click 'Configuration Templates' > 'Profiles'
- · Click the name of a Windows profile
- Click 'Add Profile Section' > 'Script Analysis'



The 'Script Analysis' settings screen contains three tabs:

- **General Settings** Enable script analysis and set the maximum file size which should be checked.
- Runtime Detection Select which programs are monitored throughout their operation.
- Autoruns Scan Choose programs that you want to monitor to see if they make changes to auto-run entries, Windows services and scheduled tasks.

General Settings



ITarian Endpoint Manager - Administrator Guide




- Perform Script Analysis Enable/Disable script analysis. CCS will only analyze the applications selected
 in the 'Runtime Detection' tab if this option is enabled. An alert is generated if malicious code is found in any
 item. (*Default = Enabled*)
- Limit the total size of saved detected scripts to CCS stores scripts run by managed applications for analysis. This option lets you specify the total size of stored scripts. When the set limit is reached, the older scripts are deleted automatically. (*Default* = 100 KB)

Runtime Detection


- Lets you select executables which should be analyzed during their execution.
- You can also add custom applications which you want to protect.
- · Click the 'Runtime Detection' tab in the 'Script Analysis' settings interface





- Use the switch in the 'Heuristic Command-Line Analysis' column to enable/disable heuristic command line analysis for each application.
- Use the switch in the 'Embedded Code Detection' column to enable/disable embedded code detection for each application.
- Select an application and click the edit button to update its details.
- Select an application and click the trash can icon to remove it from the list.
- Click 'Add' at the top to include a new application to the list.






- Enter the name of the application in the 'Add Application' dialog and click 'Add'.
- The new application will be added to the list and will be selected by default. You can use the toggle switch beside it to enable/disable it at any time.
- Repeat the process to add more applications
- To reset the list to the default list of applications, click 'Reset to Default' on the top
- Click 'OK' to apply your changes.

Autoruns Scan


- Select applications which should be monitored in case they make changes to autoruns, Windows services
 or scheduled tasks.
- You can also add custom applications which you want to monitor.
- Click the 'Autoruns Scan' tab in the 'Script Analysis' settings interface





- Use the switch in the 'Heuristic Command-Line Analysis' column to enable/disable heuristic command line analysis for each application.
- Use the switch in the 'Embedded Code Detection' column to enable/disable embedded code detection for each application.
- Select an application and click the edit button to update its details.
- Select an application and click the trash can icon to remove it from the list.
- Click 'Add' at the top to include a new application to the list.





- Enter the name of the application in the 'Add Application' dialog and click 'Add'.
- The new application will be added to the list and will be selected by default. You can use the toggle switch beside it to enable/disable it at any time.
- Repeat the process to add more applications
- To reset the list to the default list of applications, click 'Reset to Default' on the top
- Click 'OK' to apply your changes.

6.1.3.1.23. Data Loss Prevention Settings

The data loss prevention section of a profile lets you search endpoints for confidential data. For example, credit card numbers, social security numbers, bank accounts, etc.

There are two tabs:

Discovery - Discovery rules let you specify the areas you want to scan and the type of data you want to search for.


- You create the discovery rules at 'Configuration Templates' > 'Data Loss Prevention'.
- · You then come to this section to add the rules to a profile.
- See Data Loss Prevention Rules if you want help to configure the rules themselves.

Monitoring - Monitoring rules let you block endpoint users from copying data to external devices like USB sticks and storage drives.


Add a discovery scan to a profile



- Click 'Configuration Templates' > 'Profiles'
- · Open the Windows profile you want to configure
- Click 'Add Profile Section' > 'Data Loss Prevention'




- Click the 'Discovery' tab if not already open
- Click 'Add'



Choose Data Loss Prevention rule - Add an existing discovery rule to the profile.


- Start typing the first few letters of a rule name then select from the suggestions
- Repeat the process to add more rules to the profile.





- Note. Go to 'Configuration Templates' > 'Data Loss Prevention' to create new rules and view existing rules.
- Click 'Add'

The interface shows all discovery rules you have added:



Column Heading	Description	
Name	The rule label.	
	 Click the name of a rule to view and edit it. See View and Edit DLP Discovery Rules for more details. 	
Created by	The admin who added the rule. Click the name to view their details.	
Created On	Date and time the rule was created.	
Last Modified By	The admin who most recently edited the rule.	
Updated On	Date and time the rule was last edited.	
Enabled	Use the switch beside a rule to activate / deactivate it.	
Controls		
Add	Add rule to the profile. See the explanation above for help with this.	
Remove	Remove rules from the profile. Use the check-boxes to select the rules you want to delete.	

The scan will run immediately on all devices to which the profile is applied.


Add a monitoring rule

Monitoring rules let you prevent users from copying files to external devices, take screenshots of sensitive information and so on.


Click 'Configuration Templates' > 'Profiles'



- · Open the Windows profile you want to configure
- Click 'Add Profile Section' > 'Data Loss Prevention'
- Click the 'Monitoring' tab:



Click 'Add'



Choose monitoring rule - Add an existing monitoring rule to the profile.

- · Start typing the first few letters of a rule name then select from the suggestions
- Repeat the process to add more rules to the profile.






- Note. Go to 'Configuration Templates' > 'Data Loss Prevention' to create new rules and view existing rules.
- Click 'Add'

The interface shows all monitoring rules you have added:





Column Heading	Description	
Name	The rule label.	
	 Click the name of a rule to view and edit it. See View and Edit DLP Monitoring Rules for more details. 	
Туре	Indicates what kind of monitoring rule	
Action	What EM should do if the rule is triggered	
Created by	The admin that added the rule	
Created on	Date and time the rule was configured	
Last Modified by	The admin who most recently edited the rule.	
Updated on	Date and time the rule was last edited.	
Enabled	Use the switch beside a rule to activate / deactivate it. Use the master switch above to enable / disable all the rules.	
Controls		
Add	Add rule to the profile. See the explanation above for help with this.	
Remove	Remove rules from the profile. Use the check-boxes to select the rules you want to delete.	
Move up / Move down	Re-order the rule priority. Select a rule and use the buttons to re-order.	

The monitoring rules are applied immediately on all devices to which the profile is applied.



6.1.3.1.24. Patch Management Settings


The patch management section lets you disable or enable patch operations on endpoints. This setting affects:

- On-demand patch operations
- Scheduled patch operations
- Patch installations via procedures

Patch operations are allowed if you don't add this section in the first place, or if you disable the 'Turn off...' setting.


Add patch management section to a profile

- Click 'Configuration Templates' > 'Profiles'
- · Open the Windows profile that you want to work on
- Click 'Add Profile Section' > 'Patch Management'



The setting is disabled by default for both operating system and third party applications patches.

Click 'Edit'



- Operating System Enable / disable Windows OS patching
- Third Party Applications Enable / disable patching 3rd party application patches

Click 'Save' to your apply your settings.

6.1.3.2. Import Windows Profiles

In addition to creating a new Windows profile from the Endpoint Manager interface, you can create new profiles for rolling out to endpoints or endpoint group(s) in the following ways:

- Import the security configuration of CCS from a managed endpoint and save it as a new profile
- Export a profile from EM in .cfg format then import it as a new profile
- Clone an existing profile and edit it to create a new profile

This section explains more about importing CCS configuration from a selected endpoint.

 For more details on importing configuration from an exported profile, see Export and Import Configuration Profiles.



For more details on creating a new profile by using an existing profile as base, see Clone a Profile.

Import CCS Configuration from a Managed Device

By importing the configuration of Comodo Client Security from an existing endpoint, you can create a Windows profile which can be deployed to similar machines on your network.

- Step 1 Export the current configuration from the selected device as an .xml file
- Step 2 Import the .xml file as a profile to required endpoints or endpoint group(s).

Step 1 - Export the current configuration from the selected device as an .xml file

The current security configuration of the CCS installation on the endpoints depends on:

- The configuration profiles applied o the endpoint
- Manual configuration of the parameters at the endpoint.


Note: If you are manually configuring the security parameters, ensure that the option 'Enable local user to override profile configuration' is selected in the 'Client Access Control' section in the profile(s) in action on the endpoint. Otherwise your manual settings will be reverted and the security parameters will be automatically set as per the configuration profile(s) effective on the endpoint during the next polling cycle of the communication client. See **Client Access Control** for more details.

You can export the CCS configuration from a managed Windows device in two ways:

- Export configuration of a selected device from EM interface
- Manually export the CCS configuration from the selected device


Export Configuration from EM interface

- Open the 'Device List' interface from the EM console by clicking 'Devices' > 'Device List' on the left
- Click the name of the device whose configuration you wish to export to open its 'Device Details'
- Click the 'Export Security Configuration' button:



- The CCS configuration will be exported as a .xml file and saved in EM.
- You can view all configuration files exported from this device under the 'Exported Configurations' tab in 'Device Details':





- Click the name of the file that you want to import as a profile and save it in a safe location.
- Then move on to Step 2 Import the .xml file as a profile to required endpoints or endpoint group(s).

Manually export CCS configuration from a selected device

- If you haven't done so already, configure the security settings of CCS at an endpoint to your requirements.
 See 'Advanced Settings' in the CCS guide if you need help with this https://community.itarian.com/help/topic-459-1-1002-15112-CCS-Advanced-Settings.html
- To export the current configuration as an xml file, the following command locally on the endpoint: C:\[installation folder of CCS]\cfpconfg.exe --xcfgExport="C:\<filename>.xml" --filter=""


For example, C:\Program Files\COMODO\COMODO Internet Security\cfpconfg.exe --xcfgExport="C:\winconfigprofile.xml" --filter=""

- Copy the .xml file from the endpoint to the computer from which the EM console is accessed.
- Then move on to Step 2 Import the .xml file as a profile for application to required endpoints or endpoint group(s).

Step 2 - Import the .xml file as a profile for application to required endpoints or endpoint group(s)

- Click 'Configuration Templates' > 'Profiles'
- Click 'Import' > 'Import from 'Comodo Client Security Config file'






The 'Import Windows Profile' opens.


- Enter a name and description for the profile.
- Click 'Browse', navigate to the location in your computer where the .xml file is saved, select the file and click 'Open'.





Click the 'Import' button.

The Windows Profile interface will open with the security components pre-configured as per the settings in the configuration file.



- The imported profile will not be set as 'Default Profile' by default.
- To change the name of the profile and/or to enable it as a default profile, click on the 'Edit' button

 Edit at the top right of the 'General' settings screen, edit the settings and click the 'Save' button.
- You can now deploy this profile to endpoints and endpoint groups. You can add new profile components by clicking 'Add Profile Section' and can edit the settings for any security component by clicking the relevant



tab. For more details on the options available under each component, see the **explanation of the component settings Create Windows Profiles**.

6.1.4. Profiles for Mac OS Devices

Mac OS profiles let you specify the general settings and configuration of Comodo Client - Security (CCS) on Mac OS devices.

There are two ways you can add a MAC OS profile:

- Create a brand new profile. See Create Mac OS Profiles for more details.
- Clone an existing profile and modify its settings. See Clone a Profile, for more details.

6.1.4.1. Create a Mac OS Profile


Process in brief:

- Click 'Configuration Templates' > 'Profiles' > 'Create' > 'Create Mac OS Profile'
- Click 'Create' > 'Create Mac OS Profile'
- Type a name and description for your profile then click the 'Create' button. The new profile will appear in 'Configuration Templates' > 'Profiles'.
- New profiles have only one section 'General'. Click 'Add Profile Section' to add settings for various security
 and management features. Each section you add will appear as a new tab.
- Once fully configured, you can apply the profile to users, devices, and groups of users or devices.
- Click the 'General' tab then 'Edit' to make it a 'Default' profile.
 - A 'default' profile is one that is automatically applied to every device which matches its operating system. You can have multiple 'default' profiles per operating system.
- This part of the guide explains the processes above in more detail, and includes descriptions of each section.

Create a new profile

Click 'Configuration Templates' > 'Profiles' > 'Create' > 'Create Mac OS Profile'






- Name Enter a label for the profile
- Description Enter appropriate short notes for the profile
- · Click the 'Create' button

The new profile will open at the general settings page:






- Make Default A 'default' profile is one that is automatically applied to every device that matches its
 operating system. Click this button if you want all MAC OS devices to receive this profile. Do not select if
 you only want to apply the profile to selected MACs.
- · Click 'Save'.


The next step is to add sections to the profile. Each section lets you define settings for a particular security or management feature.

• Click 'Add Profile Section' then select the section you want to add from the list:





The new section will appear as a tab under the profile name. You can add as many sections as required to a profile.





Following sections explain more about each of the settings:

- Antivirus
- Certificate
- Restrictions
- VPN
- Wi-Fi
- Remote control
- Valkyrie Settings
- Procedures
- Monitors

6.1.4.1.1. Antivirus Settings for Mac OS Profile

The antivirus section lets you configure real-time monitoring, custom scans, scan schedules, exclusions and more.


Configure antivirus settings in a Mac OS profile

- Click 'Configuration Templates' > 'Profiles'
- Click the name of a Mac OS profile
- Click 'Add Profile Section' then 'Antivirus' (if you haven't yet added the AV section)

OR

· Open the 'Antivirus' tab if it was already added

The antivirus settings screen has two tabs:



- Preferences Configure general behavior, updates, parental control and log settings
- Antivirus Configure settings for all scan types, create custom scan profiles and schedule AV scans.

Preferences



The preferences tab lets you configure the following settings:

- General
- Update
- Parental Control
- Logging


General

- Automatically check for program updates Choose whether CCS should periodically contact Comodo servers for new product versions and patches. If enabled, CCS checks for updates every 24 hours AND every time users start their computers. If updates are found, they are automatically downloaded and installed. (*Default = Enabled*).
- **Show balloon messages** If enabled, notifications from CCS will appear in the bottom-right hand corner of the computer screen just above the tray icons. Balloon messages are usually generated when CCS is learning the activity of previously unknown components of trusted applications. (*Default = Disabled*).

Update Settings

The update tab lets you specify an alternate host from which endpoints should collect updates. The default download server is https://download.comodo.com


Click 'Preferences' > 'Update'



You can add the URL of an alternative download host if required. For example, you may want to distribute the updates from a local server to conserve bandwidth.

Click 'Add'






- Enter the URL or IP of the host from which endpoints should collect updates
- Select 'Enable' to activate the host
- · Click 'Ok' to apply your changes
- Repeat the process to add multiple hosts.
- Click the pencil icon
 to edit the host

Parental Control Settings

Parental controls let you password protect access to CCS settings. This helps prevent unauthorized personnel from making changes which could compromise the endpoint.

· Click the 'Parental Control' tab under 'Preferences'






 Enable password protection for the settings - Activates password protection for all important CCS settings. End-users will need to provide a password to access the settings area in the local CCS UI.

Please type the password in the field provided.

• Suppress Antivirus alerts if password protection is enabled - If selected, threats on the device are automatically blocked but no alert is shown to the end-user. This avoids the situation where a user dangerously clicks 'Allow' just to make an alert go away.

Log Settings

Click the 'Logging' tab under 'Preferences'



By default, CCS logs all antivirus (AV) events locally on the device. Users can view the logs by clicking 'View Antivirus Events' in the tasks interface.

 Write to local log database (COMODO format) - Deselect if you don't want CCS to store logs on the local device.



Configure Antivirus Settings


The antivirus tab lets you configure settings for all types of scan, view/create scan profiles, and to schedule scans. It has three sub-tabs:

- Scanner Settings
- Scan Profiles
- Scheduled Scans

Scanner Settings


You can configure the following from the scanner settings area:

- Realtime Scanning
- Manual Scanning
- Scheduled Scanning
- Exclusions



Realtime Scanning






Form Element	Description
Real time scanning	Enable or disable realtime scans.
	 On Access - Any file opened is scanned before it is allowed to run. Threats are detected before they get a chance to execute (<i>Default</i>)
	 Disabled - Real-time protection is switched off. Files are allowed to run without first being checked for threats.
Do not scan files larger than (MB)	Files larger than the size specified here will not be scanned (<i>Default</i> = 20MB).
Keep an alert on the screen for (seconds)	How long threat notifications should stay on-screen if not dismissed by the enduser. (<i>Default</i> = 120 seconds)
Automatically quarantine threats found during scanning	Threats will be encrypted and moved to a secure holding area where they can cause no harm. You can review quarantined items and delete, ignore, or restore them.
	 Disable this option if you do not want threats to be moved to quarantine.
	(Default = Enabled)
Automatically update virus database	CCS checks for and downloads database updates at system start-up, and subsequently at regular intervals.
	 Disable this option if you do not want CCS to automatically check for updates.
	(Default = Enabled).
Realtime scanning of files on	Activate or deactivate automatic scans of files on network drives.
network	 Enabled - CCS checks every file that the user interacts with on a network drive, even if it is not copied to the local machine.(Default)



Form Element	Description		
	Disabled - Network files are not checked unless they are copied to the local machine.		

Manual Scanning

- A manual scan is one you run 'on-demand' on selected files, folder or drives. Manual scans can be launched from 'Security Sub-Systems' > 'Antivirus'.
- For more details on running on-demand scans on selected devices, see Run Antivirus and/or File Rating Scans on Devices.




Manual Scanning Settings - Table of Parameters		
Form Element	Туре	Description
Do not scan files large than (MB)	Text box	Files larger than the size specified here, will not be scanned (<i>Default = 20MB</i>).
Scan archive files	Checkbox	 CCS scans archive files such as .ZIP and .RAR files. Disable this option if you don't want archive files to be scanned. (Default = Enabled).
Automatically quarantine threats found during scanning	Checkbox	Threats will be encrypted and moved to a secure holding area where they can cause no harm. You can review quarantined items and delete, ignore or restore them.



Manual Scanning Settings - Table of Parameters		
		Disable this option if you do not want threats to be moved to quarantine.
		(Default = Enabled)
Automatically update virus database before scanning	Checkbox	CCS will check for and download the latest virus database updates on system start-up, and subsequently at regular intervals. • Disable this option if you do not want CCS to automatically check for updates. (Default = Enabled).

Scheduled Scanning

- Specify general settings which will apply to all scheduled scans you create
 - Note. You actually create schedules in the 'Scheduled Scans' area. See create a scheduled scan
 if you need help with this.



Scheduled Scanning Settings - Table of Parameters		
Form Element	Туре	Description
Do not scan files large than (MB)	Text box	Files larger than the size specified here will not be scanned. (<i>Default = 20MB</i>).
Scan archives files	Checkbox	CCS scans archive files such as .ZIP and .RAR files.




Scheduled Scanning Settings - Table of Parameters		
		Disable this option if you don't want to scan archive files. (Default = Enabled).
Automatically quarantine threats found during scanning	Checkbox	Threats will be encrypted and moved to a secure holding area where they can cause no harm. You can review quarantined items and delete, ignore or restore them.
		 Disable this option if you do not want threats to be moved to quarantine.
		(Default = Enabled)
Automatically update virus database before scanning	Checkbox	CCS will check for and download the latest virus database updates on system start-up, and subsequently at regular intervals.
		 Disable this option if you do not want CCS to automatically check for updates.
		(Default = Enabled).
Show scanning progress	Checkbox	Enabled - End-users will see a scan progress bar when the scan is running.
		Disable this option if you don't want CCS to show the progress bar.
		(Default = Enabled)

Exclusions

Note. Any item you exclude will be skipped by ALL types of scan - real-time, on-demand and scheduled.






A list of excluded items will be displayed.

Add an item to the 'Exclusions' list

Click 'Add'





- Enter the location of the item to be excluded in the 'Path' field and click 'Ok'
- Repeat the process to add more items
- To edit the path of an item, click the pencil icon beside it


Scan Profiles

- Scan profiles instruct CCS to scan selected areas, folders or drives on a the device.
- You can add a scan profile to:
 - A scheduled scan
 - An on-demand scan

To create a scan profile

Click the 'Scan Profiles' tab under 'Antivirus'






The list of pre-defined scan profiles will be displayed.

Click 'Add'






- Enter a name for the scan profile
- · Click 'Add' to add the locations to be scanned as per the custom profile




Enter the path of the location to be scanned as per the custom profile and click 'Ok'

The path will be added to the profile.





- To add more paths, click 'Add' and repeat the process
- To edit the path, click the pencil icon beside it
- Click 'Ok' in the 'Add Scan Profile' dialog.
- The profile will be added to the list of 'Scan Profiles'.



Click 'Add' and repeat the process to add more custom scan profiles




Click the pencil icon beside a custom profile to edit its details.

Scheduled Scans

- The highly customizable scan scheduler lets you timetable scans to be run on managed devices according
 to your preferences. CCS automatically starts scanning the entire system or the disks or folders contained
 in the profile selected for that scan.
- You can add any number of scheduled scans for a profile to run at a time that suits your preference. A scheduled scan may contain any scan profile of your choice.

Create a scan schedule

Click the 'Scheduled Scans' tab under 'Antivirus'




A list of pre-configured scheduled scans will be displayed.

Add a new scheduled scan

Click 'Add'








Add Scheduled Scan - Table of Parameters			
Form Element	Туре	Description	
Name	Text box	Label for the scheduled scan	
Profile	Drop-down	Choose the pre-defined or custom scan profile to be applied for the scheduled scan. The scan profiles included under the 'Scan Profiles' tab will be available in the drop-down.	
Day of the Week	Buttons	Select the day(s) of the week on which the scan has to run	
Time	HH:MM drop- down combo boxes	Set the time at which the scans are to run on the selected days.	

Click 'Ok'

The scheduled scan will be added to the list.



- Click 'Add' and repeat the process to add more scheduled scans to the configuration profile.
- Click the pencil icon beside a scheduled scan to it edit its settings.
- Click 'Save' for your settings to take effect for the profile.

The settings will be saved and displayed under the 'Antivirus' tab. You can edit the settings or remove the section at anytime. See **Edit Configuration Profiles** for more details.

6.1.4.1.2. Certificate Settings for Mac OS Profile


• The 'Certificate Settings' section lets you upload certificates for use in 'Wi-Fi', 'Exchange Active Sync', 'VPN' and other areas of EM.



Configure certificate settings for Mac OS profile

- Click 'Configuration Templates' > 'Profiles'
- Open the Mac OS profile you want to configure
- Click 'Add Profile Section' > 'Certificate'

The certificate settings screen will open:



Certificate Settings		
Form Element	Туре	Description
Name	Text Field	Enter the label of the certificate.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.
Description	Text Field	Enter an appropriate description for the certificate.
Data	Browse button	Browse and upload the required certificate. Only certificate files with extensions 'pub', 'crt', 'key' or 'p12' can be uploaded.
Password	Text Field	Enter the password used for exporting a .p12 certificate.
		Click the variables button to insert dynamic values. See Create and Manage Custom Variables for more details on variables.



Click the 'Save' button.

The certificate will be added to the certificate store.



- To add more certificates, click 'Add Certificate' and repeat the process.
- To view the certificate key and edit the name, click on the name of the certificate
- To remove an unwanted certificate, select it and click 'Delete Certificate'


You can add any number of certificates to the profile and remove certificates at anytime. See **Edit Configuration Profiles** for more details.

6.1.4.1.3. Restrictions Settings for Mac OS Profile

The 'Restrictions' section allows you to modify the profile to enable or disable selected device features:


Configure Restrictions settings

· Click 'Restrictions' from the 'Add Profile Section' drop-down



The 'Restrictions' settings screen will be displayed.





Restrictions Settings - Table of Parameters			
Form Element	Туре	Description	
Device Functionality			
Allow Camera	Checkbox	Allows the user to take photos or videos (if enabled). If left unchecked, the camera icon is removed from the device and camera is disabled. Note: This feature is applicable only for OS X 10.11 and later versions.	
Spotlight will return Internet search results	Checkbox	If enabled, the spotlight features will provide suggestions from the Internet, iTunes, and the App Store for the user to quickly find any file, documents, emails, apps contacts and more on the device.	
		Note: This feature is applicable only for Supervised devices with OS X 10.11 and later versions.	
iCloud			
Allow cloud document sync	Checkbox	If enabled, users can synchronize documents on their device with iCloud. Note: This feature is applicable only for OS X 10.11 and later versions.	

· Click the 'Save' button.

The saved 'Restrictions Settings' screen will be displayed with options to edit the settings or delete the section. See **Edit Configuration Profiles** for more details.


6.1.4.1.4. VPN Settings for Mac OS Profile

The 'VPN' section allows you to configure the VPN connection settings for the profile.

Configure VPN settings


· Click 'VPN' from the 'Add Profile Section' drop-down





The settings screen for VPN will be displayed.






The connection setting parameters are similar to the VPN settings for an iOS profile. See **VPN settings** section for an iOS profile for details.

• Click the 'Save' button after configuring the settings.

The VPN connection will be added to the profile.





- Click 'Add VPN' and repeat the process to add more VPN connections
- Click the name of a VPN connection to edit its details


The settings will be saved and displayed under the VPN tab. You can edit the settings or remove the section from the profile at anytime. See **Edit Configuration Profiles** for more details.

6.1.4.1.5. Wi-Fi Settings for Mac OS Profile

The 'Wi-Fi' section allows you to configure Wi-Fi connection settings for the profile.


Configure Wi-Fi settings

· Click 'Wi-Fi' from the 'Add Profile Section' drop-down



The 'Wi-Fi' settings screen will be displayed.






The connection setting parameters are similar to the Wi-Fi settings for an iOS profile. See the **Wi-Fi settings** section for an iOS profile for details.

· Click the 'Save' button after configuring the settings.

The Wi-Fi network will be added to the list.



- Click 'Add Wi-Fi' and repeat the process to add more Wi-Fi networks
- · Click on SSID of a network to edit its details.

The settings is saved and shown under the Wi-Fi tab. You can edit the settings, add or remove Wi-Fi networks or remove the Wi-Fi networks at anytime. See **Edit Configuration Profiles** for more details.

ITarian Endpoint Manager - Administrator Guide




6.1.4.1.6. Remote Control Settings for Mac OS Profile

- 'Remote Control' settings let you configure protocol used during remote control sessions.
- You can also customize the message which is shown to Mac OS end-users when you make a remote connection to their computer.
- See Remote Management of Windows and Mac OS Devices if you need help to setup the remote control service.

Configure Remote Control Settings for MAC OS

- Click 'Configuration Templates' > 'Profiles'
- Select a Mac OS profile that you want to configure
- Click 'Add Profile Section' at the top and choose 'Remote Control' from the drop-down.
 - Note: If 'Remote Control' is not in the 'Add...' menu then it has already been added to the profile.
- The 'Remote Control' tab will open:








Remote Control Options:

- Silent remote control -The remote connection will start without requesting permission from the user.
- Ask permission then allow after NN seconds:
 - A message will be shown to the user which requests them to accept the connection. The connection
 will be automatically established if the user does not respond within the specified time.
 - Specify the timeout period (in seconds) in the text box
- Ask permission then deny after NN seconds:
 - A message will be shown to the user which requests them to accept the connection. The connection attempt will be terminated automatically if the user does not respond within the specified time.
 - Specify the timeout period (in seconds) in the text box.
- Do not allow remote control: Disable the ability to take remote control of the endpoint.

Remote Control Message

- Enter the text of the request message. For example, 'Your administrator would like to take control of your desktop. Click 'Allow' to accept the connection request.'
 - Please note that you can enter the message only if you choose the second or third notification options.



Client Notification Options

This area lets you configure the notification box which is shown on the endpoint when a remote session is active:



- Show notification to device user about who connected to his/her workstation and allow terminating the connection Let the end user know which EM admin/technician is connected to their machine.
 - Allow endpoint user to terminate the connection Choose whether the 'End Session' button should be shown in the notification box or not. If enabled, the end-user will be able to close the connection.

Protocol Options

These settings let you choose the protocol used to connect to Mac OS devices.

- These settings apply to RC version 6.17 and above.
- You can also specify custom ports to be used by the protocol for an additional layer of safety. This allows
 you to keep only the specified ports open and block other ports for security.

Note:Please make sure you do not assign well-known special ports. We recommend the following port range for custom use: 49152-65535.

- Use Chromoting RC uses Chromoting protocol to connect to the device. This option is mandatory and cannot be deselected.
- Ports Select the port type to be used by Chromoting protocol and specify the ports. The available options are:
 - Default Chromoting will use the port range 49152 65535
 - Custom Range Allows you to specify a port range to be used by Chromoting. Enter a range covering at least 4 ports.

Note: Chromoting is supported by Windows 7 and later versions. If RC is installed on a Windows XP admin machine, it will not be able to connect to a Mac OS device.

Click 'Save' to apply your changes to the profile.

6.1.4.1.7. Valkyrie Settings for MacOS Profile

- Valkyrie is a cloud-based file verdict service that subjects unknown files to a range of tests in order to identify those that are malicious.
- Comodo Client Security for Mac can automatically submit unknown files to Valkyrie for analysis. When the
 tests are complete, Valkyrie will award a trust verdict to the file.
 - Note 'Cloud Scanning' should be enabled in Antivirus section of CCS for Mac on the endpoints.
- The verdicts can be viewed in 'Security Sub-Systems' > 'Valkyrie' interface.
 - See View list of Valkyrie Analyzed Files for more details.
- Click 'Dashboard' > 'Valkyrie' to view summary of all Valkyrie results.

Note: The version of Valkyrie that comes with the free version of Endpoint Manager is limited to the online testing service. The Premium version of Endpoint Manager also includes manual testing of files by Comodo research labs, helping enterprises quickly create definitive whitelists of trusted files. Valkyrie is also available as a standalone service. Contact your l'Tarian Account manager for further details.

You can configure general Valkyrie settings and create an analysis schedule in the Valkyrie component of a Mac OS profile.


Configure Valkyrie Settings

Click 'Valkyrie' from the 'Add Profile Section' drop-down in the Mac OS Profile interface



The 'Valkyrie' settings screen will be displayed.

Click 'Edit'



Valkyrie Settings for Mac OS Profile - Table of Parameters		
Form Element	Description	
Lookup and submit files with Valkyrie	Choose this option if you want the files to be submitted to the cloud file lookup service	
Submit for	Choose the type of Valkyrie analysis, e.g, automatic online analysis or manual analysis. The options available depend on your type of subscription.	
File size limitations (MB)	Specify the maximum file size for upload to Valkyrie. The default value is 150 MB.	

Click 'Save'


6.1.4.1.8. Procedure Settings for Mac Profiles

- A procedure is a script designed to accomplish a specific task on target devices. For example, you can run
 procedures to change the permissions on specific folders on a multiple devices, or lock a device after a
 certain period of time.
- You can run scripts on Mac devices by adding a 'Procedure' section to a profile. You can create your own script or use one of the library of predefined scripts.
- New scripts must be approved by an admin before they can be deployed.
- Note This section lets you *manage* the procedures on a specific profile. The procedures themselves are actually created at 'Configuration Templates' > 'Procedures'. Click here for help to create a procedure.

Add procedures to a Mac profile


- Click 'Configuration Templates' > 'Profiles'
- Open a Mac profile in the list
- Click 'Add Profile Section' > 'Procedures'
- Click 'Edit' at top-right then 'Add':





• The 'add' screen lets you schedule the procedure and choose various other settings:





Parameter	Description
Procedure Name	Choose an existing procedure by typing the first few characters of the procedure name. Make sure you have already approved the procedure.
	See View and Manage Procedures if you want help to create procedures.
Schedule Settings	Custom Schedule
	Set a time-slot for the procedure to run on devices which use this profile (optional).
	Start date - Choose the date of the procedure's first run time.
	Schedule - Set the frequency at which the procedure should run. The available options are:




	 Never - The procedure will run only once at the time in the 'Start Date'. Daily - The procedure will run every day at your 'Scheduled Time'. Weekly - Select the days of the week that the procedure should run. Monthly - Select the dates of a month that the procedure should run. Scheduled Time - Set the time at which the procedure should run. End-Time Settings (for daily, weekly or monthly frequencies) No end settings - All procedures will run to completion. Run until - Chose a cut-off time from the calendar. Run no more than - Specify how long the procedure should run. Run until the end of the closest maintenance window - The procedure will start at the time you set, and must finish by the end of the first maintenance window after schedule start. For the last three settings, any procedure that does not finish by the cut-off time is aborted and all changes undone.
User Account Options	Choose 'Run as system user' or 'Run as logged in user' based on the access rights required for the procedure to run at the endpoint.
Execution Options	Run this procedure immediately when the profile is assigned to a new device
	The procedure will run on target devices as soon as the profile is applied to the device, in addition to any schedule.
	Skip procedure if the device is offline
	The procedure will be aborted if the device is not connected to EM at the time of execution.
	By default, procedures are queued for later deployment if the device is not connected to EM. The task will be executed as soon as it comes online.
	Select this option If you do not want the task to be added to the queue.
Report Options	Script procedures only
	 Send to current user - Procedure results are sent to the admin who is currently logged into Endpoint Manager.
	 Send to the following email addresses - Add email addresses to whom log results should be sent.
Configure parameters	Only for script procedures with variable parameters.
	Click 'Configure parameters'
	Procedure parameters ×
	Message (Data Type: String)
	Use default value Hi, How are you?
	Title (Data Type: String)
	☐ Use default value
	Message from Administrator
	Close Apply
	Use the default values or choose a new value.
	Click 'Apply'



- Click 'Add'
- Repeat the process to add multiple procedures to the profile
- Click 'Save' to add the procedures to the profile

Edit a procedure:

- Click 'Configuration Templates' > 'Profiles'
- Open the Mac profile containing the procedures component to be edited
- Click the 'Procedures' tab
- Click 'Edit' and select the procedure that needs to be modified.
- Modify the procedure as required and save it



- Then click either 'Add', 'Move Up', 'Move down', or 'Remove' based on the changes that need to take effect.
 - · Click 'Add' to add another procedure to the existing list
 - Click 'Move Up' to increase the priority of the procedure.
 - Click 'Move Down' to decrease the priority of the procedure.
 - Click 'Remove' to delete the procedure.
- Click 'Save'.

6.1.4.1.9. Monitor settings for Mac OS Profile


- The monitors settings section lets you add performance and event monitors to a Mac OS profile.
- A monitor is a script which tracks events on a managed endpoint and generates alerts if its conditions are met.
 - For example, 'Alert me when a certain process is running on the device', or 'Alert me if CPU usage goes above 75% for a certain length of time'.
- · There are two types of monitor:
 - **Predefined Monitors** A collection of monitors from Comodo which perform a range of useful monitoring tasks. These can be used in custom profiles, but cannot be edited.
 - My Monitors Custom monitors that you create. You can configure custom monitors in the 'Monitors' inventory ('Configuration Templates' > 'Monitors'). See 'Manage Monitors' for more details.
- Monitors added to the inventory can be added to a profile. You can add multiple monitors to a single profile.

Add a monitor section to a profile

ITarian Endpoint Manager - Administrator Guide




- Click 'Configuration Templates' > 'Profiles'
- Open the Mac OS profile you want to configure
- Click 'Add Profile Section' > 'Monitors'
- · Click 'Add Monitor'



- Choose Monitor(s) Add monitors to the profile
 - Start typing the first few letters of the name of a Mac OS then select from the suggestions
 - · Repeat the process to add more monitors to the profile
 - See Monitors for Mac OS Devices for help to configure a monitor
- · Click 'OK' to save your settings

The list of monitors included in the profile is shown:





Monitors - Column Descriptions		
Column Heading	Description	
Monitor Name	The monitor label.	
	 Click the name of a monitor view and edit it. See View and Edit Monitors for more details. 	
Туре	Whether the monitor is custom or predefined.	
Created by	The administrator who created the custom monitor.	
	 Click the admin name to view their details. See View User Details if you need help with this. 	
Created On	Date and time the monitor was created.	
Last Modified By	The admin who most recently edited the monitor.	
Updated On	Date and time the monitor was last edited.	
Controls		
Add Monitor	Add a monitor to the profile. See the explanation above for help with this.	
Remove Monitor	Delete monitors from the profile Use the check-boxes to select the monitors you want to remove.	

- Click any column header to sort the items based on alphabetical or ascending/descending order of entries in the respective column.
- Click the funnel button at the right end to open the filter options.

6.1.5. Profiles for Linux Devices

Linux profiles let you configure Comodo Client Security (CCS) on Linux endpoints.

ITarian Endpoint Manager - Administrator Guide



There are two ways you can add a new Linux profile to Endpoint Manager:

- Create a new Linux profile. See Create Linux a Profile for more details.
- Clone an existing profile and modify its settings to your requirements. See Clone a Profile, for more details.

6.1.5.1. Create a Linux Profile


Process in brief:

- Click 'Configuration Templates' > 'Profiles'
- Click 'Create' > 'Create Linux Profile'
- Type a name and description for your profile then click the 'Create' button. The profile will now appear in 'Configuration Templates' > 'Profiles'.
- New profiles have only one section 'General'. Click 'Add Profile Section' to add settings for various security and management features. Each section you add will appear as a new tab.
- Once configured, you can apply your profile to devices and device groups.
- You also have the option to make it a 'Default' profile. A 'default' profile is one that is automatically applied to any device which matches its operating system.
- This part of the guide explains the processes above in more detail, and includes descriptions of each profile section.

Create a new profile

Click 'Configuration Templates' > 'Profiles' > 'Create' > 'Create Linux Profile'






- Name Enter a label for the profile
- Description Enter appropriate short notes for the profile
- · Click the 'Create' button

The profile will open at the 'General Settings' section:





- 'Make Default' A 'default' profile is one that is applied automatically to any device which matches its operating system. Click this button if you want this profile to be applied to every Linux device. Do not select this if you only want to apply the profile to certain Linux endpoints.
- · Click 'Save'.


The next step is to add profile sections.

- Each profile section contains a range of settings for a specific security or management feature.
- For example, there are profile sections for 'Antivirus', 'Logging', 'UI' and so on.
- You can add as many different sections as you want when building your profile.
- To get started:
 - · Click 'Add Profile Section'
 - Select the section that you want to add to the profile:





This will open the settings screen of the component:



Click the following links to find out more about each section:

- Antivirus
- Updates
- UI Settings
- Logging Settings
- Client Access Control



Valkyrie Settings

6.1.5.1.1. Antivirus Settings for Linux Profile

The antivirus section lets you configure real-time monitoring, custom scans, scan schedules, exclusions and more.


Configure antivirus settings in a Linux profile

- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Linux profile
- Click 'Add Profile Section' then 'Antivirus' (if you haven't yet added the AV section)

OR

· Open the 'Antivirus' tab and click 'Edit' if it was already added

The antivirus settings screen will open:



It contains three tabs:

- Scanner Settings Configure real-time scans, manual scans, scheduled scans and exclusions.
- Scan Profiles Create antivirus scan profiles that define specific folders, drives or areas to scan. Once saved, you can apply a scan profile to scheduled scans.
- Scheduled Scans Timetable scans to be run on managed devices according to a selected scan profile.

Configure Scanner Settings for CCS for Linux

The 'Scanner Settings' area contains four sub-tabs:


- Realtime Scanning Set parameters for the 'always-on' virus monitor
- Manual Scanning Set parameters for on-demand scans
- Scheduled Scanning Set parameters for scheduled scans
- Exclusions View and manage items which will be skipped by virus scans.



Realtime Scanning

· Click the 'Realtime Scanning' sub-tab under 'Scanner Settings'

Please note: The real-time virus scanner is not supported on Debian. The settings in this screen do not apply to Debian devices.



Real Time Scanning Settings - Table of Parameters		
Form Element	Туре	Description
Real time scanning	Drop-down	Enable or disable the background virus monitor.
		On Access - Files are scanned before they are allowed to run. Threats are detected before they get a chance to execute (<i>Default</i>)
		Disabled - Real-time protection is switched off. Files are allowed to run without first being checked for threats.




Real Time Scanning Settings - Table of Parameters			
Do not scan files larger than (MB)	Text box	Maximum file size that the antivirus should attempt to scan. Files larger than the size specified here are not scanned. (Default = 20 MB).	
Keep an alert on the screen for (seconds)	Text box	How long threat notifications should stay on-screen if not dismissed by the end-user. (<i>Default</i> = 120 seconds)	
Automatically update virus database	Checkbox	CCS will check for and download the latest virus database updates on system start-up, and subsequently at regular intervals. • Disable this option if you do not want CCS to automatically check for updates.	
		(Default = Enabled).	
Automatically quarantine threats found during scanning	Checkbox	Threats will be encrypted and moved to a secure holding area where they can cause no harm. You can review quarantined items and delete, ignore or restore them.	
		 Disable this option if you do not want threats to be moved to quarantine. 	
		(Default = Enabled)	
Show notification messages	Checkbox	Choose whether or not a notification is to be shown to the end- user, whenever CCS identifies a threat and moves it to quarantine.	
		(Default = Disabled)	
Enable heuristic scanning	Checkbox	Enable or disable heuristics scanning and define the scan level.	
		The scan level determines how likely the scanner is to classify an unknown file as a threat.	
		 Low - Lowest sensitivity to detecting unknown threats / generates fewest false positives. The 'low' setting combines an extremely high level of security and protection with a low rate of false positives. Comodo recommends this setting for most users. (<i>Default</i>) 	
		Medium - Detects unknown threats with greater sensitivity than the 'Low' setting but with a corresponding rise in the possibility of false positives.	
		 High- Highest sensitivity to detecting unknown threats / increased possibility of false positives. 	
		(Default = Enabled with 'Low ' option)	
		Background Note : Background. Heuristics identify previously unknown malware by checking whether it contains code typical of a virus. If it is found to do so then the application deletes the file or recommends it for quarantine.	
		Heuristics is about detecting 'virus-like' attributes rather than looking for a virus signature which exactly matches a signature on the blacklist. This allows the engine to detect new viruses even if they are not in the current database.	



Manual Scanning

- Click the 'Manual Scanning' sub-tab under 'Scanner Settings'
- The options you set here will apply to manual scans on the endpoints on which the profile is active.
- A manual scan is one you run 'on-demand' on selected files, folder or drives. Manual scans can be launched from 'Security Sub-Systems' > 'Antivirus'.
- For more details on running on-demand scans on selected devices, see Run Antivirus and/or File Rating Scans on Devices.



Manual Scanning Settings - Table of Parameters		
Form Element	Description	
Do not scan files large than (MB)	Maximum file size that the antivirus should attempt to scan. Files larger than the size specified here are not scanned. (<i>Default</i> = 20 <i>MB</i>).	
Scan archive files	 CCS scans archive files such as .ZIP and .RAR files. Disable this option if you don't want archive files to be scanned. (Default = Enabled). 	
Automatically update virus database before scanning	CCS will check for and download the latest virus database before starting an on-demand scan • Disable this option if you do not want CCS to automatically check for updates. (Default = Enabled).	
Enable cloud scanning	CCS detects the very latest viruses more accurately because the local scan is	




M	anual Scanning Settings - Table of Parameters
	augmented with a real-time look-up of Comodo's online signature database. This makes it possible to detect zero-day malware even if your local virus database is outdated. (Default = Disabled).
Enable heuristic scanning	Enable or disable heuristics scanning and define the scan level.
	The scan level determines how likely the scanner is to classify an unknown file as a threat.
	 Low - Lowest sensitivity to detecting unknown threats / generates fewest false positives. The 'low' setting combines an extremely high level of security and protection with a low rate of false positives. Comodo recommends this setting for most users. (<i>Default</i>)
	 Medium - Detects unknown threats with greater sensitivity than the 'Low' setting but with a corresponding rise in the possibility of false positives.
	High- Highest sensitivity to detecting unknown threats / increased possibility of false positives.
	(Default = Enabled with 'Low ' option)
	Background Note : Background. Heuristics identify previously unknown malware by checking whether it contains code typical of a virus. If it is found to do so then the application deletes the file or recommends it for quarantine.
	Heuristics is about detecting 'virus-like' attributes rather than looking for a virus signature which exactly matches a signature on the blacklist. This allows the engine to detect new viruses even if they are not in the current database.

Scheduled Scanning

- Click the 'Scheduled Scanning' sub-tab under 'Scanner Settings'
- The options you set will apply to scheduled scans created for the profile. See **Create and Manage Scheduled Scans for the Profile** if you need help with this.





Scheduled Scanning Settings - Table of Parameters		
Form Element	Description	
Do not scan files large than (MB)	Maximum file size that the antivirus should attempt to scan. Files larger than the size specified here are not scanned. (Default = 20 MB).	
Scan archives files	CCS scans archive files such as .ZIP and .RAR files.	
	Disable this option if you don't want to scan archive files.	
	(Default = Enabled).	
Automatically quarantine threats found during scanning	Threats identified by scheduled scans will be encrypted and moved to a secure holding area where they can cause no harm. You can review quarantined items and delete, ignore or restore them.	
	 Disable this option if you do not want threats to be moved to quarantine. 	
	(Default = Enabled)	
Automatically update virus database before scanning	CCS will check for and download the latest virus database updates on system start-up, and subsequently at regular intervals.	
	 Disable this option if you do not want CCS to automatically check for updates. (<i>Default = Enabled</i>). 	
Show scanning progress	End-users will see a scan progress bar when the scan is running.	
	Disable this option if you don't want CCS to show the progress bar.	




Scheduled Scanning Settings - Table of Parameters		
Form Element	Description	
	(Default = Enabled)	
Enable cloud scanning	CCS detects the very latest viruses more accurately because the local scan is augmented with a real-time look-up of Comodo's online signature database. This makes it possible to detect zero-day malware even if your local virus database is outdated. (<i>Default = Disabled</i>).	
Enable heuristic scanning	Enable or disable heuristics scanning and define the scan level.	
	The scan level determines how likely the scanner is to classify an unknown file as a threat.	
	 Low - Lowest sensitivity to detecting unknown threats / generates fewest false positives. The 'low' setting combines an extremely high level of security and protection with a low rate of false positives. Comodo recommends this setting for most users. (<i>Default</i>) 	
	 Medium - Detects unknown threats with greater sensitivity than the 'Low' setting but with a corresponding rise in the possibility of false positives. 	
	 High- Highest sensitivity to detecting unknown threats / increased possibility of false positives. 	
	(Default = Enabled with 'Low ' option)	
	Background Note: Background. Heuristics identify previously unknown malware by checking whether it contains code typical of a virus. If it is found to do so then the application deletes the file or recommends it for quarantine.	
	Heuristics is about detecting 'virus-like' attributes rather than looking for a virus signature which exactly matches a signature on the blacklist. This allows the engine to detect new viruses even if they are not in the current database.	

Exclusions

- Click the 'Exclusions' sub-tab under 'Scanner Settings'
- You can add files to be ignored by CCS during virus scans.
- Note. Any item you exclude will be skipped by ALL types of scan real-time, on-demand and scheduled.






A list of excluded items will be displayed.

To add an item to the 'Exclusions' list

Click 'Add'






- Enter the location of the item to be excluded in the 'Path' field and click 'Ok'
- Repeat the process to add more items
- To edit the path of an item, click the pencil icon beside it

Create and Manage Scan Profiles for the Profile

- Click the 'Scan Profiles' tab under 'Antivirus'
- Scan profiles instruct CCS to scan selected areas, folders or drives on a the device.
- The scan profiles you create here will be available when you configure a scheduled scan.






The list of pre-defined scan profiles will be displayed.


To add a new scan profile

Click 'Add'






- Enter a name for the scan profile
- Click 'Add' to specify the locations to be scanned as per the custom profile




• Enter the path of the location to be scanned as per the custom profile and click 'Ok'

The path will be added to the profile.





- · To add more paths, click 'Add Path' and repeat the process
- To edit the path, click the pencil icon beside it
- Click 'Ok' in the 'Add Scan Profile' dialog.
- The profile will be added to the list of 'Scan Profiles'.




The custom profile will be added to the list.

- To add more custom scan profiles, click 'Add' and repeat the process
- To edit a custom scan profile, click the pencil icon beside it
- To remove a custom scan profile, select it and click 'Remove'



Create and Manage Scheduled Scans for the Profile

- Click the 'Scheduled Scans' tab under 'Antivirus'
- The highly customizable scan scheduler lets you timetable scans to be run on managed devices according to your preferences. CCS automatically starts scanning the entire system or the disks or folders contained in the scan profile selected for that scan.
- You can add any number of scheduled scans for a profile to run at a time that suits your preference. A scheduled scan may contain any scan profile of your choice.




A list of pre-configured scheduled scans will be displayed.

To add a new scheduled scan

Click 'Add'






Add Scheduled Scan - Table of Parameters		
Form Element	Туре	Description
Name	Text box	Label for the scheduled scan
Profile	Drop-down	Choose the pre-defined or custom scan profile to be applied for the scheduled scan. The scan profiles included under the 'Scan Profiles' tab will be available in the drop-down.
Day of the Week	Buttons	Select the day(s) of the week on which the scan has to run
Time	HH:MM drop- down combo boxes	Set the time at which the scans are to run on the selected days.



Click 'Ok'

The scheduled scan will be added to the list.



- To add more scheduled scans to the configuration profile, click 'Add' and repeat the process
- To edit the settings of a scheduled scan, click the pencil icon
 beside it
- To remove a scheduled scan, select it and click 'Remove'
- Click 'Save' on the top right for your settings to take effect for the profile.

The settings will be saved and displayed under the 'Antivirus' tab. You can edit the settings or remove the section at anytime. See **Edit Configuration Profiles** for more details.

6.1.5.1.2. Communication Client and Comodo Client - Security Application Update Settings for Linux Profile

This section lets you enable or disable automatic updates and specify an alternate host from which endpoints should collect updates. By default, updates are downloaded from <a href="https://download.com/download.c

Configure updates settings in a Linux profile


- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Linux profile
- Click 'Add Profile Section' then 'Updates' (if you haven't yet added the 'Updates' section)

OR

· Open the 'Updates' tab and click 'Edit' if it was already added

The 'Updates' settings screen will open:






 Use the checkbox beside 'Enabled' to enable or disable downloading updates from the URL specified beside it.

You can add the URL of an alternative download host if required. For example, you may want to distribute the updates from a local server to conserve bandwidth.

To add a host in the local network

· Click 'Add'





- Enter the URL or IP of the host from which updates should be downloaded in the 'URL' field
- Select the 'Enable' to activate the host
- Click 'Ok' to apply your changes
- Repeat the process to add multiple hosts.
- To edit a host, click the pencil icon beside the host name in the list
- · Click 'Save' for your settings to take effect in the profile

6.1.5.1.3. User Interface Settings for Linux Profile

The 'UI Settings' section lets you choose the interface language for the CCS application on the endpoint.

Configure Language Settings in a Linux Profile


- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Linux profile
- Click 'Add Profile Section' then 'UI Settings' (if you haven't yet added the 'UI Settings' section)

OR


· Open the 'UI Settings' tab and click 'Edit' if it was already added

The 'UI Settings' screen will open:





 Select the language which should be used in the Comodo Client Security interface from the Language dropdown. (*Default = English (United States*))



Click 'Save' to apply your changes to the profile.

6.1.5.1.4. Logging Settings for Linux Profile

- The 'Logging' area lets you specify how logs should be collected in CCS
- For example, you can choose max. log size, log format and location, and extended log options.

Configure 'Logging' Settings in a Linux Profile

Click 'Configuration Templates' > 'Profiles'




- · Click on the name of a Linux profile
- Click 'Add Profile Section' then 'Logging Settings' (if you haven't yet added the 'Logging' section)

OR

· Open the 'Logging' tab and click 'Edit' if it was already added

The 'Logging' settings screen will open:





Logging Settings - Form Parameters		
Parameters	Description	
Write to Local Log Database (COMODO Format)	The log is saved in native Comodo format on the local endpoint.	
Write to Syslog Server	Endpoint Manager log events are written to a remote syslog server. If enabled you have to specify the hostname/IP address and port number settings for the server.	
Host *	The host name or IP address of the syslog server.	
Port *	The port number of the syslog server.	
Write to Log File (CEF Format)	Logs are saved locally on the endpoint in Common Event Format (CEF) file format. If enabled, please specify the location of the CEF file.	
Path	Enter the location of the CEF file.	
Log file size (MB)	Specify the maximum size of the log file (default = 100 MB).	
Action when file log size reaches limit:	Specify behavior when the log file reaches the max. size.	
Keep on updating it removing the oldest records	Once the log file reaches the maximum size, the file will be appended with the new log entries and the oldest entries will be deleted.	
Move it to	Move and save the log file when it reaches the maximum size.	
The path to the folder for old log files *	If 'Move it to' is enabled, type a destination path for the log file.	

Fields marked * are mandatory.

Click the 'Save' button to apply your changes.

6.1.5.1.5. Clients Access Control Settings for Linux Profile

- Access control lets you password-protect the antivirus settings area on Comodo Client Security on managed endpoints.
- Once set, users will need to enter a password to access the antivirus settings area ('Antivirus' > 'Scanner Settings').
- This stops users from opening the clients locally and making potentially dangerous changes. Without password protection, any user can modify AV settings and options.
- Users can still run some simple tasks without the password, including on-demand scans and database updates.

Implement access control


- Click 'Configuration Templates' > 'Profiles'
- Click on the name of a Linux profile
- Click 'Add Profile Section' then 'Client Access Control' (if you haven't yet added the section)

OR

· Open the 'Client Access Control' tab and click 'Edit' if it was already added

The 'Client Access Control' settings screen will open:





- Enable password protection for the settings Make users enter a password before they can access the AV settings area in the CCS interface.
 - · Enter and confirm the password in the fields provided
 - Click 'Save' for your changes to take effect

6.1.5.1.6. Valkyrie Settings for Linux Profile

- Valkyrie is a cloud-based file verdict service that subjects unknown files to a range of tests in order to identify those that are malicious.
- Comodo Client Security for Linux can automatically submit unknown files to Valkyrie for analysis. When the
 tests are complete, Valkyrie will award a trust verdict to the file.
 - Note 'Cloud Scanning' should be enabled in Antivirus section of CCS for Linux on the endpoints.
- The verdicts can be viewed in 'Security Sub-Systems' > 'Valkyrie' interface.
 - See View list of Valkyrie Analyzed Files for more details.
- Click 'Dashboard' > 'Valkyrie' to view summary of all Valkyrie results.

Note: The version of Valkyrie that comes with the free version of Endpoint Manager is limited to the online testing service. The Premium version of Endpoint Manager also includes manual testing of files by Comodo research labs, helping enterprises quickly create definitive whitelists of trusted files. Valkyrie is also available as a standalone service. Contact your lTarian Account manager for further details.

You can configure Valkyrie and create an analysis schedule by adding a 'Valkyrie' section to a profile.




Configure Valkyrie Settings

- Click 'Configuration Templates' > 'Profiles'
- Open the Linux profile that you want to work on
- · Click 'Add Profile Section'
- · Select 'Valkyrie' from the menu

The 'Valkyrie' settings screen will open.

· Click 'Edit'



Valkyrie Settings for Linux Profile - Table of Parameters		
Form Element	Description	
Lookup and submit files with Valkyrie	Choose this option if you want the files to be submitted to the cloud file lookup service	
Submit for	Choose the type of Valkyrie analysis, e.g, automatic online analysis or manual analysis. The options available depend on your type of subscription.	
File size limitations (MB)	Specify the maximum file size for upload to Valkyrie. The default value is 150 MB.	


Click 'Save'

6.2. View and Manage Profiles

- Click 'Configuration Templates' > 'Profiles' to open this interface
- The 'Profiles' screen shows all available configuration profiles for Android, iOS, Mac OS, Windows and Linux devices.
- You can create, deploy, import/export, and clone profiles from this interface.

ITarian Endpoint Manager - Administrator Guide





The interface has two tabs:

- Profiles A list of all profiles added to Endpoint Manager.
- Default Profiles A default profile is one that is automatically applied to any device that matches its
 operating system. See Manage Default Profiles for more details.




The 'Profiles' interface			
Col	lumn	Description	
OS		The operating system that the profile supports.	
Name		Label of the profile.	
		 Click the profile name to open the profile settings and configuration interface. See Edit Configuration Profiles for more details. 	
Created by		The administrator who created the profile.	
		 Click the name of an administrator to view their user details. See View the details of the User for more details. 	
Created		The date and time at which the profile was created.	
Updated at		The date and time at which the profile was last updated.	
		Controls	
Create	Create Android profile	Add a new Android profile. See 'Profiles for Android Devices' for more details.	
	Create iOS profile	Add a new iOS profile. See 'Profiles for iOS Devices' for more details.	
	Create Mac OS profile	Add a new Mac OS profile. See 'Profiles for Mac OS Devices' for more details.	
	Create Windows profile	Add a new Windows profile. See 'Create Windows Profiles' for more details.	
	Create Linux profile	Add a new Linux profile. See 'Profiles for Linux Devices' for more details.	
Import	Import from Comodo Client Security Config file	Import the security configuration of CCS from a .cfg configuration file as a Windows profile. The configuration file will usually have been exported from a managed endpoint with CCS installed. See 'Import Windows Profiles' for more details.	
	Import from Exported Profile	Import a configuration profile from a previously exported and saved profile. See Export and Import Configuration Profiles for more details.	
Clone Profile	e	Create a new profile by cloning an existing profile and modifying its settings as required. See Clone a Profile for more details.	
Export profile		Export the selected configuration as a .cfg file and save it for future implementation. See Export and Import Configuration Profiles for more details.	
		The control will appear only if a single profile is selected from the list.	
Delete profil	e	Remove selected profile(s).	
		The control will appear only if one or more profiles are selected.	
Export		Save the list of profiles as a comma separated values (CSV) file. See Export the List of Profiles for more details.	



Sorting, Search and Filter Options


- · Click any column header to sort items in ascending/descending order
- Click the funnel icon to filter profiles by various criteria:



Export the List of Profiles

- Click 'Configuration Templates' > 'Profiles'
- Click the 'Export' button above the table then choose 'Export to CSV':





- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

6.2.1. Export and Import Configuration Profiles


You can export and import profiles for re-deployment to other devices and groups.

Note: 'Monitor Settings' and 'Procedure Settings' are not included in exported profiles. You will need to reconfigure these sections before deploying, if you require them.

Export a profile

- Click 'Configuration Templates' > 'Profiles'
- · Select the 'Profiles' tab.
- Select the profile you want to export then click the 'Export profile' button:






You will see a prompt stating that the monitoring and procedures sections will be omitted from exported profiles.

- Click 'Confirm' to export the profiles to .cfg file
- Exported files can be imported back into Endpoint Manager as a profile at any time.


To import a profile from a saved .cfg file

• Open the 'Profiles' interface by clicking 'Configuration Template' from the left and choosing 'Profiles' from the options.



- Click 'Import' > 'Import from Exported Profile'.
- Navigate to the location in your computer where the .cfg file is stored, select the file and click 'Open'.
- The 'Profile' interface will open, with the prefix [Imported] in the file name and security components preconfigured as per the source profile.





The imported profile is not set as a 'Default Profile' by default.

- Click the 'Edit' button in 'General Settings' to change the profile name and/or make it a default profile.
- · Click 'Add Profile Section' to add a new component
- Click the name of an existing component name to view/edit its settings

See the following sections for help with profiles:

- Profiles for Android Devices
- Profiles for iOS Devices
- Profiles for Mac OS Devices
- Profiles for Windows Devices.
- Profiles for Linux Devices


6.2.2. Clone a Profile

- Cloning then modifying a profile is an easy way to set up a new profile with custom settings.
- You can edit the cloned profile according to the requirements of your target devices or group.

Clone a profile

- Click 'Configuration Templates' > 'Profiles'
- Select the 'Profiles' tab.
- Click on the name of the profile you want to clone.
- Click 'Clone Profile' in the profile details page
 - Alternatively, select the profile in the 'Profiles' interface and click 'Clone Profile' at the top.





The name of the new profile is the same as the source profile with the prefix [cloned].

- Enter a new name for the profile (if required) and a short description
- · Click 'Clone'.

The new profile has identical settings to the source profile at this stage. To configure the profile:

- Click 'Configuration Templates' > 'Profiles'
- · Click on the name of the cloned profile
 - · Click 'Add Profile Section' to configure settings that were not included in the original
 - Click a section name then 'Edit' to change existing settings. Each existing section is shown as
 a tab underneath the profile name
- For more details on the options available under each component, see the following sections for more details:
 - Profiles for Android Devices
 - Profiles for iOS Devices
 - Profiles for Mac OS Devices
 - Profiles for Windows Devices.
 - Profiles for Linux Devices




6.3. Edit Configuration Profiles

- You can edit an existing configuration profile to modify settings as required.
- For example, you might want to enable or disable certain security components or add a procedure to the profile.
- The updated profile is automatically deployed to endpoints after you save.

Edit a profile

- Click 'Configuration Templates' > 'Profiles'
- Select the 'Profiles' tab
- · Click on the name of the profile that you want edit.
- This will open the profile details screen:



The tabs let you configure various Endpoint Manager modules. Click 'Add Profile Section' if you want to add a new module.

Click the tab of the section you want to edit. For example, 'General', 'Monitoring', 'Antivirus', 'Firewall'.



• Some tabs let you directly edit the parameters. In others, you will need to click the 'Edit' button:



- See the following sections for in-depth help on the settings in a profile:
 - Profiles for Android Devices
 - Profiles for iOS Devices
 - Profiles for Mac OS Devices
 - Profiles for Windows Devices.
 - Profiles for Linux Devices
- Click 'Save' for your changes to take effect
- Click the 'Delete Profile' button if you want to entirely remove a profile. The profile will be automatically
 uninstalled from devices on which it is active.

6.4. Manage Default Profiles

- 'Default' profiles are automatically assigned to new devices which match their operating system IF no user / user-group profile exists for the OS.
 - Default profiles are only applied if no user or user-group profile exists for the operating system.
 - If you remove all user profiles from a device then they will be replaced by the appropriate default profiles.
 - You can mark any profile you want as a 'default' profile. You can also apply multiple default profiles to the same devices.
- Endpoint Manager ships with the following default profiles:
 - · Windows Security Level 1 Profile
 - Mac OS Security Level 1 Profile
 - Android Security Level 1 Profile
 - iOS Security Level 1 Profile
 - Linux Security Level 1 Profile


Each of the profiles above provides good, baseline security for managed devices. These profiles cannot be modified or deleted, but may be replaced on devices by another profile.

- Endpoint Manager also ships with three, non-default, profiles for Windows:
 - Windows Security Level 1 Profile [Former Standard Profile]
 - Windows Security Level 2 Profile
 - Windows Security Level 3 Profile
- You can remove 'default' status from any profile, including the 'built-in' profiles mentioned above. However, it is mandatory to have at least one default profile per operating system.
- You can turn any profile you want into a default profile. You can also clone a default profile to use as a template for a new profile.

View and manage default profiles

- Click 'Configuration Templates' > 'Profiles'
- Select the 'Default Profiles' tab at the top.





The image above shows the default profiles shipped with Endpoint Manager.

Click the following links for more help:

- Create a default profile
- View and manage default profiles
- Assign default profiles to devices
- Remove default profiles
- Cancel default profiles
- Export the list of Default Profiles to a CSV file

Create a default profile


You can turn any profile into a 'default' profile. You can do this when you create a new profile, or by editing an existing profile.

- Create a new default profile
- Turn an existing profile into a default profile

Create a new default profile

- Click 'Configuration Templates' > 'Profiles'
- Click the 'Profiles' tab
- Click 'Create' and choose the OS of the profile:






- Enter a name and description for the profile
- · Click the 'Create' button

The profile will open at the 'General Settings' screen.


· Click 'Edit' at the top right and enable 'Is Default':





· Click 'Save'.

The new profile will be listed in the 'Default Profiles' area:






You can edit the profile and add profile components (sections) as required. See **Edit Configuration Profiles** for more details.

Turn an existing profile into a default profile


- Click 'Configuration Templates' > 'Profiles'
- Click the 'Profiles' tab
- Click the name of the profile that you want to set as a default:




- Click the 'Make Default' button in the profile details screen.
 - Or
- · Click the 'Edit' button then enable 'Is Default'
- Click 'Save'.



The profile will be listed in the 'Default Profiles' screen:



The 'Default Profiles' interface




Default Profiles - Column Descriptions		
Column Heading	Description	
OS	The operating system of the devices to which the profile is applied.	
Name	The label of the profile Click the profile name to open its details interface. This area lets you view and edit profile settings. See Edit Configuration Profiles for help with this.	
Created by	The admin who created the profile.	



	 Click the admin name to view their details. See View the details of the User if you want help with the user details screen.
Updated at	Date and time the profile was most recently edited.

- Click any column header to sort items in ascending/descending order of the entries in that column.
- · Click the funnel icon to filter by OS, profile name, author or date:




Assign default profiles to devices

- New devices are automatically given the default profiles for their operating system IF there are no user/user group profiles for the device owner.
- Conversely, if you remove all user/user-group profiles from a device, then the default profiles are automatically deployed to take their place.



Cancel default profiles

- You can cancel the default status of built-in profiles so they are not applied to new devices on enrollment. They will also be removed from any existing devices.
- For devices with no profiles applied, you can carry out on-demand functions such as run antivirus scans, run a procedure and so on. For Windows devices with CCS installed, when there are no profiles applied, the default CCS settings will apply.
- To open the default profiles screen, click 'Configuration Templates' > 'Profiles' on the left then choose the 'Default Profiles' tab.



- Click the name of the default profile from the list
- Click 'Cancel Default' button at the top Or
- Click 'Edit' on the right, deselect 'Is Default' check box and click 'Save'

The 'Edit' button is not available for built-in default profiles. You can remove default status only by clicking the 'Cancel Default' button at the top.

Notes:

• It is mandatory to have at least one default profile for each operating system.




- You cannot cancel a default profile if it is the only default available for an OS.
 - Workaround Assign a different profile as a default, then go back and cancel the first profile.

Export the list of Default Profiles to a CSV file

You can export the list of default profiles to a comma-separated values (CSV) file as follows:

Click the 'Export' button above the table then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

6.5. Manage Alerts

Click 'Configuration Templates' > 'Alerts'

- You can create procedures and monitors to track certain activities and generate an alert if their conditions
 are met. For example, 'Generate an alert if CPU usage exceeds 90%', or 'Alert me when all Windows
 patches have been installed.'
- The 'Alerts' section contains templates of settings for these alerts. For example 'Send a notification to these recipients...', or 'Create a service desk ticket from the issue'.
- You apply the alert template to the procedure, monitor or discovery scan. You can have multiple templates
 to address different types of events. For example, you might want the alert for a failed patch to be different
 to the alert for a system restart.
- In the standard workflow, all procedures, monitors and discovery scan tasks have the 'Default Alert' template applied to them.
 - Click 'Configuration Templates' > 'Alerts' > 'Default Alert' to view these settings.
- You can activate or deactivate alerts as per your requirement.
- If you want different alert settings for a specific event then you must create a new alert in this interface. For
 example, you may want the alert to be sent to specific recipients, or certain metrics to be included in the
 alert.
- Example:

ITarian Endpoint Manager - Administrator Guide



- Click 'Procedures' > 'Predefined Procedures' > 'Monitors' > 'Alert if a new scheduled Task is Created'.
 You will notice the 'Default Alert' is used if the procedure fails. If you want to implement different alert settings then:
- Click 'Clone' to make a copy of the procedure. The procedure will be saved in the 'My Procedures' section as '[cloned] Alert if a new scheduled task is created'.
- Go to the alerts section and click 'Create Alert'. Name the alert and configure its settings as required.
- Next, open your cloned procedure and click 'Edit'. Type the name of the alert settings you want to use in the 'Use alert settings...' field. Click 'Save'.
- You can also specify that your new alert settings are used in the 'Monitoring' section of a profile.

Column Heading	Description
Alert Name	Label of the alert.
	Click the alert name to open the alert configuration interface. See Edit / Delete an Alert for more details.
Status	Indicates whether the alert is enabled or disabled.
Created by	The administrator who created the alert.
	 Click the name of an administrator to view their user details. See View the details of the User for more details.
Created on	The date and time at which the alert was created.
Last Modified by	The administrator who recently edited the alert.
	 Click the name of an administrator to view their user details. See View the details of the User for more details.
Updated on	The date and time at which the alert was last updated.
	Controls
Create Alert	Add a new alert. See 'Create a New Alert' for more details.
Clone Alert	Create a new alert by cloning an existing alert and modifying its settings as required. See 'Create a New Alert' for more details.
Delete Alert	Remove selected alert(s).
	The control will appear only if one or more alerts are selected. See Edit / Delete an Alert for more details.
Turn on Alert	Enable alerts. Alerts are shown only if they are enabled. See Enable Alerts for more details.
Turn off Alert	Disable alerts. Alerts are not shown if they are disabled. See Disable Alerts for more details.
Export	Save the list of alerts as a comma separated values (CSV) file. See Export the List of Alerts for more details.




- Click on any of the column headers to sort the items in ascending/descending order of entries in that column.
- Click the funnel icon to search for alerts based on the filter parameters
- To display all alerts again, clear all filters and click the 'Apply' button.
- · Click the funnel icon again to close filter options

Enable Alerts

Alerts are shown only if they are enabled. When an alert is created, it is activated by default.

Activate disabled alerts

- Click 'Configuration Templates' > 'Alerts'
- Select a deactivated alert and click 'Turn On Alert' above




The alert is activated.

Disable Alerts


Deactivated alerts are not shown when triggered. Default alert is always turned on. The following message is shown if you select a deactivated alert during a component configuration.





Deactivate enabled alerts

- Click 'Configuration Templates' > 'Alerts'
- Select an activated alert and click 'Turn off Alert' above




The alert is disabled and not shown when triggered.

Export the List of Alerts

Export the list of alerts to a .csv file as follows:

- Click 'Configuration Templates' on the left then choose 'Alerts'.
- Click the 'Export' button above the table then choose 'Export to CSV':





- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Click the following links for more details:

- · Create a new alert
- · Edit / delete an alert

6.5.1. Create a New Alert


There are two ways to create an alert:

- Create new alert
- · Clone an existing alert and edit it as required

Create a new alert


- Click 'Configuration Templates' > 'Alerts'
- Click 'Create Alert'






- Alert name Enter a label for the alert
- **Description** Short notes about the alert
- Click 'Create'

The alert is saved and the configuration screen opens at the 'General' section:



Click the 'Alert Settings' tab then 'Edit'






- **Don't create additional alerts (about the same issue) for** Specify whether repeat alerts should be generated if the same issue occurs within the stated period. You can choose a time period between 5 minutes and 5 days.
- Create notifications on the portal The alert is also shown in the Notifications screen.
- Create alert tickets on the Service Desk If enabled, a support ticket is automatically created in Service Desk in response to the alert. You can choose the department to which the ticket is assigned.
 - Append to an original ticket if there is an open ticket for performance monitoring conditions Enable to add the alert information to an existing ticket, if one exists for the same issue. If disabled, a
 new ticket is created for every alert.
 - Automatically close the ticket if the metrics go below the threshold Enable to auto-close the
 ticket if the monitored condition reverts back to acceptable levels. For example, if an alert is created
 because disk usage goes above 90%, the ticket will be auto-closed should disk usage fall back below
 90%
 - Open the tickets under Select the Service Desk department to which you want to assign the tickets.



The drop-down shows all departments in Service Desk

Click the 'Synchronize' button to instantly import any new departments created in Service Desk

- Open the tickets with priority Select the ticket priority normal, high or critical.
- Additional device data and metrics to be inserted in the ticket By default, the name of the company, device type, device OS and the owner information are included in the ticket. To add additional device data and metrics to the ticket, select the respective options.
 - Device Data Adds device information like brand, model. IP address and so on
 - Performance Metrics Adds device performance information like CPU usage, RAM usage, disk usage, network usage and more
 - Connectivity Metrics Adds information on network to which the device is connected, like local IP address, external IP address, gateway IP address and more
- Click 'Save'
- Click 'Additional Recipients' then 'Edit' to choose additional recipients of alert emails:




- Send e-mails if Monitoring or Procedure register alerts more than the selected number of consecutive times Choose when email alerts should be sent about an issue. For example, if you select 5 from the drop-down, email alerts are only sent if the same issue occurs 5 times.
 - Send to the portal administrators Emails are sent to all users that have an 'Administrator' role.
 - Send to the following e-mail addresses Add additional recipients of the alert. You can add multiple recipients. Press either 'Tab' or 'Enter' between email addresses.
 - Send to the following portal users Add recipients who have a 'User' role. Start typing the username and select from the suggestions. You can add multiple users.



Click 'Save' to apply your changes. The alert will be created and displayed in the list. The alerts will be
available for selection in the Procedure section and while configuring Monitor Settings for a Windows
profile.

Create an alert by cloning an existing alert

- Click 'Configuration Templates' > 'Alerts'
- Select the alert you want to clone.
- Click 'Clone Alert' at the top:




- If required, enter a new name for the alert and a short description
- Click 'Clone'.

A new alert will be created with settings identical to the source alert.

Click the name of the cloned alert





- Edit the alert settings as required. The **section above** explains all settings, if you need help with them.
- · Click 'Save' to apply your changes

6.5.2. Edit / Delete an Alert

Modify an alert:


- Click 'Configuration Templates' > 'Alerts'
- · Click the name of the alert you wish to modify
- Click the 'Edit' button on the right
- You can edit settings in the 'General', 'Alert Settings' and 'Additional Recipients' areas
- · See 'Create a New Alert' for more information on the settings in these areas
- Click 'Save' to apply your changes

Before deleting an alert, please consider whether it is currently being used on any **Procedures** or **Monitors** for a Windows profile. Please also investigate whether the alert could be edited rather than deleted.

Delete an alert:

- Click 'Configuration Templates' > 'Alerts'
- Click the name of the alert you wish to delete
- Click the 'Delete' button on the right.
- Click 'Confirm' in the confirmation dialog:





6.6. Manage Procedures

- Click 'Configuration Templates' > 'Procedures'
- · Procedures are instruction scripts for Windows and Mac devices.
- You can use procedures to identify and fix issues, monitor resources, and run patches
- You can add procedures to a profile or run them directly on devices.
- You can use one of the ready-made predefined scripts, or write your own custom script. Custom scripts
 must be approved by an admin before you can deploy them.
- Windows run script and/or patch procedures. Mac devices custom script procedures only.

Features include:

- Select a predefined or custom procedure to execute on endpoint
- · Easily modify procedure variables.
- Compose your own scripts in our Python editor.
- Update Windows and third party apps with a patch procedure
- Combine procedures to build broader procedures.
- Import procedures from JSON.
- Export and clone procedures.
- Run procedures on demand by selecting 'Run Over Device'.
- Add procedures to profiles and create schedules for them.




Please use the following links to learn more about procedures:

- View and Manage Procedures
- Create a Custom Procedure
- Combine Procedures to Build Broader Procedures
- Review / Approve / Decline New procedures
- Add a Procedure to a Profile / Procedure Schedules
- Import / Export / Clone Procedures
- Change Alert Settings
- Apply Procedures to Devices
- Directly Apply Procedures to Devices
- Edit / Delete Procedures
- View Procedure Results

6.6.1. View and Manage Procedures

- Click 'Configuration Templates' > 'Procedures'
- There are two categories of procedure:
- 'Predefined Procedures- two types: 'Script' and 'Patch' procedures.
 - EM does not support patch procedures for MAC devices, and there are currently no predefined procedures for MAC. You can only create custom procedures.
- 'My Procedures' custom procedures that you create.
- You cannot edit a predefined procedure, but you can clone one and modify it to create a custom procedure.
 See Create a Custom Procedure for help with this.
- The predefined procedures folder has multiple sub-folders with scripts for various task areas. Click here to view a full list of sub-categories.
- The 'Patch Deployment' sub-folder has procedures to install updates on Windows OS devices.






Column Heading	Description
OS	The operating system for which the procedure was designed.
Procedure Name	The procedure label. Click the name to view, edit, schedule or approve/decline the procedure. See Review / Approve / Decline New Procedures and Edit / Delete Procedures for more details.
Туре	Whether the procedure is a custom or a predefined procedure.
Status	The current status of the procedure. The possible statuses are:
Content Type	States whether the procedure is script procedure or a patch procedure.
Created by	The administrator who created the custom procedure. • Click the admin name to view their details. See View User Details if you need help with this.
Created On	Date and time the procedure was created.
Last Modified By	The admin who most recently edited the procedure.
Updated On	Date and time the procedure was last edited.
	Controls
Create	Configure a new script or patch procedure. See 'Create a Custom Procedure' for help with this.
Import / Export / Clone	Import a saved procedure, export and save a procedure, or clone an existing procedure. Cloned procedures can be modified to create a new, custom procedure. See 'Import / Export / Clone Procedure' for more details.
Run	Execute a procedure on target devices. See 'Directly Apply Procedures to Devices' for more details.
Delete Procedure	Remove procedures from Endpoint Manager. Use the check-boxes to select the procedures.
Export	Save the list of currently displayed procedures as a comma separated values (CSV) file. The exported .csv is available at 'Dashboard' > 'Reports' See Export the List of Procedures for more details.

Sub-categories of 'Predefined Procedures':

EM currently has predefined procedures for Windows devices only.



- Click 'Configuration Templates' > 'Predefined Procedures'
- Click the 'Predefined Procedures' folder
- Open a category folder to view related procedures
- Procedures are shown on the right:



The following table lists all predefined categories and procedures:

Category	Procedures
Application	Scripts to run tasks on Comodo and 3rd party applications.
	Examples include install/uninstall applications, kill running applications, get details on running applications/processes/servers + many other useful scripts.
C1 Integration	Scripts to ensure your ITarian environment runs smoothly. Examples include generate a patch report, run a backup operation, and restart the communication client.
File Operations	Copy, move/delete files/folders, find and remove duplicate files, compress/decompress folders, clean up temporary/downloaded files, and more.
Monitors	Scripts to generate alerts or run specific tasks if a condition is met. For example, 'Alert me if someone connects a USB drive to the system'.
	These can be used in the monitor settings of a Windows profile. See Add Custom Monitoring Conditions for more details.
Network	Scripts to run tasks on, or get information about, your network.




	For example, view TCP/IP settings, save/restore network configurations, clear DNS cache and more
Patch Deployment	Installation and update of OS patches of different categories.
Reports	Contains procedures for obtaining various system logs.
System	Reboot devices, create restore point, enable/disable USB ports, mapping network drives, running disk defragmentation, fixing disk errors and more.
Task Scheduler	Create new tasks and schedule them, run tasks and more.
User Accounts	Add/remove domain user to a group, enable/disable user access control (UAC), get UAC status and more.

Any predefined procedure can be cloned and edited to create a custom procedure. See the following sections for more details.

- Import / Export / Clone Procedures
- Edit Procedures
- Add a Procedure to a Profile / Procedure Schedules

View 'My Procedures':


• Click 'Configuration Templates' > 'Procedures'. Expand the 'My Procedures' folder. Each folder has subfolders which display procedures under specific categories (for example, 'Ready for review').



Add a sub folder to the My Procedures folder:


Place your mouse on the 'My Procedures' folder and click '+' beside it





Enter a name for the sub-folder to be created in the 'Add Folder' dialog and click 'Add'

The sub-folder will be created and displayed under 'My Procedures'



You can also add sub-folders of a sub-folder. Once sub folders are created, you can create new procedures inside them or import/clone predefined procedures.


See the following sections for more details about:

- Create a new procedure
- Import / Export / Clone a procedure
- Edit a Procedure

Edit the name of a sub folder under 'My Procedures'

- Place your mouse on the sub folder and click the pencil symbol beside it
- Enter a new name for the sub-folder in the 'Edit Folder' dialog and click 'Save'






The folder name will be updated in folder tree.

Note: You cannot edit or delete the 'Ready for Review' folder.

Delete a sub folder under 'My Procedures' folder:

Place your mouse on the sub folder and click the trash can symbol beside it






· Click 'Confirm' to update the tree.

Export the Procedure List

- Click 'Configuration Templates' > 'Procedures'.
- · Click 'My Procedures' or 'Predefined Procedures'
- · Click the 'Export' button then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.




6.6.2. Create a Custom Procedure

Endpoint Manager lets you create custom script/patch procedures to achieve specific tasks. Click the following links to find out more:

- Create a custom Windows / Mac OS script procedure
- Create a custom Windows patch procedure
- Create a custom Windows 3rd Party application patch procedure


Create a custom Windows / Mac OS script procedure

Click 'Configuration Templates' > 'Procedures' > 'Create Vindows Script Procedure' or 'Create macOS Script Procedure'



The process to create script procedure for Windows and Mac OS is the same. Windows script procedure creation is explained below.






- Procedure name Create a label which describes the purpose of the procedure.
- Description Add background comments and notes about the procedure.
- Folder Specify where it should be saved


Click 'Create'

You are taken to the procedure configuration screen:




Click 'Edit' to modify the basic settings:






- Default Alert You can view the settings of the default alert in 'Configuration Templates' > 'Alerts'. You can
 create custom alert settings if required from this interface. Make sure the alert is active to receive
 notifications.
- Click 'Save' to apply your settings.
- Click the 'View Procedure' tab followed by 'Edit' to define a Python script for your procedure. The built-in text editor lets you to compose your script:



- You can include variables whose values are populated when the procedure runs:
 - Click the 'View Procedure' tab followed by 'Edit'
 - In the text editor, type the parameter name and enter the value as itsm.getParameter('parameter name'). Examples:
 - Age = itsm.getParameter('age')



- Year = itsm.getParameter('year')
- The variables will become available in the 'Parameters' tab. You can define the type, label and default values for them. An example is shown below:



Configure the following for each parameter:

- Type Choose the category of variable. The supported types are:
 - Integer
 - Double
 - String
 - List
- **EM Label** Enter a name for the variable.
- Default Value Enter a value for the parameter to be taken when no value is input during run-time
- Click 'Save' to save the script.




- After saving your script you need to approve it before it can be deployed in a profile.
- You can create a schedule for a procedure when you add it to a profile. See Add a Procedure to a Profile / Procedure Schedules for more details.
- The execution log will get populated after the procedure has successfully run on end-points. You can view
 the history of execution of this procedure at anytime by selecting this procedure from the Procedures
 interface and clicking the 'Execution Log' tab.
- Note 1. ITarian runs a free script library at https://scripts.itarian.com/ which contains Python scripts covering a wide range of tasks. Feel free to try any script that fits your needs. You can also use this site to request a new script for a particular task you think will be useful. You can contribute your own scripts to the MSP forum at https://forum.itarian.com/forum/script-library
- Note 2. You can also use the Import and Clone features if you wish to create a new procedure using an
 existing procedure as a starting point

Create a custom Windows patch procedure

Windows only.


Click 'Configuration Templates' > 'Procedures' > 'Create' > 'Create Patch Procedure'



- Enter a name and description and specify the folder where it should be saved. If required, you can create new sub-folders under 'My Procedures' in the 'Procedures' area.
- Click 'Create' to open the configuration screen:


Procedure Configuration






• To configure patch options for your procedure, click the 'Execution Options' tab followed by the 'Edit' button. You can select the Microsoft software updates required for the procedure from the options.





- Click the link 'Read the definitions from Microsoft website' link to view patch details.
- · Choose which types of patch the procedure should install and click 'Save'
- Click the 'Restart Control' tab followed by the 'Edit' button to configure restart options for the endpoint after the procedure has run successfully.






- You can choose to:
 - Continue the operation of the endpoint without restart by selecting 'Suppress the reboot'
 - Force restart the endpoint a certain period of time after the procedure has completed.
 OR
 - Display a warning to the user and let them postpone the restart. Type a message for the user if you choose this option.
- The 'Schedule' tab will be auto-populated once you add the procedure to a configuration profile and schedule its execution. See Add a Procedure to a Profile / Procedure Schedules for more details.
- The 'Execution Log' will be auto-populated after the procedure has been successful executed as part of a profile. You can view a history of executions at anytime by selecting this procedure in the 'Procedures' interface and clicking the 'Execution Log' tab.
- After saving, your patch procedure will be automatically approved, added to the 'Procedures' list and can be deployed in a profile.

Important Note: Patches that are hidden by administrators will not be executed. See ' Manage OS Patches on Windows Endpoints' for more details.




Create a custom 3rd party patch procedure


Click 'Configuration Templates' > 'Procedures' > 'Create' > 'Create Windows 3rd Party Patch Procedure'



- Enter a name and description for your procedure and specify the folder in which you want to save it.
- Click 'Create' to open the procedure configuration screen:




• To configure patch options for your procedure, click the 'Execution Options' tab followed by the 'Edit' button. You can select the applications to be updated from the options.




- Select 3rd party software to update Allows you to choose whether all upgradable applications identified at the endpoint to be updated or only specific application(s) is/are to be updated.
 - Update all applications Select this option if you want all outdated applications in the endpoint to be updated on running the procedure
 - **Update only the selected applications** Select this option if you want only specified applications are to be updated on the endpoint, then specify the applications to be updated.



- Start entering the first few characters of the application. The upgradable applications identified from all managed endpoints and matching the search criteria will be displayed as options
- Select the application from the list



- Click 'Save'
- Click the 'Restart Control' tab followed by the 'Edit' button to configure restart options for the endpoint after the procedure has run successfully.



- You can choose to:
 - · Continue the operation of the endpoint without restart by selecting 'Suppress the reboot'




- Force restart the endpoint a certain period of time after the procedure has completed.
 OR
- Display a warning to the user and let them postpone the restart. Type a message for the user if you choose this option.
- The 'Schedule' tab will be auto-populated once you add the procedure to a configuration profile and schedule its execution. See Add a Procedure to a Profile / Procedure Schedules for more details.
- The 'Execution Log' will be auto-populated after the procedure has been successful executed as part of a
 profile. You can view a history of executions at anytime by selecting this procedure in the 'Procedures'
 interface and clicking the 'Execution Log' tab.
- After saving, your patch procedure will be automatically approved, added to the 'Procedures' list and can be deployed in a profile.

6.6.3. Combine Procedures to Build Broader Procedures

Note - this section only applies to script procedures, not patch procedures.

- Open your custom procedure and click the 'View Procedure' tab
- · Click 'Edit' on the right
- Place your mouse at the point in your script where you want to add the new code
- Click 'Add Existing Procedure'
- Type the name of the procedure you want to import
- Click 'Add'. The code will be added to your existing script at the place you specified.
- You can, of course, subsequently modify the script as required.



Click 'Save' for your changes to take effect.



6.6.4. Review / Approve / Decline New Procedures

The process to review / approve / decline new Windows and Mac procedures are same.

- New custom script procedures are given an initial status of 'Created'.
- Custom script procedures must be approved before they can be added to a profile.
- Custom patch procedures do not require approval.


The review/approval process:

- Script writer -
 - Go to 'Configuration Templates' > 'Procedures' and create a new script procedure.
 - Save the procedure in 'My Procedures' (or a sub-folder).
 - The procedure will have a status of 'Created'.
 - Click the name of the new procedure to open its configuration screen.
 - Click the 'Ready to Review' button
- Approver -
 - · Receives a notification that a procedure requires approval
 - Go to 'Configuration Templates' > 'Procedures'. Open the procedure details page.
 - Click 'Approve' to commit the script and make it available for selection in profiles.
 - Click 'Decline' to reject the script.

Notes:

- The writer and approver in the example above can be the same person.
- The permissions required to approve a procedure are:
- 'manage.procedures' and 'manage.procedures.manage'
 - · Both these permissions are enabled in the 'Admin' and 'Technician' roles
 - Make sure these permissions are enabled in a custom role if its members are to approve procedures





Approved procedures can be selected and added to a profile.

ITarian Endpoint Manager - Administrator Guide




6.6.5. Add a Procedure to a Profile / Procedure Schedules

FYI. Procedure schedules are configured in the 'Profiles' area. You create the schedule when you add the procedure to the profile. The 'Schedule' tab in the procedures area just shows you which profiles are using the procedure.


- Click 'Configuration Templates' > 'Profiles'
- Click the profile to which you want to add a procedure
- Click 'Add Profile Section' > 'Procedures'





- This adds a 'Procedures' tab to the profile.
- Click the 'Add button' to open the procedure configuration screen






- Procedure Name Type the name of the procedure that you want to add to the profile (make sure you
 have approved the procedure)
- Schedule Settings Create a custom schedule, or add it to an existing maintenance window
 - **Custom schedule** Choose the start date, start time and frequency of the schedule.
 - Maintenance window A maintenance window is a set time-slot reserved for running procedures.
 - Choose the window type from 'Daily', 'Weekly', 'Monthly', or 'Week of month'.
 - You will see a list of available windows of that type. Choose the window in which you want the schedule to run.
 - Click 'Add Profile Section' > 'Maintenance Window' in a profile if you want to define a new window.
- Run as Local System User / Run as Logged in user Choose the user account under which the procedure should run. This option is not available for patch procedures.
- Run this procedure immediately when the profile is assigned to a new device The procedure is executed instantly on devices which use the profile. Thereafter it will run as per scheduled.
- Skip procedure if the device is offline The procedure is not executed on devices that are not connected to EM




- Send the resulting logs by email Script procedures only.
 - Send to current user Procedure results are sent to the admin who is currently logged into Endpoint Manager.
 - Send to the following email addresses Add email addresses to whom log results should be sent.
- **Configure parameters** Specify values for script variables. This is only available for scripts that have variables associated with them:




Each variable is pre-populated with its default value

- You can change these variables as required, or leave it at use default value.
- · Click 'Apply'.
- · Click 'Add'.
- Finally, click 'Save' to apply the procedure and the schedule to the profile:



• The 'Schedule' tab of the procedure interface lists all profiles which have this procedure scheduled:





Important Note: Patches that are hidden by administrators will not be executed. See **Manage OS Patches on Windows Endpoints** for more details.


6.6.6. Import / Export / Clone Procedures

Endpoint Manager allows you to export or import procedures in order to use them in profiles. The procedure files are saved in .json format. You can also clone a procedure and use it as a starting point to create a new procedure according to your requirements. Click the following links to find out more:

- Export a procedure
- Import a procedure
- Clone a procedure

Export a procedure

- Click 'Configuration Templates' > 'Procedures'
- Navigate to the folder containing the procedure to be exported
- Select the procedure and click 'Export' at the top. Please note you can export only custom procedures.




The selected procedure file will be saved in your default download location.


Import a procedure



- Click 'Configuration Templates' > 'Procedures'
- · Click 'Import' at the top



• Click 'Browse', navigate to the location where the procedure file is saved and click 'Open' The selected file will be displayed on the 'Import Procedure' dialog.




· Click 'Import'

The procedure is imported and placed in the 'My Procedures' folder. The procedure name is prefixed with "Imported" to distinguish it from other procedures.

You can save the procedure in a different folder by editing it. See Edit / Delete Procedures for guidance on this.

ITarian Endpoint Manager - Administrator Guide






Please note you have to **approve** the imported procedure in order to deploy it in profiles. To change the name and/or edit the script, click on the procedure and then click 'Edit' button on the right. Refer to the section 'Edit / Delete Procedures' for more details.

Clone a procedure

- Click 'Configuration Templates' > 'Procedures'
- Navigate to the folder containing the procedure to be cloned
- Select the procedure and click 'Clone' at the top.






- Change the name, if required, and provide an appropriate description of the profile
- · Select the folder in which the cloned procedure is to be placed
- Click 'Clone'

The procedure will be added to the list:





Please note the status of the cloned procedure will be same as that of the procedure that was cloned. For example, if the status was approved then the cloned procedure will also be of the same status.


6.6.7. Change Alert Settings

Endpoint Manager is capable of issuing alerts when procedures fail to execute as intended. You can set the type of alert shown while you are creating a new procedure, or by editing an existing procedure. Please note you can only select alerts that are already created in the 'Alerts' interface ('Configuration Templates' > 'Alerts'). See 'Manage Alerts' for more details.

Change alert settings

- Click 'Configuration Templates' > 'Procedures'
- Navigate to the folder containing the procedure to be configured for alert
- Click the name of the procedure to open its details interface and select the 'General' tab.
- · Click 'Edit' on the top right





- Make sure the 'Use alert settings when the procedure fails' check box is selected and the alert is active to receive notifications.
- The current alert name is displayed in the 'Use alert settings when the procedure fails' field.
- Start typing the name of the alert in the field and choose the alert to be used, from the options.
- Click 'Save' at the top right.

6.6.8. Apply Procedures to Devices

- 1. Procedures area Click 'Configuration Templates' > 'Procedures' > select a procedure > Click 'Run'
- 2. **Device list** Click 'Devices' > 'Device List' > select target devices > Click 'Run Procedure'
- 3. Schedule in a profile Click 'Configuration Templates' > 'Profiles' > click on a profile name > Click 'Add Profile Section' > 'Procedures'
- 4. On users Click 'Users' > 'User List' > select target users > Click 'Run Procedure'
- 5. On user groups Click 'Users' > 'User Group' > select target groups > Click 'Run Procedure'
- On customer groups Click 'Devices' > 'Device List' > select customer groups in the middle column >
 Click 'Run Procedure'


The following section describes 1), how to apply procedures from the procedures interface. Note - EM does not support patch procedures on Mac devices.



For Windows devices, make sure patch management setting is disabled to execute patches.

Run a procedure

- Click 'Configuration Templates' > 'Procedures'
- Browse the folder tree to locate the procedure you want to run
- Select the procedure and click 'Run' at the top. Note only **approved** procedures can be applied. You can also run only one procedure at a time.



Choose the execution options from the 'Run Procedure' dialog

- All Devices The procedure is applied to every device which matches its target operating system.
- Selected Device(s) Type the name of a device and select it from the list. You can add multiple devices in the field.




Run Procedure	×
Run procedure «Finance Dept Script» over:	
All devices Selected device(s)	
Type device name to search among devices	
☐ Send the resulting logs by email ☐ Send to the current user ☐ Send to the following email addresses Add emails	
Run as LocalSystem User Run as Logged in User	
Please check the status for the devices are not in the maintenance window Total number of devices outside of maintenance window 1	
Number of devices blocked by maintenance window settings 0	
Number of devices warned by maintenance window settings 1	
Skip devices warned by maintenance windows settings	
In order to check maintenance window status, go to related profile maintenance window section	OW
Configure parameters R	un



- Send the resulting logs by email Script procedures only.
 - Send to current user Procedure results are sent to the admin who is currently logged into Endpoint Manager.
 - Send to the following email addresses Add email addresses to whom log results should be sent.
- Run as Local System User / Run as Logged in user Choose the user account with which the procedure has to be run on the devices based on the access rights required for the procedure. Please note this option will not be available for a patch procedure.
- Maintenance window status Details of any maintenance windows in the device's profile.
 - Total number of devices outside of maintenance window The number of devices that are not part of a maintenance window. The procedure can run on these devices.
 - Number of devices blocked by maintenance windows settings The number of devices on which you cannot run the procedure because the admin has blocked procedures outside the maintenance window.
 - Number of devices warned by maintenance window settings The number of devices that
 are part of a maintenance window and have warnings enabled. You can still run the procedure
 on these devices.
 - Skip devices warned by maintenance windows settings A maintenance window is a
 time-slot reserved for running important tasks on target devices. Admins can enable a
 warning if somebody attempts to run a procedure outside of the window. This setting will
 skip those devices which have been added to a maintenance window with warnings
 enabled.
- **Configure parameters** Available only for script procedures defined with variable parameters and allows you to enter the values for them.

To specify values for variable parameters

· Click 'Configure Parameters'



ITarian Endpoint Manager - Administrator Guide



The list of variable parameters will appear with their default values pre-populated in their respective text fields

- Enter the value for each parameter in the respective text box
- Select 'Use default value' if you want the default value to be applied for a parameter,
- Click 'Apply'

Tip: You can skip this step If you want to use default values for all parameters. For more info on default values, see **Create a Custom Procedure**.

Click the 'Run' button in the 'Run Procedure' dialog.

The procedure is applied to the selected devices. A confirmation dialog is displayed and the process is logged. You can view the details in the **Procedure Logs** screen for script procedures. **Patch procedure logs** will be available in the respective patch procedure itself.

Important Note: Patches that are hidden by administrators will not be executed. See **Manage OS Patches on Windows Endpoints** for more details.

6.6.9. Edit / Delete Procedures


Custom procedures can be edited or deleted according to your requirements. Please note that if you edit a script procedure, it has to be **approved** again. Predefined procedures cannot be edited or deleted. Click the following links for more details:

- Edit / delete a script procedure
- Edit / delete a patch procedure

Edit a Script Procedure

- Click 'Configuration Templates' > 'Procedures'
- · Browse the folder tree to locate the procedure you want to edit
- Click on the script procedure to open its details interface
- Select a tab and click 'Edit' to modify its details





General

Modify the procedure name, description, the folder in which the procedure is saved and / or alert settings

View Procedure

· Modify the script and / or add another existing procedure

Execution Log

 Displays the results of the script procedure that was executed, both manually and scheduled on Windows profiles.


Schedule

The schedule can be edited only in the profile(s) that the procedure is deployed.

• Click the 'Schedule' tab to view the profile(s) in which the procedure is being used.

ITarian Endpoint Manager - Administrator Guide






• Click the profile for which you want to edit the procedure schedule.

The selected profile is displayed with the 'Procedure' tab opened.

Click 'Edit' at the top right.






You can find the procedure type, whether script or patch, under the 'Type' column.

- Click the schedule parameter under 'Schedule' column beside the procedure.
- The 'Procedure Schedule' dialog will be displayed. Modify the schedule per your requirement and click 'Set'.
- The schedule will be modified for the profile. Please note the procedure schedule will impact only the profile that you modify. The schedule for the same procedure deployed onto other profiles will not be affected.




Click 'Save'

The changes for the procedure will be saved. The following image shows the same procedure having different schedule for different profiles.



To delete a script procedure

- Click 'Configuration Templates' > 'Procedures'
- · Browse the folder tree to locate the procedure you want to edit
- Select the check box beside the procedure and click 'Delete Procedure' at the top.
- Alternatively, click on the procedure that you want to delete and click 'Delete' on the top right




• Click 'Confirm'. The procedure is removed from the list as well as from the profiles on which it is deployed.

Edit a patch procedure

- Click 'Configuration Templates' > 'Procedures'
- · Browse the folder tree to locate the procedure you want to edit



- Click on the patch procedure to open its details interface
- · Select a tab and click 'Edit' to modify its details



General

 Modify the procedure name, description, the folder in which the procedure is saved and / or alert settings


Execution Options

- Modify the patch options. See the explanation of Procedure Configuration in Create a Custom Procedure for help on configuring the execution settings.
- Click 'Save' when done



Restart Control

Modify the restart options for the endpoint after the procedure has run successfully.



- See the explanation of Procedure Configuration in Create a Custom Procedure for help on configuring the restart control settings.
- Click 'Save' when done

Execution Log

 Displays the results of the patch procedure that was executed, both manually and scheduled on Windows profiles.


Schedule

The schedule can be edited only in the profile(s) that the procedure is deployed.

• Click the 'Schedule' tab to view the profile(s) in which the procedure is being used.

ITarian Endpoint Manager - Administrator Guide






• Click the profile for which you want to edit the procedure schedule.

The selected profile is displayed with the 'Procedure' tab opened.

· Click 'Edit' at the top right.





You can find the procedure type, whether script or patch, under the 'Type' column.

- Click the schedule parameter under 'Schedule' column beside the patch procedure.
- The 'Procedure Schedule' dialog will be displayed. Modify the schedule per your requirement and click 'Set'.
- The schedule will be modified for the profile. Please note the procedure schedule will be impacted for only
 the profile that you modify. The schedule for the same procedure deployed onto other profiles will not be
 affected.
- · Click 'Save'

The changes for the patch procedure will be saved.

Important Note: Patches that are hidden by administrators will not be executed. See **Manage OS Patches on Windows Endpoints** for more details.



6.6.10. View Procedure Results

The results of any script or patch procedure can be viewed in the 'Logs' section of a device. The results can also be found in the 'Procedures' interface.

Click the following links for more details:

- Script procedure results
- · Patch procedure results

Script Procedure Results

There are two places you can view script results:

- 1 Device List
 - Windows Click 'Devices' > 'Device List' > open a Windows device > 'Logs' > 'Script Logs'
 - Mac Click 'Devices' > 'Device List' > open a Mac device > 'Logs' > 'Procedure Logs'
- 2 Procedures area Click 'Configuration Templates' > 'Procedures' > open a script procedure > 'Execution Log' Shows all devices on which a selected script was run.

1) Script results on a particular device


- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows / Mac device then select the 'Logs' tab in the device details interface
- Select the 'Script Logs' sub-tab for Windows or the 'Procedure Logs' sub-tab for Mac

This opens the list of all script procedures run on the device. You can also see the scripts start/end time and whether or not it was successful.

The script procedure results screen are same for Windows and Mac devices. Windows script procedure result is explained below.

• To view the results of a particular procedure, click 'Details' in the row of the procedure name.






The 'Tickets' tab lists tickets which were created as a result of a failed procedure. Clicking the ticket link will
open the ticket in service desk.

2) Results of a script on all devices

- Click 'Configuration Templates' > 'Procedures'.
- Browse the folder tree to locate the procedure for which you want to view results
- Click the name of the script procedure then click 'Execution Log'
- This will open a list of all devices on which the script was run





Script Procedure Logs - Table of Column Descriptions		
Column Heading	Description	
Device Name	The label of the device on which the script procedure was run. • Click the device name to open the device details interface of the respective device.	
Started At	The date and time when the procedure commenced on the device.	
Started By	 Who or what launched the procedure. A profile name will be shown here if the procedure was scheduled in a profile which is active on the device. An admins name or email address will be shown if the procedure was run manually. Click the name/email address to view the details of the admin. 	
Launch Type	Whether the procedure was scheduled or run manually.	
Executed By	The user account type used by Endpoint Manager to execute the procedure.	
Finished At	The date and time when the procedure was completed.	
Status	Whether the script successfully executed or not. Each status is color coded: • Started - Blue • In progress - Blue	




	Finished Success - Green
	Failed - Red
	You can configure an alert if a procedure deployment fails. See 'Manage Procedures' for more details.
Last Status Update	The date and time when the information was last updated.
Details	Click the 'Details' link to view a log of the procedure's execution.
	 See the explanation of View results of script procedure execution on a device given below.

- Click the funnel icon \mathbf{Y} on the right to search by various parameters
- To display all the items again, remove / deselect the search key from filter and click 'OK'.

Export script procedure execution records as a CSV file

- Click 'Configuration Templates' > 'Procedures' > click on a script procedure
- Click the 'Execution Log' sub-tab
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button and choose 'Export to CSV':



The report is generated in .csv file format.


Report has been created. Please check «Reports» at the Dashboard

Click 'Dashboard' > 'Reports' to view the report. See Reports if you need more help with this interface.

View results of script procedure execution on a device

• Click 'Details' in the row of a device to view specific results:





The details are shown under two tabs:

• Statuses - The date and time at which successive stages in the procedure were run, their success status and results.

For example, the 'Get Running Processes' results show a list of all processes found running on the device.

- Tickets Shows tickets raised for any failed procedures.
 - Click the ticket link to open the ticket in service desk.

Patch Procedure Results

There are two places you can view patch procedure results:

- 1. **Device List** Click 'Devices' > 'Device List' > *Open a Windows device* > 'Logs' > 'Patch Logs' Displays results for all patch procedures run on a selected device.
- 2. **Procedures area** Click 'Configuration Templates' > 'Procedures' > *Open a patch procedure* > 'Execution Log' Displays all devices on which the selected patch procedure was run.


1) Patch procedure results on a specific device

- Click 'Devices' > 'Device List'
- Click the 'Device Management' tab in the top-menu
 - Select a company or a group to view just their devices
 Or
 - Select 'Show all' to view every device enrolled to EM
- Click on any Windows device then select the 'Logs' tab in the device details interface
- Select the 'Patch Logs' sub-tab

This opens a list of all patch procedures run on the device along with their status (success/failure), their start/finish time and time of last status update.



Click 'Details' in the row of a procedure to view specific results:




• The 'Tickets' tab shows tickets which were created as a result of a failed procedure. Click the ticket link to open the ticket in service desk.

2) Results of a selected patch procedure run on all devices



- Click 'Configuration Templates' > 'Procedures'.
- Click the name of the patch procedure under 'My Procedures' or 'Predefined Procedures' for which you want to view results, then click 'Execution Log' in the Procedure Details screen.
- This will open a list of all devices on which the script procedure was run along with their status (success/failure), their start/finish time and time of last status update.
- Click 'Details' in the row of a device to view specific results:



The 'Tickets' tab displays a list of tickets which were created as a result of a failed procedure. Clicking the
ticket link will open the ticket in service desk.



• Note - Sorting, filtering and exporting is similar to that for script procedure results explained above.


6.7. Manage Monitors

Click 'Configuration Templates' > 'Monitors'

- A monitor is a script which tracks events on managed Windows and Mac OS devices. You can instruct the
 monitor to take specific actions if its conditions are met.
- For example, 'Alert me when a removable disk is connected to the system', or 'Create a log entry if CPU usage goes above 75% for a certain length of time'.
- You can also tell a monitor to run a procedure to remediate issues.
- Monitors are added to configuration profiles which are in-turn applied to a devices. To add a monitor to a profile:
 - Click 'Configuration Templates' > 'Profiles'
 - Open an existing profile or create a new profile
 - Click 'Add Profile Section' > 'Monitoring'
- A single monitor can be used in multiple profiles. A single profile can include any number of monitors. You can clone an existing monitor to create a new one.
- There are two types of monitors:
 - **Predefined Monitors** A collection of monitors from Comodo which perform a range of useful monitoring tasks. These can be used in custom profiles, but cannot be edited.
 - **My Monitors** Custom monitors that you create. These monitors are saved in the 'My Monitors' folder. You can create sub-folders as required.

View and manage monitors

Click 'Configuration Templates' > 'Monitors'



Column Heading	Description
OS	The operating system that the monitor supports.

ITarian Endpoint Manager - Administrator Guide



Monitor Name	The monitor label.		
	 Click the name of a monitor view and edit it. See View and Edit Monitors for more details. 		
Туре	Whether the monitor is custom or predefined		
Number of profiles	The quantity of profiles on which the monitor is active.		
Created by	The administrator who created the custom monitor.		
	 Click the admin name to view their details. See View User Details if you need help with this. 		
Created On	Date and time the monitor was created.		
Last Modified By	The admin who most recently edited the monitor.		
Updated On	Date and time the monitor was last edited.		
Controls			
Create Monitor	Configure a new monitor. See 'Create Monitors and Add them to Profiles' for help with this.		
Clone Monitor	Create a new monitor using an existing one		
Delete Monitor	Remove monitors from Endpoint Manager. Use the check-boxes to select the monitors to be removed.		


- Click any column header to sort the items in ascending/descending order of entries in that column.
- · Click the funnel icon on the right to search for monitors

Next, see Create a monitor and add it to a profile


Add a sub folder to the 'My Monitors' folder

- Click 'Configuration Templates' > 'Monitors'
- Place your mouse on the 'My Monitors' folder and click '+' beside it





• Enter a name for the sub-folder to be created in the 'Add Folder' dialog and click 'Add' The sub-folder will be created and displayed under 'My Monitors'




You can also add sub-folders of a sub-folder. Once sub folders are created, you can create new monitors inside them. See **Create Monitors and Add them to Profiles** for more details about adding new monitors.

Edit the name of a sub folder under 'My Monitors'

Click 'Configuration Templates' > 'Monitors'



- Expand the 'My Monitors' folder (or the parent folder of the sub-folder)
- · Place your mouse on the sub folder and click the pencil symbol beside it
- Enter a new name for the sub folder in the 'Edit Folder' dialog and click 'Save'




The folder name will be updated in folder tree.

Remove a sub folder under 'My Monitors' folder

- Click 'Configuration Templates' > 'Monitors'
- Expand the 'My Monitors' folder (or the parent folder of the sub-folder)
- Place your mouse on the sub folder and click the trash can symbol beside it





Click 'Confirm' to remove the folder.

Note: You can only remove empty folders. Delete all monitors in a folder before attempting to delete the folder.

Following sections explain more about:

- Create Monitors and Add them to Profiles
- View and Edit Monitors

6.7.1. Create Monitors and Add them to Profiles

Custom monitors let you track and respond to events of your choice. For example, you may create a monitor to alert you if disk space on a device falls below 10%.

- You can set a monitor to run a specific procedure if its conditions are met. For example, you could run a
 disk-defrag procedure when free space falls below a set threshold. (Windows only)
- You can also configure custom notifications by modifying the alert template on the procedure. Click 'Configuration Templates' > 'Alerts' to view alert templates.

Monitors are added to security profiles which, in-turn, are deployed to devices. You need to add a 'Monitors' section to a profile to add your monitor.


See the following sections for help with creating OS-specific monitors:

- Monitors for Windows Devices
- Monitors for Mac OS Devices




6.7.1.1. Monitors for Windows Devices

- Click 'Configuration Templates' > 'Monitors'
- · Click 'Create Monitor'



- Enter a label and description for the monitor
- Select 'Windows' in the OS drop-down
- Specify where to save the new monitor. You can create new sub-folders under 'My Monitors' if required.
- Click 'Create' to open the monitor configuration screen:





Modify the following settings if required:

- **Trigger an alert if** Select when the alert should be sent to admins. The options are send alert when all conditions are met or when any condition is met.
- Use Alert Settings Choose the alert template you want to use if the conditions of this monitor are met.
 - Alert templates are collections of settings which govern alert recipients and additional options.
 - For example, you can create a Service Desk ticket from the alert, and choose whether or not you
 want to see the alert in the portal.
 - You can create different alert templates for different situations.
 - Click 'Configuration Templates' > 'Alerts' to view and manage alert templates. Make sure the alert
 is active to receive notifications. See Manage Alerts if you need help.
- Auto Remediation on alert Choose how you want to respond to the alert:
 - Taken no action No automatic response is made to the alert. You can, of course, manually run a
 procedure in response to the alert.
 - Run below procedure Select a procedure to run on affected endpoints in response to the alert. The
 procedures listed here are defined in the Procedures interface. Type the first few characters of the
 procedure and select from the list.


Click 'Save'.

ITarian Endpoint Manager - Administrator Guide



- · Click the 'Conditions' tab followed by 'Edit' to define monitor thresholds
- · Click 'Add Condition'

<new image>



• Choose the parameter you want to monitor:

	Available Monitors
Performance	Checks CPU, RAM and network usage and triggers an alert if certain conditions are met.
File Size	Checks the disk space used by a specific file. Triggers an alert if the file size is less or more than a specific size.
Folder Size	Checks the disk space used by a directory. Triggers an alert if the folder size is less or more than a specific size.
Disk	Checks free disk space, or for large changes to free disk space in short periods. Trigger an alert if disk space falls below a certain level, or if there are large alterations to disk space in a short time period.
Service	Checks whether or not a named service is running. Triggers an alert if the condition is met.
Process	Checks whether or not a named process is running. Triggers an alert if the condition is met.
Event	Checks if a specific event occurs and alerts you accordingly. The condition monitors Windows event logs. You must specify the event ID, the criticality of the event, and the source of the event.



TCP	Checks whether a specific port is open or closed and alerts you accordingly. This is useful for important ports that need to remain open/closed for operational reasons.		
	You need to specify the host name/ IP of the target port, the port number, the polling interval (in seconds), and whether you want to test for an open or closed state.		
Ping	Checks whether a host is online or not. You need to specify the host name, the polling interval (in seconds), and whether you want to test for an online or offline status.		
Web Page	Checks whether specific content is present or not present on a webpage. You need to specify the URL, the content you want to search for, the polling interval (in minutes), and the present/not present status. You are alerted if the condition is met.		
Device Status	Checks every managed device to see whether it has been online or offline for a certain length of time. You will receive an alert if the device has been offline/online for the length of time you specify.		
	Background. Every minute, managed devices send a message to Endpoint Manager to signal they are online. If EM does not receive this signal for three minutes straight then the device status is set to 'Offline'. This condition will alert you if a device has been continuously 'Offline' (or 'Online') for the total length of time you specify.		
Custom Script	Create a python script to monitor for your own set of conditions. Paste your script in the space provided. See Add Custom Monitoring Conditions if you need help with this.		
Security Events	Checks for significant security related events on the managed endpoint. Example events monitored are: • Malware detected and handled • Malware detected and not handled • Unknown application is placed in the container • An external device was blocked by device control You can receive an alert when the condition is met, or automatically run a procedure.		
Security Client Events	Alerts you when there are errors with Comodo Client Security (CCS). CCS is the endpoint application which provides the antivirus, firewall and containment services. This monitor checks for any failure in those processes, including: • Antivirus scan failed or interrupted • Antivirus database update failed • Antivirus scan interrupted • Another antivirus is installed You can receive an alert when the condition is met, or automatically run a procedure.		
OS Patches Event	Alerts you on events when various types of Windows patches are installed. You can monitor the installation of:		




	UpdatesSecurity updates	
Disk Utilization	Checks disk utilization performance. Triggers an alert if the performance matches the defined parameters.	
Free space left on any disk	Checks disk space available in any disk. Triggers an alert if the available free disk space matches the defined parameters.	

Define the specifics of the condition. The type of information you need to provide depends on the condition.
 For example, if you select 'Disk' monitor, you have the option to specify conditions for three values. See the example image below.



Repeat the process to add more parameters and monitoring conditions.



- To remove a monitoring condition, select the check box beside it and click 'Remove Condition' at the top.
- Click 'Save' to apply your changes.

Add Custom Monitoring Conditions




- Endpoint Manager allows you to create custom monitoring conditions per your business requirements.
- You can create custom scripts in python and can define which items should be monitored. You can also
 define the threshold before an alert is generated.
- You can use custom script with parameters when creating a monitor
- Predefined script monitors are available in 'Configuration Templates' > 'Procedures' > 'Predefined Procedures' > 'Monitors'. These are available for selection in the 'Add Existing Procedure' > 'Procedure name' drop-down.

Add a custom script to the monitoring conditions

Choose 'Custom script' from the 'Add Condition' drop-down

The 'Add Condition for Custom Script' form will appear.



Add Condition for Custom Script - Table of Parameters	
Form Element	Description
Name	Enter a label for the script, shortly describing its purpose.



	Add Condition for Custom Script - Table of Parameters
Description	Enter a short description for the script.
Check Period	Enter the time interval at which the script should be run on the endpoints to which the profile is applied.
	Tip : Ensure that the check period is greater than the time taken for the script to run and complete, so that successive executions of the script do not overlap.
Trigger monitoring alert if custom script failed	Select this if you want to generate a warning notice if the custom script did not run successfully.
Script	Enter your Python script in the text editor.
	Note 1: Keep the following lines intact in the editor and enter your script below these: import os import sys
	import _winreg
	<pre>def alert(arg):</pre>
	sys.stderr.write("%d%d%d" % (arg, arg, arg))
	<pre># Please use "alert(1)" to turn on the monitor(trigger an alert)</pre>
	<pre># Please use "alert(0)" to turn off the monitor(disable an alert)</pre>
	# Please do not change above block and write your script below
	Note 2: If you want an alert to be triggered if the condition is met set the argument to alert parameter to 1, i.e. 'alert(1)'.
	If you do not want an alert to be triggered even if the condition is met set the argument to alert parameter to 0, i.e. 'alert(0)'.
	Note 3: You can import an existing script procedure in EM if you wish to create a new custom monitor script using an existing procedure as a starting point. To do so, click 'Add Existing Procedure' and choose the existing procedure. Edit the script as per your requirement as per Note 1. For more details on procedures, See Manage Procedures.
	Note 4: In addition to the above, Python script monitors by the Comodo development team are available in the 'Monitors' folder under 'Configuration Templates' > 'Procedures' > 'Predefined Procedures'. You can add these predefined scripts by clicking 'Add Existing Procedure' and select from the 'Procedure name' drop-down and can be used directly without any changes. Feel free to try any script that fits your needs. If you require custom scripts from Comodo, please raise a request at https://c1forum.comodo.com/forum/script-library/4460-script-requests-comodo-will-write-the-scripts-for-you-for-free

• Complete the form and click 'Create'

The custom monitor will be added to the list of monitors under the 'Monitors' tab.

Add parameters to custom scripts

You can add parameter types such as integer, list, unicode and float to your custom script in the monitor condition form.




- Click 'Configuration Templates' > 'Monitors'
- Click 'Create Monitors'
- Complete the form as explained above.
- Click 'Add Condition' and select 'Custom script'
 - See 'Add Custom Monitoring Conditions' explained above.
- Scroll down to the script area and enter the following code:
 name=itsm.getParameter('parameterName')



Click 'Create'

Custom script parameters dialog box appears:



- Type Select the parameter type from the drop-down. Available types are:
 - Integer
 - Float
 - Unicode




- List
- · Value Enter appropriate parameter value.
- · Click 'Save'

The monitor will be available for selection under 'Add Monitor' when configuring the 'Monitors' section of a Windows profile. For more details on adding a monitor to a profile, see **Monitors** in **Create Windows Profiles**.

6.7.1.2. Monitors for Mac OS Devices


- Click 'Configuration Templates' > 'Monitors'
- · Click 'Create Monitor'



- Enter a label and description for the monitor
- Select 'macOS' in the OS drop-down
- Specify where to save the new monitor. You can create new sub-folders under 'My Monitors' if required.
- Click 'Create'.



• You will be taken to the monitor configuration screen:



Modify the following settings if required:


- **Trigger an alert if** Select when the alert should be sent to admins. The options are send alert when all conditions are met or when any condition is met.
- **Use Alert Settings** Select the alert that should be generated. The alert types listed here are defined in the 'Alerts' section. Make sure the **alert is active** to receive notifications. See 'Manage Alerts' for more details.

Click 'Save'

- · Click the 'Conditions' tab followed by 'Edit' to define monitor thresholds
- · Click 'Add Condition'

ITarian Endpoint Manager - Administrator Guide






· Choose the parameter you want to monitor


	Available Monitors
Performance	Checks CPU, RAM and network usage and triggers an alert if certain conditions are met.
	You can specify thresholds for these parameters and the length of time the threshold can be continuously exceeded, before triggering an alert.
Disk	Checks free disk space, or for large changes to free disk space in short periods.
	 Triggers an alert if disk space falls below a certain level, or if there are large alterations to disk space in a short time period.
Process	Checks whether or not a named process is running.
	Triggers an alert if the condition is met.
Device Status	Checks every managed device to see whether it has been online or offline for a certain length of time. You will receive an alert if the device has been offline/online for the length of time you specify.
	Background. Every minute, managed devices send a message to Endpoint Manager to signal they are online. If EM does not receive this signal for three minutes straight then the device status is set to 'Offline'. This condition will alert you if a device has been continuously 'Offline' (or 'Online') for the total length of time you specify.

Define the specifics of the condition. The type of information you need to provide depends on the condition.
 For example, if you select 'Disk' monitor, you have the option to specify conditions for three values. See the example image below.





- Click 'Create' after specifying the conditions.
- Repeat the process to add more conditions



- To remove a monitoring condition, select the check box beside it and click 'Remove Condition' at the top.
- · Click 'Save' to apply your changes.


6.7.2. View and Edit Monitors

- You can view the details of predefined and custom monitors, but you can only edit custom monitors.
- You can also view profiles in which a monitor is active, and events generated by the monitor.

View details of a monitor

- Click 'Configuration Templates' > 'Monitors'
- · Click the name of a monitor to open its configuration interface






The configuration interface allows you to:

- Edit general settings and monitoring conditions
- View all profiles which use a particular monitor
- View the log of events related to the monitor. from all devices on which profiles with the monitor is applied

Edit a Monitor

- Click 'Configuration Templates' > 'Monitors'
- Click on the name of a monitor. The monitor configuration interface will open at the 'General' tab.
- Click the 'Edit' button to modify the details.






- General Modify the name, description, location, alert settings and more
- Editing the conditions is similar to adding conditions to a monitor. See Monitors for Windows
 Devices / Monitors for Mac OS Devices for more details.
- Click 'Save' for your changes to take effect.
- The changes are immediately implemented in all profiles which use the monitor.

View all profiles which use a particular monitor

- Click 'Configuration Templates' > 'Monitors'
- Click the name of a monitor to open its configuration interface.
- Click the 'Profiles' tab.






Monitors - Column Descriptions		
Column Heading	Description	
Profile Name	The profile in which the monitor is active.	
	 Click the profile name to open its configuration screen. See Edit Configuration Profiles for more details. 	
Owner	The administrator who created the profile.	
	 Click the name to view their user details. See View the details of the User for more details. 	

View Monitor Logs

- Click 'Configuration Templates' > 'Monitors'
- Click the name of a monitor to open its configuration interface.
- · Click the 'Logs' tab.

The 'Logs' tab shows all instances where the conditions of the monitor were breached:






Monitoring Logs - Table of Column Descriptions		
Column Heading	Description	
Device Name	The Windows device on which the violation occurred. • Click the name of the device to open its details interface. See Manage Windows Devices for more details.	
Status	Whether or not the monitor is currently active on the device.	
Hit Count	Number of times the monitored conditions were breached in the last 24 hours.	
Last Hit Time	Date and time the monitoring rule was last broken.	
Last Update Time	Date and time when the information was last refreshed.	
Details	 Click the 'Details' link to view a log of the breach events. See View Details of Monitor Logs (given below) for more information. 	

View Details of Monitor Logs

• Click the 'Details' link to view the details of the violations of the monitoring conditions:



Details are shown under three tabs:

Logs - The date and time when the event occurred. Also shows the details of the monitoring rule that detected the event.



Monitoring Log Details - 'Logs' tab - Table of Column Descriptions			
Column Heading	Description		
Time	Date and time of the event.		
Status	The current state of the monitor on the device: On - The device is exceeding the thresholds of the monitor Off - The device is operating within the thresholds of the monitor		
Additional Information	Details on the condition monitored and the breach		


Tickets - Shows any service desk tickets which were automatically generated by the alert.

DESKTOP-D80SVJJ - Log Details — Bac		
Logs Tickets Statuses		
LINK	STATUS	CREATED ON
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 04:14:15 PM
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 03:37:35 PM
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 03:32:34 PM
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 03:01:44 PM
https://freetfork.staging.servicedesk.comodo.com/scp/tickets.nbs2id_1062		2019/19/21 02:56:36 PM

Monitoring Log Details - 'Tickets' tab - Table of Column Descriptions		
Column Heading	Description	
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.	
Status	Indicates whether the ticket is open or closed	
Created On	The date and time at which the ticket was created.	



Statuses - Shows the current status of each condition in the monitor:



Column Heading	Description		
Condition Type	The category of monitor. Click the type to view its exact conditions and thresholds. An example is shown below:		
	«CPU usage» Condition ×		
	CPU usage Value During More than 5% 5 sec Note 5 sec		
	The monitor checks the computer performance metrics. If the selected parameter meets the specified condition, the monitor triggers an alert. OK		
Value	The thresholds set for the parameter.		
Status	The current state of the monitored parameter on the device. Green - The device is operating within the thresholds of the monitor Grey - Unknown Red - The device is exceeding the conditions of the monitor.		
Status Changed at	The date and time of the last change in state of the monitored parameter.		



6.8. Data Loss Prevention Rules

Click 'Configuration Templates' > 'Data Loss Prevention'


- Data loss prevention (DLP) discovery rules let you scan managed devices for files that contain sensitive information. For example, credit card numbers, social security numbers etc.
- DLP monitoring rules let you prevent sensitive information from being copied to external devices like USB data devices, block screenshots of running applications, documents and so on.
 - EM currently supports only removable storage monitoring rule. More monitoring rules in next version.
- A single rule can be used in multiple profiles. A single profile can include any number of rules.

See the following links for more help with DLP rules:

- The DLP rules area
- Create DLP discovery rules and add them to profiles
- View and edit DLP discovery rules
- Create DLP Monitoring Rules and add them to Profiles
- View and Edit DLP Monitoring Rules

The DLP rules area

Click 'Configuration Templates' > 'Data Loss Prevention'



Column Heading	Description
Rule Name	The rule label. • Click the name of a rule to view and edit it.
	Click the name of a fulle to view and edit it.
Content Type	Indicates whether it is a discovery rule or a monitoring rule.
# of profiles	The number of EM configuration profiles in which the rule is used.
Created by	The admin who added the custom rule. Click the name to view their details.
Created On	Date and time the rule was added to EM.



Last Modified By	The admin who most recently edited the rule.	
Updated On	Date and time the rule was last edited.	
Controls		
Create	Configure a new DLP rule. See Create DLP discovery rules and add them to profiles and Create DLP monitoring rules and add them to profiles for help with this.	
Delete Rule(s)	Remove rules from Endpoint Manager. Use the check-boxes to select the rules you want to remove.	

- Click any column header to sort items in ascending/descending order of entries in that column.
- Click the funnel icon on the right to search for rules.

See the following sections for more help:

- Create DLP discovery rules and add them to profiles
- View and edit DLP discovery rules
- Create DLP Monitoring Rules and add them to profiles
- View and Edit DLP Monitoring Rules

6.8.1. Create DLP Discovery Rules and add them to Profiles

Process in brief

- Step 1 Add keywords to keyword groups. See View and Manage Keyword Groups for more details.
- Step 2 Create custom data patterns, if required. See View and Manage Pattern Variables for more details.
- Step 3 Create a DLP discovery rule using the predefined and custom data patterns and keyword groups. See this section.
- Step 4 Add the DLP rule to profiles. See **Data Loss Prevention Settings** for more details.
- Step 5 Deploy profiles on devices. See View and Manage Profiles Associated with Device for more details.
 - Click 'Configuration Templates' > 'Data Loss Prevention' > 'Create' button > 'Discovery Rule'

DLP discovery rules allow you to identify sensitive information in files on managed devices, including card numbers, social security numbers, bank routing numbers and more.

You will define the following items when you create a discovery rule:


- Location The folders or drives that you want to scan on the target devices. For example, 'C:\Users\'.
- File types The file extensions you want to inspect. For example, .doc., .xls., .txt.
- **Search pattern** The type of data you want to search for. For example, card numbers, bank account numbers, social security numbers, dates-of-birth, etc.
- Action The response Endpoint Manager should take when the rule conditions are met. The options are 'ignore' and 'quarantine'.

You can then add the discovery rule to a profile, which is in turn applied to target devices or users.

Create a DLP discovery rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click 'Create' button then 'Discovery Rule'





Complete the following fields:

Name - Enter a label for the rule

Description – Add a short note for your reference.


Action - The response Endpoint Manager should take on files which meet the rule conditions. The options are:

- **Ignore** Take no action on the file. You can still review the files at 'Security Sub-systems' > 'Data Loss Prevention' > 'Logs'.
- Quarantine The file is moved from its original location on the endpoint and placed in a secure holding area. Users cannot open quarantined files. You can review quarantined files as follows:
 - Local Endpoint Open Comodo Client Security > Click 'Tasks' > 'DLP Tasks' > 'Data Loss Prevention Quarantine'. You can restore the files to original location from here if required.
 - Endpoint Manager Click 'Security Sub-Systems' > 'Data Loss Prevention' > 'Logs'.

Show match results with first and last symbols in view logs - If enabled, the log file shows the actual data discovered in the file. Only the first and last characters of the record are shown. For example, a name with seven digit account number would be shown as J**e S***h 1*****7.

Click 'Create' to move to the rule configuration screen:






Targets / scan locations

- Click the 'Targets' tab > 'Edit'
- The path 'C:\Users' is included by default.
- Click 'Add' > 'File Path' to add a new scan location:






- Enter the location you want to scan then click 'Ok'
- Repeat the process to add more locations
- Click the pencil icon in the 'Action' column to edit a location
- Click 'Save'

Exclusions

You can omit specific locations and/or file types from your discovery scan.

- · Click the 'Exclusions' tab then click 'Edit'
- Click 'Add'
 - File path Exclude a folder or file
 - File Groups Exclude a specific set of file types:






File groups make it easy to exclude an entire class of file. Choose the group you want to exclude then click 'Save'.

- Click 'Settings' > 'System Templates' > 'File Group Variables' if you want to view and manage file groups
- See File Groups if you want help with them.

Repeat the process to add more exclusions.






Patterns

The patterns tab is where you tell the scan what types of data you want to search for.

- A 'pattern' is the format used by the type of data you want to find. Each pattern is a combination of a keyword group and information format.
- For example, the 'Name with SSN' pattern consists of:
 - Keyword group = 'Names' group.
 - Information format = 9 digit number in a 3-2-4 format, like '123-45-6789'.
- Endpoint Manager ships with a number of patterns which you can use to search for sensitive data.
- You can also create custom patterns to search for specific data.
- Click 'Settings' > 'System Templates' > 'Pattern Variables' to view all available patterns and create custom patterns.
 - See View and Manage Patterns Variables if you need more help on patterns.


Add patterns

- Click the 'Patterns' tab then 'Edit'
- Click 'Add Pattern'



- **Select Pattern** Choose the type of information that you want to search for in scanned locations. For example, credit card numbers, social security numbers and more. You can also select custom pattern that you created in **pattern variables** screen.
- **Threshold** The number of times that data matching the pattern must be found in a document. Endpoint Manager will flag a document if it contains the threshold quantity of pattern examples.





- Note You MUST add keywords to the keyword group or the search will not work.
- You can add keywords to keyword groups at 'Settings' > 'System Templates' > 'Keyword Variables'
- Note You MUST add keywords to the keyword group or the search will not work.
- You can configure keywords and groups at 'Settings' > 'System Templates' > 'Keyword Variables'
- See View and Manage Keyword Groups for help to manage keyword groups


Predefined Pattern	Description
Name with 5 Digit Account Number	Consists of Keyword Group 'Names' and 5 digit bank account number.
Name with 6 Digit Account Number	Consists of Keyword Group 'Names' and 6 digit bank account number.
Name with 7 Digit Account Number	Consists of Keyword Group 'Names' and 7 digit bank account number.
Name with 8 Digit Account Number	Consists of Keyword Group 'Names' and 8 digit bank account number.
Name with 9 Digit Account Number	Consists of Keyword Group 'Names' and 9 digit bank account number.
Name with 10 Digit Account Number	Consists of Keyword Group 'Names' and 10 digit bank account number.
Name with SSN	Consists of Social Security Number and Keyword Group 'Names'.
ABA Routing number	Consists of American Bankers Association (ABA) routing number. This is the nine digit bank code printed in negotiable instruments in the US.
Date of birth	Consists of Birth Date.
Credit Card Number	Consists of Credit Card Number.
IP Network	Consists of IPv4 and IPv6 IP Addresses.
	Examples:



	192.0.2.0/24 198.51.100.0 2001:0db8:85a3:0000:0000:8a2e:0370:7334 2001:db8:1234::/48
Network Address	Consists of URLs, and domain names.
	Examples:
	http://domain.name
	https://domain.name
	www.domain.name
	domain.com
	local.net
IBAN Code	Bank account number in International Bank Account Number (IBAN) format.
MAC Address	Searches for mac addresses, the unique identifier assigned to network cards.

· Click 'Ok'

The pattern configuration dialog depends on the selected pattern. The image below is shown for 'Name with 5 digit account number':




Pattern Elements – Available for 'name with account numbers' predefined patterns

- Keyword Groups 'Names' keyword group is added by default for 'name with account numbers' predefined
 patterns. You cannot edit this.
- Custom Mask (optional) Specify the number(s) that you want to scan and identify. The number of digit
 fields shown here depends on the selected pattern. For example, six fields are shown if you select 'name
 with 6 digit account number'.



Click 'Custom Mask'.




- Allow to specify Mask Enable this if you want to search for specific numbers.
 - Enter the number in each field. For example if you want to search for account numbers ending with 345, then leave the first two fields blank and enter 3, 4 and 5 in third, fourth and fifth fields.
- · Click 'Set Mask Configuration' then 'Ok'.

The pattern type is added to the list.

· Repeat the process to add more patterns






- Click the pencil icon in the 'Action' column to edit a pattern selection and / or its threshold.
- · Click 'Save'

Document types

- This tab lets you choose which types of file you want to scan for sensitive data.
- You can choose PDFs, Word documents, HTML files, text files and/or ZIP files.
- The scan will search the content of all files which have a matching file extension in the locations you specified.

Click the 'Document Types' tab then 'Edit':



- Use the switches in the status column to choose which types of files you want to scan
- · Click 'Save'

You can now add the rule to the 'Data Loss Prevention' section of a Windows profile.

See Data Loss Prevention Settings for help to add a DLP scan to a profile.




6.8.2. View and Edit DLP Discovery Rules

You can view and edit DLP discovery scan rules, and see which profiles contain the rule.

View rule details

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click the name of a rule to open its configuration interface




Edit a rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click on the name of a rule. The rule configuration interface opens at the 'General' tab.
- Click the 'Edit' button to modify the details.
 - Editing a rule is similar to adding a new rule. See Create DLP Discovery Rules and Add them to Profiles for help with this.

View all profiles which use a particular rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click the name of a rule to open its configuration interface.
- Click the 'Profiles' tab:





Column Heading	Description
Profile Name	The profile in which the rule is active. • Click the profile name to open its configuration screen. See Edit Configuration Profiles for more details.
Created by	 The administrator who added the profile. Click the name to view their user details. See View the details of the User for more details.

6.8.3. Create DLP Monitoring Rules and add them to Profiles


Click 'Configuration Templates' > 'Data Loss Prevention' then the 'Create' button > 'Create Monitoring Rule'

- DLP monitoring rules let you prevent sensitive information from being copied to external devices like USB keys, block screenshots of running applications, documents and so on.
- After creating a monitoring rule, you can then add the rule to a profile, which in turn is applied to target devices or users.
- EM currently supports only removable storage monitoring rule. More monitoring rules in next version.

Create a DLP monitoring rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click 'Create' then 'Create Monitoring Rule'





You can create the following monitoring rules:

Removable Storage Rule


Removable Storage Rule

• Set up rules which block or allow copy/move operations to USB data devices

Create a removable storage monitoring rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click 'Create' then 'Create Monitoring Rule'





- Name Enter an appropriate label for the rule
- **Description** Enter short notes for the rule
- Monitoring type Select 'Removable Storage Rule' from the drop-down
- Action What EM should do if it detects data being moved from the target devices:
 - Ignore Data transfers to the device are allowed.
 - **Block** The storage device is set to 'Read-only' mode. Users cannot copy data to / from the storage device.
- Log when this action is performed Choose whether you want to create an event log whenever the rule is enforced. Click 'Security Sub-Systems' > 'Data Loss Prevention' > 'Logs' to view DLP logs.
- · Click 'Create'.

The rule is saved and the rule configuration screen opens:





General

- · Click 'Edit' at top-right
- Update the fields if required.
- Click 'Save'

Criteria

Click 'Edit' at top-right




USB Data Devices - Enable / disable the removal storage device for USB devices. If disabled, the
monitoring rule for USB devices becomes inactive.



- Supported USB devices include external HDDs / SSDs, SD cards, SDXC-SDHC cards, eSata removable drives and devices using MTP protocol
- · Click 'Save'.

Profiles

• Shows the profile(s) that are using this monitoring rule.



• Profile Name – Click the profile name to open the profile configuration screen



Created By – Click the user name to open the user details screen

You can now add the rule to the 'Data Loss Prevention' section of a Windows profile.


See Data Loss Prevention Settings for help to add a DLP monitoring rule to a profile.

6.8.4. View and Edit DLP Monitoring Rules

You can view and edit DLP monitoring rules, and see which profiles contain the rule.

View rule details

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click the name of a rule to open its configuration interface




Edit a rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click on the name of a rule. The rule configuration interface opens at the 'General' tab.
- Click the 'Edit' button to modify the details.
 - Editing a rule is similar to adding a new rule. See Create DLP Monitoring Rules and Add them to Profiles for help with this.

View all profiles which use a particular rule

- Click 'Configuration Templates' > 'Data Loss Prevention'
- Click the name of a rule to open its configuration interface.
- Click the 'Profiles' tab:






Column Heading	Description
Profile Name	The profile in which the rule is active. • Click the profile name to open its configuration screen. See Edit Configuration Profiles for more details.
Created by	The administrator who added the profile. • Click the name to view their user details. See View the details of the User for more details.

7. Network Management

Click 'Network Management' > 'Discoveries'.

- The discovery feature lets you scan networks and active directory (AD) servers to identify all devices on the network.
- The scan will identify both managed and unmanaged devices. You can configure EM to alert you if a scan
 finds new devices.
- You can run simple network scans from a 'probe device' situated in the target network. The probe device must be a managed Windows endpoint which has already been added to Endpoint Manager.
- You can scan Active Directory servers either with or without the use of a probe device.
- All discovered devices are shown in 'Network Management' > 'Devices' > 'Discovered Devices':





Enroll discovered devices to EM

- All newly discovered devices are 'Unmanaged', so you cannot control them with Endpoint Manager yet. You
 need to install the communication client on the devices to enroll them.
- EM can auto-enroll discovered Windows devices. Auto-enrollment of other discovered devices is coming in later releases.
- You can also create a client install package for discovered devices, then use Comodo's auto-deployment tool to install the package. You can change the owner and group of these devices after they have been enrolled.

Manage device over SNMP

- The SNMP (Simple Network Management Protocol) scan identifies devices such as printers, routers, switches, UPS etc.
- Click 'Manage Device over SNMP' to apply an SNMP profile to these devices. SNMP profiles are quite simple, offering to alert you if the device is powered on or off for a certain length of time.
- However, this still gives you some management of devices that do not run on a supported operating system (Windows / Android / Linux / Mac / iOS).
- You can view these devices in 'Network Management' > 'Devices' > 'Managed Devices' tab.

Please see the following sections:

- Create and Run Network Discovery Tasks
- Manage Profiles for Network Devices
- Manage Network Devices
- Manage Network Monitors

7.1. Create and Run Network Discovery Tasks

Click 'Network Management' > 'Discoveries' in the left menu

Discovery scans consist of the IP range you want to scan, a probe device, and a destination group for discovered devices.


- The Discoveries Area
- Example Deployment Process
- Create a Discovery Task
- Run a Discovery Task



- View Discovery Logs
- Manage a Discovery Task
- Remove Discovery Tasks
- Export Discovery Tasks

The Discoveries Area

The discoveries area lets you manage, create and run discovery scans:



Column Heading	Description
Name	The label of the discovery task.
	Ideally, the label should help you identify the target or purpose of the task in future. For example, 'Discovery Task on Company X network'.
	Click the discovery name to open its configuration screen. See Create a Discovery Task for more details
Туре	The kind of scan used to audit the network. The three possible types are:
	Active Directory
	Network
	• SNMP
	You enable SNMP scans within the network scan type. They run simultaneously with the network scan. SNMP results are reported separately to Endpoint Manager and may find additional devices.
Customer	The company that owns/controls the target network.
Device Group	The group to which identified devices are assigned. You can specify the target device group when you configure the scan.



Last Discovery Date	Date and time the scan was most recently run.	
Last Updated Date	Date and time the scan task was most recently edited.	
Created by	The admin who created the discovery task.	
	 Click the admin name to view their details. See View User Details if you need help with this. 	
	Controls	
Create Discovery	Add a new discovery task.	
	See Create a Discovery Task for more details	
Discover Now	Run an on-demand scan to identify all devices connected to the target network.	
	See Run a Discovery Task for more details.	
Clone Discovery	Create a new scan by copying an existing scan and modifying its settings as required.	
	See Create a Discovery Task for more details.	
Delete Discovery	Remove selected discovery tasks. The control will appear only if a discovery task is selected.	
	See Remove Discovery Tasks for more details.	
Export	Save the discovery tasks as a CSV file.	
	See Export Discovery Tasks for more details.	

Example Deployment Process

Optional - Make sure your probe device is in place. The probe is required for network and SNMP scans, but is optional for Active Directory scans.

- Create a new group for discovered devices under the company of your choice: 'Devices' > 'Device List' > 'Group Management' > 'Create Group'.
 - Name the group. For example, 'Discovered Devices Company X'.
 - Leave this group empty as it is purely to segment the discovered devices. You can move the
 devices to different groups after they have been enrolled.
- Click 'Network Management' > 'Discoveries' > 'Create Discovery' > 'Discovery by Network' > create a name for the discovery task. E.g 'Discovery Task on Company X network'.
- Click 'OK' to open the task configuration screen. Click 'Edit' to actually configure the scan.
 - Specify the customer / target device group.
 - See **Network discovery scan** if you need help to configure a network/snmp scan
 - See AD discovery scan for help to configure an AD scan
- Save your task then select it in the 'Discoveries' screen. Click 'Discover Now' to run the scan.
- The scan will take around 10 minutes. All discovered devices will go into your new group. You can view discovered devices in 'Network Management' > 'Devices' > 'Discovered Devices'.
- Auto-enrolled Windows devices can be viewed in 'Devices' > 'Device List'
- Next, we will create a package to install the communication client on Windows devices, then use the autodeployment tool to deploy the package.
- Click 'Devices' > 'Device List' > 'Bulk Installation Package'. Configure the package as required.
 - Remember to specify the correct company and the group you just created.

ITarian Endpoint Manager - Administrator Guide



- Do not change the filename of the .msi. It is unique to this deployment.
- Click 'Download Installer' and save the file to your local machine.
- Next, download and install the 'Auto Discovery and Deployment Tool' (ADDT). You can do this at the prompt, or download it from the ITarian portal (click 'Tools' in the top-menu).
- In ADDT, choose the .msi you just created as the 'Deployment Package'.
- Deployment options Choose 'Network Addresses' then enter the same IP range as you used in your discovery scan.
- Click 'Start Deployment' to install the .msi on the target devices. This will enroll the devices to Endpoint Manager in the customer/group you created earlier.
 - See the ADDT user guide at https://community.itarian.com/help/topic-452-1-955-13346-Deploy-Applications---Packages.html if you want help with the utility
- In Endpoint Manager, click 'Devices' 'Device List' > 'Group Management' > Company/Group to view the enrolled devices.
- You can now assign the devices to new users, or move them to new groups, as required.
- See 'Bulk Enrollment of Devices' for more information about enrolling Windows, Mac and Linux devices.

Create a Discovery Task

There are two ways you can create a discovery task:

- Create new discovery task
- · Clone an existing task and edit it as required

Create a new discovery task


- There are two types of discovery task:
- **Network** Scan an IP range using a probe device. The probe must be a managed Windows device connected to the network. You can run a concurrent SNMP scan when you run a network scan.
- Active Directory Scan an Active Directory domain for devices. You can configure the scan with or without
 a probe device. If not specified, EM will directly scan the AD server.

Network discovery scan

Click 'Network Management' > 'Discoveries'




Click 'Create Discovery'



- **Discovery Name** Create a label for the discovery task. Ideally, the label should help you identify the target or purpose of the task in future.
- · Select 'by Network'
- Click 'Next' to add probe devices.






- **Select Device(s)** Start typing the name of the device you want to use as probe and select from the suggestions.
 - A probe device is a managed Windows endpoint inside the network that you want to scan. The
 device must already be enrolled to Endpoint Manager and have communication client (CC) 6.32 or
 higher installed. This device will launch the scans you request on the target network.
 - You can also add additional devices for fail-over. The device added first will be used as the probe. If the first device is offline then EM will use the next device for the scan.
- Enable SNMP for discovery Run a simple network management protocol (SNMP) scan alongside
 the network scan.
 - If enabled, the SNMP scan will run simultaneously with the IP range scan.
 - The SNMP results are shown as separate row in the 'Network Management' > 'Devices' >
 'Discovered Devices' interface.
 - **Community String** This is a passcode sent with each SNMP Get-Request to authenticate access to a router or other device. If the community string is correct, then the device responds with the requested information.
- Run immediately after discovery is created The discovery scan will start after it is saved.

Click 'Create' when finished. This opens the discovery config screen:






Next, click 'Edit' on the right to configure scan targets and options. Click the following sub-headers if you need help with a particular tab:

- **General** Specify the IP addresses you want to scan. Set the customer and device group to which new devices should be assigned. Choose your probe device.
- Auto Enrollment Windows devices only. Set the customer and device group to which you want to assign
 discovered Windows devices. Complete the instructions in the 'Auto Enrollment' tab on the probe and target
 devices.
- Notifications Select which events you want to be notified about. Events include when the scan ends, when a new device is found, and when a new IP is found.
- Schedule You can automate the discovery scans by scheduling them to run daily, weekly or monthly.
- Discovery Logs View the results of previous scans run under this task. You can see the date, type and
 other general details about a scan. Click 'Details' then 'Click Here' to view a list of devices found by the
 scan.

General Settings





Saddle and Pedals

TECHMONSTER


TECHMONSTER\girid



- Discovery name This is pre-populated with the label you created in the previous step. Edit the name, if required.
- Customer Specify the company that owns/controls the target network.
 - Enter first few letters of a company name and select from the suggestions.
- **Device group** Specify the group to which discovered devices should be assigned. The device group must belong the 'Customer' named in the previous row.
 - Enter the first few letters of the device group and select from the suggestions.
- SNMP Pre-populated with the choice you made in the previous step. Change the choice if required.
 - If enabled, the SNMP scan will run simultaneously with the IP range scan.
 - SNMP results are shown as a separate row in 'Network Management' > 'Devices' >
 'Discovered Devices'.
 - **Community String** This is a passcode sent with each SNMP Get-Request to authenticate access to a router or other device. If the community string is correct, then the device responds with the requested information.

Most network vendors ship their equipment with a default password of "public". This is the so-called "default public community string".

- Probe Devices Pre-populated with the list of devices you specified in the previous step. You
 can add a new probe as follows:
 - Click 'Add' at top-left:




- Start typing the name of the device you want to use as probe. Select from the suggestions.
- You can add multiple devices for fail-over, if required. You must choose a default probe if you add multiple probes. The other probes are only used if the default is not available.




• IP Ranges - Specify the IP address range that you want to scan for connected devices. You can add any number of IP ranges within the network for a single discovery task. You can also specify addresses you want to exclude.

Leave this blank if you want to scan the entire network to which the probe is connected.




- IP from Start address of the IP range
- IP to End address of the IP range
- **Description** Add any brief comments about of the IP range (optional). Use this if there are different IP segments which you want to identify. You can enable or disable ranges as required in any scan task.
- Click 'Add' to add the IP range to the list. Repeat the process to add more IP address ranges
- IP Range Exclusions Specify IP addresses that should not be scanned.





- IP from Start address of the IP range to be excluded
- IP to End address of the IP range to be excluded
- **Description** Brief description of the range you want to exclude (optional). Use this so you and other admins can easily identify excluded ranges. You can enable or disable exclusions as required in any scan task.
- Click 'Add' to add the IP range to the list
- · Repeat the process to add more IP address ranges
- Select an IP range and click 'Remove' to delete it from the list
- IP Range Exclusions Specify IP addresses that should not be scanned.





Next:


- Click the 'Auto Enrollment' tab to configure the scan to auto-enroll Windows devices. See **Auto Enrollment** for help with this.
- Click the 'Notifications' tab to configure alerts. See Notification Settings for help with this.
- Click the 'Schedule' to run the scan at a set time. See Schedule the discovery task for help with this.

AD discovery scan

- Click 'Network Management' > 'Discoveries'
- · Click 'Create Discovery'

The 'Create Discovery' wizard starts:





- **Discovery Name** Enter a label for the new discovery task. Ideally, the label should help you identify the target or purpose of the task in future.
- Select 'by Active Directory'
- Click 'Next'.

Select discovery type:

- With Probe Device Specify a probe device to run the discovery scan on the AD domain.
 - Choose this option if the AD server is not directly accessible over the internet.
 - A probe device is a managed Windows endpoint on the same network to which the AD server is connected.
 - The device must already be enrolled to Endpoint Manager and have communication client (CC) version 6.32+ installed. This device will launch the scans you request on the target network.



- The probe device need not be a member of the AD domain
- Choose your probe device in the 'Select Devices' field
- Without Probe Device The discovery scan will be run directly by EM
 - · Select this option if the AD server is accessible through the internet.
 - You need not specify a probe device to run the scan.

Select Device(s) - Applies only if 'With Probe Device' is chosen.


- Start typing the name of the probe device you want to use and select from the suggestions.
- You can also add additional devices for fail-over. The device added first will be used as the probe. If the first device is offline at the time of discovery, EM will use the next device and so on.

LDAP Settings:

- LDAP server host Enter the IP address or hostname of the AD server that hosts the AD domain
- LDAP account domain Enter the domain name of the AD domain
- LDAP account login and LDAP account password The admin username and password required to
 access the AD server.

Run immediately after discovery is created - The discovery scan will start right after it is saved.

- Click 'Create'
- The discovery task configuration screen opens:



Click 'Edit' on the right to get started. Click the following sub-headers if you need help with a particular tab:


• **General** - Edit the LDAP details of the AD server you want to scan. Set the customer and device group to which new devices should be assigned. Choose your probe device.



- Notifications Select which events you want to be notified about. Events include when the scan ends and when a new device is found.
- Schedule You can automate the discovery scans by scheduling them to run daily, weekly or monthly.
- Discovery Logs View the results of previous scans run under this task. You can see the date, type and
 other general details about a scan. Click 'Details' then 'Click Here' to view a list of devices found by the
 scan.

General Settings

- · Click the 'General' tab (if it is not already open)
- Click the 'Edit' button at the top-right




Discovery name - This field is pre-populated with the label you created in the previous step. Edit
the name, if required.



- LDAP Settings The hostname of the AD server, AD domain name, AD admin username and
 password are pre-populated from the details you entered in the previous step. Modify them if
 required.
- **Customer** Specify the company that owns/controls the target AD network.
 - Enter first few letters of a company name and select from the suggestions.
- **Device group** Specify the device group to which identified devices will be assigned. The device group must belong the 'Customer' named in the previous row.
 - Enter the first few letters of the device group and select from the suggestions.
- Probe Devices Applies only if you have chosen 'With Probe Devices' in the previous step. The list is prepopulated with the probe devices you specified in the previous step. You can add or remove devices if
 required.

Add a probe device:

Click 'Add' at the top-left:



- Start typing the name of the device you want to use as the probe then select from the suggestions.
- You can also add additional devices for fail-over. The device added first will be used as the probe. if the first device is offline at the time of discovery, EM will use the next device and so on.
- Click 'Add'.
- Repeat the process to add more probes. Multiple probes act as fail-overs for each other.
- You must select a default probe for scans if you add multiple probes. The other probes will only run the scan if the default probe is not available
- Click 'Save'

Next:

Click the 'Notifications' tab to configure the alerts. See Notification Settings for help with this.




 Click the 'Schedule' tab to create a schedule to periodically run the scans. See Schedule the discovery task for help with this.

Auto Enrollment

- You must download and install PsTools on the probe device before you can use the auto-enrollment feature.
- You also need to enable NetBIOS over TCP/IP on target devices.
- Read the full instructions on the 'Auto Enrollment' page and complete the steps therein.

Auto-enroll devices:

- Click the 'Auto Enrollment' tab
- Click the 'Edit' button at the top-right




- Auto Enrollment Enable this to auto-enroll discovered Windows devices to EM
- User Name / Password Admin credentials for the target devices.



- Device Owner Select the admin of the customer that you selected in the general tab. The devices
 are assigned to this admin after enrollment. You can assign the device to the appropriate user later.
 Start typing a name and select from the suggestions.
- Device Group Choose the group to which you want to assign auto-enrolled devices. Start typing the group name and select from the suggestions.
- Assigned Profile Choose the profile you want to apply to discovered devices. Start typing a profile
 name and select from the suggestions. Note The security client has to be installed for the profile to
 take effect.
- Click 'Save' to apply your changes

Notification Settings

- Click the 'Notifications' tab
- Click the 'Edit' button at the top-right



- Alert Choose the alert template for your notification. An alert template contains general settings
 of your alert and specifies its recipients. Alert templates are configured in 'Configuration Templates'
 > 'Alerts'. See Manage Alerts for more details.
- Select which events generate an alert:
 - Discovery complete Get an alert when a discover scan finishes
 - New device detected Get an alert when a device is identified for the first time
 - Device IP change detected Get an alert if the IP address of a device changes
- Click 'Save' for your settings to take effect
 - Select which events generate an alert:
 - Discovery complete Get an alert when a discovery scan finishes
 - New device detected Get an alert when a device is identified for the first time
 - Device IP change detected Get an alert if the IP address of a device changes (Available only for network scans)
- Click 'Save' for your settings to take effect


Schedule the discovery task

The 'Schedule' tab lets you configure daily, weekly or monthly scans to run at specific times.

Click the 'Schedule' tab



Click 'Add' to create a schedule




- Name Enter a label for the discovery scan schedule
- Start date Select what date the scan should start
- Schedule Specify whether the scan should run daily, weekly, monthly, or never.
 - For weekly, specify the days of the week
 - For monthly, specify the days of the month



- Scheduled time Specify the scan start time
- Finish date The options are:
 - · No end date
 - End date Select the date on which the schedule will end.
- Skip if probe device is offline The scan will be aborted if all probe devices are offline at the scheduled time. If disabled, the scan will be queued until the device comes online.
- Click 'Add

The schedule will be saved and added to the list.




- Repeat the process to add more schedules
- · Select a schedule and click the Edit button on the top to modify it
- Select a schedule and click the 'Remove' button at the top to delete it

Create a new discovery task by cloning an existing task

- Click 'Network Management' > 'Discoveries'
- Select the discovery task you want to use as the base and click 'Clone Discovery'
- Alternatively, click the name of the discovery scan task and click Clone Discovery on the top of the configuration screen.





- **Discovery Name** The label of the discovery task. This is auto-populated with the name of the source discovery task wit the prefix '[Clone]'. Create a new name for the task, if required.
- Clone along with schedules Select if you want to use the same schedule as the source task.
- Click 'Clone'.

The new discovery scan task is created with the parameters of the source task. See **above** if you need help.

Click 'Save' to apply your changes

Run a Discovery Task

There are two ways you can run a discovery task:


- From 'Network Management' > 'Discoveries'
- From 'Network Management' > 'Devices'

The following section explains how to run a scan from the 'Discoveries' interface.

Run an on-demand network discovery scan

- Click 'Network Management' > 'Discoveries'
- Select the discovery scan task from the list and click 'Discover Now' on the top
- Alternatively, click the name of the discovery task and click 'Discover Now':






- The scan will start and will run for ten minutes. Any SNMP scans will start simultaneously.
- All discovered devices will appear in 'Network Management' >'Devices' > 'Discovered Devices'
 - See Discovered Devices for more details.

View Discovery Logs

The 'Discovery Logs' tab in the discovery scan task configuration screen lets you view the history of scans run by the task and their details.

- Click 'Network Management' > 'Discoveries'
- Click the name of a discovery scan task to open its configuration interface
- Click the 'Discovery Logs' tab




Discovery Scan Logs - Table of Column Descriptions	
Column Heading	Description
Probe Device	The Windows device that ran the scan. Shown only for network discovery scans and AD discovery scans configured with a probe device.



	Click the device name to view device's details.
Status	Current progress of the scan. The possible values are:
Started At	Date and time when the scan commenced.
Started By	 Email address of the admin who launched the scan. Click the email address to view the details of the admin. See View User Details if you need help with this.
Finished At	Date and time the scan completed.
Launch Type	Whether the scan was scheduled or started manually.
Type of Discovery	The kind of the scan. The possible types are:
Details	 Click the 'Details' link to view information such as the names and number of devices found. See View Details of a Discovery Scan for more info on the details screen.

View Discovery Scan Details

• Click 'Details' in the row of a scan to view additional information:



Click the 'Click here' link to view the devices found by the scan. See **Discovered Devices** for more details.

Edit a Discovery Task

- Click 'Network Management' > 'Discoveries'
- Click the name of a discovery scan task to open its configuration interface
- · Click the 'Edit' button on the right
- · You can edit settings in the 'General', 'Auto Enrollment' and 'Notifications' areas




- You can edit settings in the 'General', 'Auto Enrollment', 'Notifications' and 'Schedule' areas
- Edit the parameters as required. See the explanations of configuration screens of network discovery task and AD discovery task for more details.
- · Click 'Save' to apply your changes

Remove Discovery Tasks

Discovery scan tasks that are no longer required can be removed from Endpoint Manager

- Click 'Network Management' > 'Discoveries'
- Select the discovery task to be removed and click 'Delete Discovery' on the top
- Alternatively click the name of the discovery task and click 'Delete Discovery' on the top of the configuration screen




• Click 'Delete' in the confirmation dialog to remove the task.

Export discovery tasks to CSV

- Click 'Network Management' > 'Discoveries'
- Click the 'Export' button above the table then choose 'Export to CSV':





- You can find the CSV file at 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.


7.2. Manage Profiles for Network SNMP Devices

Click 'Network Management' > 'Profiles'

- Network profiles are used on SNMP compliant devices that don't run a supported operating system (Windows, Linux, iOS etc). Example devices include routers, switches and printers.
- The profiles let you track events on SNMP devices and receive alerts if certain conditions are met.
- You first create a monitor to track events, then you add the monitor to a network profile. You then deploy the
 profile to your SNMP devices.
 - You must have run at least one discovery scan to find your SNMP devices.
 - You should also have created at least one network monitor. See 'Manage Network Monitors'

Open the Network Profiles interface

Click 'Network Management' > 'Profiles'



Click the following links to learn more about each task:


- Create Network Profile
- Clone a Network Profile




Delete a Network Profile

Create a Network Profile

- Click 'Network Management' > 'Profiles'
- Click 'Create' at top-left



- Name Create a label for the profile. For example, 'Profile for routers'.
- Description- Add any short notes you think are required.
- Click 'Create'. This opens the profile, ready for you to configure.
- Click 'Edit' on the right:




Click the 'Network Monitors' tab:






- Click 'Add monitor'
- A network monitor tracks activity on your devices and generate an alert if certain conditions are met.



- Choose Monitors Start typing the monitor name and select from the suggestions. You can add multiple monitors.
 - See 'Manage Network Monitors' if you have not yet saved a monitor.
- Click 'OK'

The page shows all monitors on the profile:



- Click 'Probe Devices'
- Choose the device you want to use to keep track of SNMP devices.




A probe device is a managed Windows endpoint inside your target network. The device must already be enrolled to Endpoint Manager and have the communication client installed. This device will run the monitors on your target SNMP devices.



Click 'Add'



- Device Start typing the managed Windows device name and select from the suggestions.
- Click 'Add'



- Repeat the process to add more probe devices. More devices act as fail-overs for each other.
- Note The first device that you add will be default probe device. If you want to change, select the probe
 device and click 'Set as default'.

The profile is now configured. You can deploy the profile to discovered SNMP devices as follows:

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab
- Select your target SNMP devices
- · Click 'Add Profile'




- · Type the name of the profile you just created
- · Click 'Add'

Click here for an illustrated walk-through of the profile deployment process.

Clone a Network Profile

You can add a new profile by using the settings of an existing network profile.

- Click 'Network Management' > 'Profiles'
- Click 'Clone' at top-left



The cloning process is similar to creating a new profile explained above. Edit the settings as required.


Click here for an illustrated walk-through of the profile deployment process.

Delete a Network Profile

You will no longer get alerts if a network profile is deleted.

- Click 'Network Management' > 'Profiles'
- Click 'Delete' at top-left






Click 'Delete' to confirm

7.3. Manage Network Devices

- Click 'Network Management' > 'Devices'
- This interface lets you view the results of all discovery scans. You can also manage Simple Network Management Protocol (SNMP) compliant devices.
- Managed devices tab Monitor and apply profiles to SNMP compliant devices
- Discovered devices tab View all discovered devices. Select SNMP devices for management.





Click the following links for details:


- Manage SNMP Devices
 - SNMP Device Details Interface
- Discovered Devices

7.3.1. Manage SNMP Devices

- Click 'Network Management' > 'Devices' > 'Managed Devices'
- This area lets you apply network profiles to SNMP compliant devices.
- Network profiles provide limited management of devices that don't run a supported operating system (Windows, Linux, iOS etc). In other words, devices that you cannot apply a regular configuration profile to.
 - For example routers, printers, switches, UPS devices, etc.

Open the Managed Devices interface

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device



Managed Devices - Column Descriptions		
Column Heading	Description	
Device Name	The label assigned to the device by the user. • NEW - Endpoint Manager has not seen this device before. Click 'Mark as read' to remove this tag. • Click a device name to open its details screen.	
Device Type	The category to which the device belongs. For example, endpoint, router, printer and so	



	on. The icon indicates the device's category.
SNMP	Shows whether the device responded to SNMP requests during the scan.
	SNMP devices are usually items like routers, printers, switches etc. These devices don't run a supported operating system (Windows, Mac etc), so you cannot enroll them as you would a regular endpoint.
IP Address	The unique network address of the device
MAC Address	The address of the machine's network card
Last Discovery Date	Date and time the device was most recently identified
First Discovery Date	Date and time when the device was first identified
Last Found By	The discovery scan task that most recently identified the device Click the task name to view its details See Create, Manage and Run Network Discovery Tasks for more details on the discovery scan tasks
Customer	The company that owns/controls the target network.
Device Group	The device group to which the device belongs.
	Controls
Discover Now	Select a discovery scan task then click this button to run the associated discovery scan. • See Run a Discovery Scan in 'Discovered Devices' section for more details
Manage Profiles	Select a SNMP device and deploy profiles in order to monitor it. • See Deploy Profile on SNMP Device
Change Device Type	Update device category type • See 'Change Device Type' in 'Discovered Devices' section for more details
Remove from Managed List	Move the SNMP device back to Discovered Devices section.
Delete Device	Remove selected devices from the list.
Export	Save managed devices as a CSV file
	See Export Managed Devices List for more details

• Use the funnel on the right to filter devices by name, customer, IP address and more.

The interface lets you:

- Run a Discovery Scan
- Deploy Profile on SNMP Device
- Change Device Type
- Move SNMP Devices to Discovered Devices
- Remove SNMP Devices
- Export Managed Devices List


Run a Discovery Scan




This task is same as described in the discovered devices section. Click here for help with this.

Deploy Profiles on SNMP Device

- Network profiles are created and managed in 'Network Management' > 'Profiles'. See Manage Profiles for Network SNMP Profiles
- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device
- Select the device and click 'Manage Profiles'



- Alternatively, click the device name then 'Manage Profiles' in the device details screen.
- · Click 'Add Profile'



In the add network profile dialog, start typing the profile name and select from the suggestions.



Click 'Add'

The profile is added to the selected device and confirmation message is shown:



- Repeat the process to add more profiles, if required.
- Clicking a profile name will take you to the profile details screen.
- To remove a profile, select it and click 'Remove Profile'


Change Device Type

This task is same as described in the discovered devices section. Click here for help with this.

Move SNMP Devices to Discovered Devices

You can move SNMP devices back to discovered devices if required. Note - Profiles associated with the SNMP device is removed if you move it to discovered devices section.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - · Select 'Show all' to view every managed SNMP device
- Select a device and click 'Remove from managed list'



• Alternatively, click the device name then 'Remove from managed list' in the device details screen.

A confirmation message is shown:


Successfully removed from Network Management Devices



Remove SNMP Devices

If you delete a device from the managed devices interface, it will be removed from this screen and also from the discovered devices section. It will be however added to discovered devices screen during the next discovery scan.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group
 Or
 - Select 'Show all' to view every managed SNMP device
- Select a device and click 'Delete Device'




Alternatively, click the device name then 'Delete Device' in the device details screen.

A confirmation message is shown.

Export Managed Devices List

- Click 'Network Management' > 'Devices' > 'Managed Devices'
- Click the 'Export' button above the table then choose 'Export to CSV':






- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

7.3.1.1. SNMP Device Details Interface

- The device details page lets you view an SNMP device's hardware and software, profiles, and event logs.
- You can also manage profiles, remove it from the managed list, rename device's name and delete the
 device.

Open SNMP Device Details Screen

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device
- Click the name of any SNMP device to view its details:



The details screen contains four tabs:

- **Device name** The label of the device
- Summary General hardware and network details.



- Associated Profiles Network profiles deployed on the device.
- Logs Device event logs

The buttons above the table let you perform various tasks:




- Manage Profiles Add / remove network profiles to / from the SNMP device. See Deploy Profile on SNMP Device
- Remove from managed list The device is moved back to the 'Discovered Devices' section. See Move SNMP Devices to Discovered Devices
- Delete Device The SNMP device is removed from the list. See Remove SNMP Devices

Device Name

The device name page lets you change the device name to more recognizable one, if required. For example, as 'Admin department printer' for easy identification.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group
 Or
 - Select 'Show all' to view every managed SNMP device
- Click the name of any SNMP device to open its details pane and click 'Device name' tab:



- Custom device name The current name of the device.
- Allow auto rename of device custom name Indicates whether the actual device name will automatically replace any custom name during the next sync.
- To change the name of the device, click the 'Edit' button at the right.





- Enter the new name in the 'Custom Device Name' field
- Make sure the 'Allow Auto Rename of Device Custom Name' is disabled to retain the custom name in the list. If this is enabled, the custom name will be automatically replaced with the device's name or model number during the next sync with the EM communication client on the device.
- Click 'Save' for your changes to take effect.


The device is listed with its new name.

 To restore the name of the device as it was at the time of enrollment, click 'Edit' from the 'Device Name' interface, click 'Restore' at the right and click 'Save'.

SNMP Device Summary

The summary page contains general information about the device. This includes IP / MAC address, discovery times, and device type.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device
- Click the name of any SNMP device to open its details pane:





Manage Profiles Associated with the Device

The profile tab shows all profiles which have been applied to the device. Profiles contain **monitors** which track events on the device and alert you when certain conditions are met. For example, you can set up a monitor to alert you if a device has been switched off for a certain length of time.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device
- Click the name of any SNMP device to open its details pane
- Click 'Associated Profiles':



Column Heading	Description
Name	Label of the profile. • Click the profile name to view and edit it. See Create a Network Profile.
Source Associated	The type of object to which the profile is applied. This column will always say 'Device' for SNMP profiles.
Information about Association	The current status of profile deployment. For example, successfully processed, deployment failed, etc.

SNMP Device Event Logs

The logs tab shows all activity on a specific SNMP device.

- Click 'Network Management' > 'Devices'
- Click the 'Managed Devices' tab if not already open
 - Select a company or a group to view managed SNMP devices assigned to that group Or
 - Select 'Show all' to view every managed SNMP device
- Click the name of any SNMP device to open its details pane then click 'Logs' tab





Column Heading	Description
Monitor Name	The monitor that recorded the event.
	 Click the name of the network monitor to open its details interface. See 'View Monitor Details'
Status	Whether or not the monitor is currently active on the device.
Hit Count	Number of times the monitor's conditions have been triggered.
Last Hit Time	Date and time the monitor's conditions were most recently triggered.
Last Update Time	Date and time when the information was last refreshed.
Details	View a log of the breach events.
	 This is similar to network monitor logs except here it shows logs associated with the device. See View Details of Network Monitor Logs for more information

7.3.2. Discovered Devices


Click 'Network Management' > 'Devices' > 'Discovered Devices'

- This is the results screen for devices found by the discovery scans. Discovery scans help identify all devices connected to a specific IP range or AD domain.
- You can configure and run a discovery scan in 'Network Management' > 'Discoveries'. Click here if you want help on this.

Open Discovered Devices

- Click 'Network Management' > 'Devices' > 'Discovered Devices'
 - Select a company or a group to view discovered devices assigned to that group Or
 - Select 'Show all' to view every discovered device





Column Heading	Description
Device Name	The label assigned to the device by the user.
	Endpoint Manager has not seen this device before. 'New' devices can be enrolled to EM if required.
	Alternatively, select the device and click 'Manage Device over SNMP' if it is a printer, router etc.
	Select a device and click 'Mark as read' to remove the 'New' tag.
	Click a device name to open its details screen.
Device Type	The category to which the device belongs. For example, endpoint, router, printer and so on. The icon indicates the device's category.
Discovery Type	The kind of discovery scan by which the device was identified. The possible types are:
	Active Directory
	Network
	SNMP
IP Address	The unique network address of the device.
MAC Address	The address of the machine's network card.
Last Discovery Date	Date and time the device was most recently identified.
First Discovery Date	Date and time when the device was first identified.
Last Found By	The discovery scan task that most recently identified the device.
	Click the task name to view its details
	See Create, Manage and Run Network Discovery Tasks for more details on the discovery scan tasks
Customer	The company that owns/controls the target network.
Device Group	The group to which the device is assigned.



	Controls
Discover Now	Select a discovery scan task then click this button to run the associated discovery scan. • See Run a Discovery Scan for more details
Manage Device over SNMP	Select a SNMP device and move to 'Managed Devices' for applying network profiles. • See 'Move SNMP Devices for Management'
Mark as read	Removes the 'New' status of selected devices • See Mark Recognized Devices as Known Devices for more details
Change Device Type	Update device category type • See 'Change Device Type'
Delete Device	Remove selected devices from the list
Export	Save discovered devices as a CSV file • See Export Discovered Devices List for more details

• Use the funnel on the right to filter devices by name, customer, IP address and more.

The interface lets you:

- Run a Discovery Scan
- Move SNMP Devices for Management
- Mark Recognized Devices as Known Devices
- Change Device Type
- Remove Selected Devices
- Export Discovered Devices List


Run a Discovery Scan

- Discovery scans are configured and run in 'Network Management' > 'Discoveries'. Chapter 7.1 covers this
 in more detail.
- You can also run existing scans from the results screen ('Network Management' > 'Devices' > 'Discovered Devices')

Run a scan

- Click 'Network Management' > 'Devices'
- Click the 'Discovered Devices' tab
- Click the 'Discover Now' button above the table





- **Discovery** Select the pre-configured discovery task you want to run.
 - Enter the first few letters of the scan name and select from the suggestions
- Skip if probe device is offline Will abandon the scan if the probe device(s) are not available.
 - The command is queued if this option is not selected. The scan will start once the probe device comes online.
- Click 'Discover' to run the scan. The scan will run for ten minutes and report all discovered devices found at the end of this period. If selected, the SNMP scan will run simultaneously.
- You can see discovered devices in 'Network Management' > 'Devices' > 'Discovered Devices'.
- Results include SNMP, managed and unmanaged devices. Managed devices = already enrolled to Endpoint Manager. Unmanaged = not enrolled to Endpoint Manager.

Manage SNMP Devices


- Endpoint Manager is capable of detecting SNMP devices in a discovery scan. You should have enabled SNMP detection when setting up the scan.
- The SNMP feature provides simple management of devices which don't run a supported operating system (Windows, Mac, Linux etc). SNMP devices are usually items like UPS, printers, routers, switches etc.
- You can apply a simple network profile to these devices which alerts you if the device has been powered on or off for a certain period of time.
 - See Manage Profiles for Network SNMP Devices for more on this.

Move SNMP devices to management

- Click 'Network Management' > 'Devices'
- Click the 'Discovered Devices' tab



- Select a company or a group to view the list of devices identified in that group Or
- Select 'Show all' to view every discovered device
- Select an SNMP compliant device then click 'Manage Device over SNMP'



- You can move one device at a time
- A confirmation message is shown:

Successfully added to Network Management Devices


Mark Recognized Devices as Known Devices

- Unmanaged devices identified for the first time are marked 'New'.
 - You can enroll discovered devices to Endpoint Manager. See Example Deployment Process in chapter 7.1 for a quick guide on this.
 - After enrolling devices you may want to remove the 'New' tag.
 - If you remove the 'New' tag the device will not be flagged as new in subsequent scans.

Mark new devices as known

- Click 'Network Management' > 'Devices'
- · Click the 'Discovered Devices' tab
 - Select a company or a group to view the list of devices identified in that group Or
 - · Select 'Show all' to view every discovered device
- Select the new devices that are to be marked as known devices and click 'Mark as read'.






- Click 'OK' in the confirmation dialog
- The 'New' tag NEW beside the device will disappear

Change Device Type

You can change the device category in case it was detected incorrectly after a scan.


- Click 'Network Management' > 'Devices'
- Click the 'Discovered Devices' tab
 - Select a company or a group to view the list of devices identified in that group Or
 - · Select 'Show all' to view every discovered device
- Select the devices that you want to change the category





• Select the device type from the drop-down






Click 'Change'

The category will change with appropriate icon in the device type column.

Remove Selected Devices from the 'Discovered Devices' list

- Click 'Network Management' > 'Devices'
- Click the 'Discovered Devices' tab
 - Select a company or a group to view the list of devices identified in that group Or
 - Select 'Show all' to view every discovered device
- Select the devices to be removed and click 'Delete Device'.






- Click 'Delete' in the confirmation dialog. The device will be removed from the list.
- If a deleted device is discovered again in subsequent scans, it will be shown as a new device.

Export Discovered Devices List

- Click 'Network Management' > 'Devices' > 'Discovered Devices'
- Click the 'Export' button above the table then choose 'Export to CSV':



The CSV file will be available in 'Dashboard' > 'Reports'



See Reports in The Dashboard for more details.


7.4. Manage Network Monitors

Click 'Network Management' > 'Monitors'

- A monitor is a script which tracks events on SNMP devices and takes specific actions if its conditions are
 met. For example, you can set up a monitor to alert you if a device is switched off for a certain length of
 time.
- Network monitors are added to network profiles, which are in-turn applied to your SNMP devices.
 - Click 'Network Management' > 'Profiles' to view and create network profiles.
 - Click 'Network Management' > 'Devices' to view discovered SNMP devices.
 - Click 'Network Management' > 'Discoveries' to create and run scans to find SNMP devices on your network.
- A single network monitor can be used in multiple network profiles. A single profile can include multiple monitors

View and manage monitors

Click 'Network Management' > 'Monitors'



Network Monitors - Column Descriptions	
Column Heading	Description
Monitor Name	The label of the network monitor
No. of Profiles	Show how many network profiles are using the monitor. Click the number to view a list of the profiles.
Created By	Admin that added the network profile
Created On	Date and time the profile was added
Last Modified By	Admin that most recently edited the profile
Updated On	Date and time the profile was most recently modified.
Controls	
Create Monitor	Configure a new monitor



	See Create a Network Monitor
Delete	Remove a monitor


- Use the funnel on the right to filter monitors by various criteria.
- Click a column header to sort items by ascending / descending/ alphabetical order

See the following links for more help:

- Optional Create a sub-folder in the My Monitors folder
- Create a network monitor
- Edit a monitor
- Delete a monitor
- View monitor details

Optional - Create a sub-folder in the My Monitors folder

- Click 'Network Management' > 'Monitors'
- To keep things organized, it is a good idea to create a sub-folder to house your SNMP monitors. You can
 create individual folders named after your target SNMP devices, or simply create a single folder for all
 SNMP monitors.
- Place your mouse on the 'My Monitors' folder and click '+'



- Name Enter an appropriate label for the sub-folder and click 'Add'
- Repeat the process to add more folders as required.






You can also add sub-folders to a sub-folder. You can now save **network monitors** in your new folders.

- Rename a sub-folder Place your mouse over it, click the pencil icon, enter a new name and click 'Save'
- **Delete a sub-folder** Place your mouse over it, click the trash can icon and confirm removal in the delete folder dialog.

Create a Network Monitor


- Click 'Network Management' > 'Monitors'
- Select the folder on the left in which you want save the monitor. All monitors are shown in 'My Monitors' irrespective of which you folder save them.
- Click 'Create Monitor'





- Monitor name Enter an appropriate label for the monitor, for example, 'Monitor for Switches'
- **Description** Any short notes about the monitor, if required.
- **Folder** Select which folder you want to save the monitor. Default is 'My Monitor'. Start typing the folder name and select from the suggestions.
- Click 'Create'. This opens the monitor, ready for you to configure.





- Monitor name, description and folder are what you configured in the previous step. Update if required.
- Trigger an alert if If the conditions that you configure in the 'Conditions' tab is breached, select when alert should be activated. The options are:
 - All of the conditions are met All rules that you configure in 'Conditions' tab is met.
 - Any of the conditions are met Any of the rules that you configure is met.
- Use alert settings Select the alert type that should be triggered. See 'Manage Alerts' to configure
 custom alerts and manage them.
- Trigger Alerts if Probe Device Cannot Reach the Monitored Device Alert is activated if the probe device(s) is not able to establish communication with the SNMP device.
- Click the 'Conditions' tab. This is where you configure rules for the monitor:




Click 'Add Condition' and select the item you want to monitor:





Next, specify the exact conditions of the rule:



• Click 'Create' to add the rule to the monitor:



- · Repeat the process to add more rules.
- Click 'Save'. The monitor will be available for selection when creating a network profile.


Edit a Monitor

- Click 'Network Management' > 'Monitors'
- Click the monitor name





· Click 'Edit' at top-right




- The monitor update process is similar to creating a monitor explained above.
 - 'Profiles' and 'Logs' screens are populated after the monitor is added to profiles. See 'View Monitor Details'
- Click 'Save' to apply your changes.

Delete a Monitor

If you delete a monitor, it will be removed from the applicable profiles also.

- Click 'Network Management' > 'Monitors'
- Select the monitor and click 'Delete Monitor'






Click 'Confirm'



View Monitor Details

- Click 'Network Management' > 'Monitors'
- Click the name of a network monitor. The monitor configuration interface opens at the 'General' tab:



The configuration interface lets you to:

- Edit the general settings and monitoring conditions
- View all profiles that use the monitor
- View the log of events related to the monitor from all SNMP devices on which the profiles with the monitor is applied


Edit a Monitor

See Edit Monitor section above.

View all Profiles that use the Monitor



- Click 'Network Management' > 'Monitors'
- Click the name of a network monitor.
- · Click the 'Profiles' tab



Network Profile - Table of Column Descriptions	
Column Heading	Description
Profile Name	The profile in which the monitor is active. • Click the profile name to open its configuration interface. See Create a Network Profile.
Created By	The admin that created the profile Click the name to view user details. See View User Details.

View Network Monitor Logs

- Click 'Network Management' > 'Monitors'
- Click the name of a network monitor.
- · Click the 'Logs' tab

The logs tab shows all instances where the conditions of the monitor were breached:




Network Monitor Logs - Table of Column Descriptions	
Column Heading	Description
Device Name	The SNMP device on which the breach occurred. • Click the name of the SNMP device to open its details interface. See SNMP Device Details Interface
Status	Whether or not the monitor is currently active for the device



Hit Count	Number of times the monitored conditions were breached
Last Hit Time	Date and time the monitoring rule was last breached
Last Update Time	Date and time when the information was last refreshed
Details	 Click the 'Details' link to view a log of the breach events See View Details of Network Monitor Logs (given below) for more information

View Details of Network Monitor Logs

Click the 'Details' link to view the details of the breaches of the monitoring conditions:



Details are shown under three tabs:

Logs - The date and time when the event occurred. Also shows the details of the monitoring rule that detected the event.

Network Monitoring Log Details - 'Logs' tab - Table of Column Descriptions	
Column Heading	Description
Time	Date and time of the event.
Status	The current state of the monitor on the device: On - The device is exceeding the thresholds of the monitor Off - The device is operating within the thresholds of the monitor
Additional Information	Details on the condition monitored and the breach

Tickets - Shows any service desk tickets which were automatically generated by the alert.





Network Monitoring Log Details - 'Tickets' tab - Table of Column Descriptions	
Column Heading	Description
Link	A link to the support ticket created for the breach event. • Click the link to open the ticket in service desk.
Status	Indicates whether the ticket is open or closed
Created On	The date and time at which the ticket was raised.

Statuses - Shows the current status of each condition in the monitor:



Network Monitoring Log Details - 'Statuses' tab - Table of Column Descriptions	
Column Heading	Description
Condition Type	The category of monitor. Click the type to view its exact conditions and thresholds. An example is shown below:
	«Online / offline» Condition
	Condition Period Device is offline 3 min Note: The monitor checks if a device stays offline or online longer than specified time period and triggers an alert. Do not use 'Device status' condition with other conditions in the same monitor. Please also note that 'Auto remediation' will not work with 'Device status' monitor.
Value	Condition set in the monitor
Status	The current state of the monitored parameter on the device. • Green - The device is operating within the thresholds of the monitor



	 Grey - Unknown Red - The device is exceeding the conditions of the monitor.
Status Changed at	The date and time of the last change in state of the monitored parameter.

8. Applications

Click 'Applications' in the left-menu to view this section.

Endpoint Manager provides visibility and control over the applications which are installed on user devices.

The applications area has the following sections:

- Mobile Applications View all applications installed on enrolled Android and iOS devices. Block any
 application identified as malicious. Once blacklisted, the application is not allowed to run on any device on
 which it is installed.
- Patch Management View a constantly updated list of OS and third party application patches available for managed Windows devices. The area lets you install or uninstall patches/updates as required.
- Global Software Inventory View all applications installed on your Windows devices. You can uninstall unwanted applications as required.
- **Vulnerability Management** Shows known weaknesses on your devices along with their common vulnerabilities and exposures (CVE) listing. You can run patches on affected devices.



Click the following links for more help:

- View Applications Installed on Android and iOS Devices
 - Blacklist and Whitelist Applications
- Patch Management
- View and Manage Applications Installed on Windows Devices
- Vulnerability Management




8.1. View Applications Installed on Android and iOS Devices

- Click 'Applications' > 'Mobile Applications'
- The 'Mobile Applications' interface shows all applications identified on enrolled Android and iOS devices. Additional details include the package name and the number of devices on which the app was found.
- You can blacklist application you feel are suspicious or not trustworthy.
- Blacklisted apps are blocked on any devices on which they are installed. EM also prevents them from being
 installed on other devices in future.

Access the 'Mobile Applications' interface

Click 'Applications' > 'Mobile Applications'.






Mobile Applications - Column Descriptions		
Column Heading	Description	
OS	The operating system on which the application runs.	
Name	Application label.	
	 Click the name of an application to open the 'Devices' interface that shows the list of only those devices on which the app is installed. 	
	This enables you to identify the devices using the application.	
Package	The package name or identifier of the package from which the app was installed.	
Number of Devices	The count of devices on which the app is found installed.	
Verdict	Whether the application is allowed or blacklisted.	
	Controls	
Add to Black List	Add selected applications to the global black list.	
	Blacklisted apps are blocked on any devices on which they are installed. EM also prevents them from being installed on other devices in future.	
	See Blacklist and Whitelist Applications the next section for more details.	
Remove from Black List	Release an application from the global black list.	
	Released applications are allowed to run on devices on which they are installed. They can also be installed in future on other devices.	
	See Blacklist and Whitelist Applications the next section for more details.	
Apply Changes to All Devices	Deploy the new settings to all devices.	
Export	Save the list of mobile applications as a comma separated values (CSV) file. See Export the List of Mobile Applications for more details.	

Sorting, Search and Filter Options

- Click any column header to sort the items based on alphabetical order of entries in that column.
- Click the funnel button T at the right end to open filter options.






Export the List of Mobile Applications

Export the list of mobile applications to a .csv file as follows:

- Click 'Applications' > 'Mobile Applications'.
- Click the 'Export' button above the table then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

8.1.1. Blacklist and Whitelist Applications

- Click 'Applications' > 'Mobile Applications'
- The mobile applications area shows a list of applications installed on all enrolled Android and iOS devices.
- You can review the list and decide which apps should be allowed or blocked.
- If a suspicious or malicious application is identified then it can be moved to the blacklist. This blocks the application on all devices and prevents other devices from installing the application in future.




Blacklisted files that are subsequently found to be trustworthy can be moved to the whitelist.

To move selected apps to blacklist

- Click 'Applications' > 'Mobile Applications'.
- Select the apps to be blocked.

Tip: You can filter the list or search for a specific app by using the filter options that appear on clicking the funnel icon at the top right.



- Click 'Add to Black List' on the top.
- Click 'Confirm' in the confirmation dialog.

The selected apps will be added to the 'Black List' and their status will change to 'Blocked'. The apps will be blocked at the devices on which they are currently installed, during the next polling cycle of the device.

 Click 'Apply Changes to All Devices' to instantly block the apps on the devices on which they are currently installed.


Unblock Blacklisted Apps

Applications that were blocked by mistake can be released from blacklist and allowed to be installed or run
on the devices.

Remove trustworthy apps from blacklist

- Click 'Applications' > 'Mobile Applications'.
- Select the apps with 'Blocked' status, to be whitelisted.





Click 'Remove From Black List' at the top.

The status of the apps will change to 'Allowed'. The apps will be allowed to run on the devices on which they are currently installed, during the next polling cycle of the device.

 Click 'Apply Changes to All Devices' to instantly change the status of the apps in the devices and allow them to run.

8.2. Patch Management


Click 'Applications' > 'Patch Management'

- The patch management area lets you install OS updates and patches for 3rd party applications on managed Windows devices.
- The area also lets you uninstall Windows updates and patches if you want to roll back to the previous version.
- You can also create procedures to deploy operating system and 3rd party application patches. The
 procedures can be added to profiles to automatically install any new patches.
- Patches need to be approved before it can be deployed on endpoints. Auto-approval is enabled by default.
- You can choose to decline patches so they are not deployed.
- You can filter patches by company and device group.

Tip: This area lets you manage patches across all devices in your network. As an alternative, you can manage patches on *individual* devices by clicking 'Devices' > 'Device List' > 'Device Management' > Click on a device > 'Patch Management'. See **View and Manage Patches for Windows and 3rd Party Application** to find out more.

Open the patch management interface


- Open Endpoint Manager
- Click 'Applications' > 'Patch Management':



The interface has two tabs:

- Operating System All OS patches available for deployment through Endpoint Manager.
 - Only approved OS patches are installed on endpoints.
 - Each patch has additional details such as classification, the Windows component to which the patch applies, severity, release date, installation status and links to knowledgebase articles.
 - The interface lets you install or uninstall selected patches on multiple devices. You can also generate a report on overall patch status.
 - See Manage OS Patches on Windows Endpoints for more details.
- Third Party Applications All updates available for 3rd party applications installed on managed Windows endpoints.
 - Only approved 3rd patches are installed on endpoints.
 - You can update selected applications on all required endpoints. See Install 3rd Party Application
 Patches on Windows Endpoints for more details.
 - See EM Supported 3rd Party Applications for a list of applications that we support for patching.

The slider at top-right contains links to help videos on various patch management tasks:




Use the videos to guickly learn about patch deployment tasks.

View patches by company / device group

The tree structure on the left shows all enrolled organizations and device groups:





- Type a company or group name in the search field to look for a specific entity
- Click a company name to view patches for all device groups under it
- Click '+' beside a company to view device groups under it
- Click a device group to view patches for devices belonging to that group
- Click 'Show all' to clear any selections and view all patches

8.2.1. Manage OS Patches on Windows Endpoints

Click 'Applications' > 'Patch Management' > 'Operating System' tab

- The operating system tab lets you deploy and manage OS updates on Windows devices.
- Endpoint Manager checks Microsoft update servers for available Windows patches and lists them in the
 interface. You can deploy patches to devices as required. You can also uninstall patches from devices if
 required.
- Patches need to be approved for deployment. You can choose to decline / approve patches. By default, patches are automatically approved.
- The interface shows details about each patch, including patch classification, the Windows component to which it applies, release date, severity, previous versions, Microsoft bulletins and number of endpoints which require the patch.
- You can filter patches by company and device group.
- You can hide patches if you do not want to deploy them. Hidden patches will not be available for deployment in the 'Device Management' screen and will not be executed if added to a patch procedure.
- You can also create procedures to deploy operating system and 3rd party application patches. The
 procedures can be added to profiles to automatically install any new patches.
- You can also generate reports on the current patch status of your Windows devices.

Manage operating system patches



- Click 'Applications' > 'Patch Management'
- · Select the 'Operating System' tab
 - Select a company or group to view updates for that entity's devices
 Or
 - · Select 'Show all' to view every available Windows update



'Operating System' Patch Management - Column Descriptions			
Column Heading	Description		
Title	The descriptive name of the patch.		
	 Click the name to view patch details. See View Patch Details for more information on this interface. 		
КВ	The knowledgebase article number that describes the patch.		
	Click the number to view the Microsoft Knowledgebase article on the patch.		
Bulletin	The Microsoft Bulletin number that contains details about the patch release.		
	Click the number to view the patch bulletin.		
Classification	The category of the patch. The possible values are:		
	Update - Fixes a specific non-critical problem, but not a security-related bug.		
	 Definition update - Contains updates to a product's definition database. For example, an update to the virus signature database for Windows Defender. 		
	 Critical Update - Fixes a specific, critical OS problem or a critical security- related bug 		
	Security update - Fixes a version specific, security related vulnerability		
	 Update rollup - Contains a collection of hotfixes, security updates, critical updates, and updates packaged together for easy deployment. These updates generally target a specific Windows component. 		
	 Driver - Adds software for controlling peripherals or add-on devices that could be connected to the endpoint 		
	Feature pack - Adds new functionality distributed after an OS release.		
	 Service pack - Contains a collection of hotfixes, security updates, critical updates, updates, and additional fixes. 		



	 Tool - Installs a utility or feature for a specific task or a set of tasks. Upgrades - Updates the Windows OS version on the endpoint to the latest build.
Product	The Windows component to which the patch applies.
Severity	The criticality of the patch. The possible levels are: Critical Important Low Moderate Unspecified
Status	Indicates whether the patch is ready for deployment. The statuses are: • Auto-Approved -You can install the patch • Approved -You can install the patch • Declined – You cannot deploy the patch • Waiting for approval – You cannot install the patch
Reboot	Whether or not the endpoint requires a restart to complete the patch installation.
Not Installed	 The number of managed endpoints on which the patch is yet to be installed. Click the number to view the patch details screen at the 'Device List' tab. See the explanation of View Details of a Patch for more details on the 'Patch Details' screen. The 'Device List' tab shows devices to which the patch is relevant. You can deploy the patch to those devices which need it. See Install a patch on selected endpoints for more details.
Installed	 The number of managed endpoints on which the patch has already been installed. Click the number to view the patch details screen at the 'Device List' tab. See View Details of a Patch for more details on the 'Patch Details' screen. The 'Device List' tab shows devices along with the installation status of the selected patch. You can select devices on which the patch is required and start the installation process. See the explanation of Install a patch on selected endpoints for more details.
Release Date	The date on which the patch was released by Microsoft.
	Controls
Install Patch(es)	Deploy selected patches to all devices on which they are yet to be installed. See Install selected patches on all managed endpoints at once for more details.
Uninstall Patch(es)	Remove selected patches from all devices on which they are installed. See Uninstall selected patches from all managed endpoints at once for more details.



Hide Patch(es)	Conceal selected patches that you do not want to be deployed onto enrolled endpoints.
	Hidden patches will not be visible in the 'Device Management' screen and will not be executed as well if added to a patch procedure.
Unhide Patch(es)	Reveal all hidden patches.
Export	Generate current patch statuses for the devices. See Generate Patch Statuses Report .
Create Patch Procedure	Add a new procedure capable of auto-installing patches on your endpoints.
	The procedure can be added to a profile and scheduled to install specific updates at specific times. See Create a New Patch Procedure for more.
Schedule Patch Procedure	Takes you to the 'Profiles' interface in Endpoint Manager.
	You can add a procedure to a profile which will install your selected updates onto your endpoints. See Procedure Settings in Profiles for Windows Devices for guidance on this.
Show hidden patch(es)	Reveal all hidden patches so they can be potentially deployed.
Approve	Only permitted patches are installed. See Approve / decline a Windows OS patch for more details.
Decline	Unapproved patches are not installed. See Approve / decline a Windows OS patch for more details.
Auto Approve	You can set the patches to be automatically approved.
	Enabled - Newly listed patches are automatically approved
	 Disabled – The status for newly listed patches shows as 'waiting for approval'. Disable this if you want to evaluate the patch and then approve / decline.

• Click any column header to sort the items in ascending/descending order of the entries in that column.

The 'Operating System Patch Management' interface allows you to:

- View Details of a Patch
- Hide Patches
- Restore Hidden Patches
- Install selected patches on all managed endpoints at once
- Install a patch on selected endpoints
- Uninstall selected patches from all managed endpoints at once
- Create a New Patch Procedure
- Approve / decline a Windows OS patch
- Search specific patches in the Patch Management interface
- Generate Patch Statuses Report

View Details of a Patch


- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab



 Select a company or a group to view the list of patches and Windows updates available for its devices

Or

- Select 'Show all' to view a list of all available patches and Windows updates
- Click the name of a patch to open its patch details screen.



The details of the patch are displayed under six tabs:

- **General** Shows the name and general description, version number, severity as set by the vendor, release date and a link to the knowledgebase (KB) article for the patch release.
- Vendor Indicates the publisher of the patch, with a link to the support page for the patch from the vendor
- Supercedes Contains information on previous patches that are replaced by this patch
- Bulletin Contains the Bulletin ID and a short summary of the bulletin published by the vendor for the patch



- CVE IDs Displays the Common Vulnerabilities and Exposure (CVE) Identity numbers set for the patch by the vendor.
- Device List The list of managed Windows endpoints with the installation status of the patch on them. You
 can install the patch on selected the endpoints from the list. See Install a patch on selected endpoints for
 more details.

Hide Patches


- You can hide those patches that you do not want to be rolled out to the endpoints, from the list.
- These patches will also be not available for deployment from the 'Device Management' screen and will not be executed as well if added to a patch procedure.
- You can view the hidden patches by using the 'Show hidden patch(es) toggle button and install these
 patches onto endpoints.

Hide unwanted patch(es)

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
 - Select a company or a group to view the list of patches and Windows updates available for its devices

Or

- Select 'Show all' to view a list of all available patches and Windows updates
- Select the patch(es) you want to hide and click 'Hide Patch(es)'



To view the hidden patches again, you have to **unhide** them.

Restore Hidden Patches

 Restored patches will also be available for installation in the Device Management interface and can be added to a patch procedure.




View hidden patches and restore them

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
 - Select a company or a group to view the list of patches and Windows updates available for its devices

Or


- Select 'Show all' to view a list of all available patches and Windows updates
- Click the funnel icon on the right, select 'Show hidden patch(es)' and click 'Apply'



The hidden patches are shown with dark gray background stripe.

• Select the hidden patch(es) from the list and click 'Unhide Patch(es)'






A confirmation message is displayed. The patches are re-added to the list.

Install patch(es) on all managed endpoints at-once

- Click 'Applications' > 'Patch Management'
- · Select the 'Operating System' tab
 - Select a company or a group to view the list of patches and Windows updates available for its devices

- Select 'Show all' to view a list of all available patches and Windows updates
- Select the patch(es) to be installed and click 'Install Patch(es)'





Click 'OK' in the confirmation dialog


The command will be sent and the selected patch(es) will be installed on all endpoint(s) in which the patch is not already installed.

Install a patch on selected endpoints

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
 - Select a company or a group to view the list of patches and Windows updates available for its devices

- Select 'Show all' to view a list of all available patches and Windows updates
- Click the number in the 'Not Installed' column of the patch you want to install.





The 'Patch Details' screen will open at the 'Device List' tab. The screen shows all managed devices to which the patch is relevant. The 'Installed' column tells whether the patch is installed on the device.

- Select the device(s) on which the patch is to be installed and click 'Install Patch'.
- A confirmation dialog will appear:

Patch(es) successfully added to install queue.

The command will be sent to the selected device(s) and a schedule will be created for installation of the selected patch(es) on the devices.


Uninstall selected patches from all managed endpoints at-once

You can remove unwanted patches and Windows updates from the managed devices. This is useful if you want the managed endpoints to be rolled back to the previous build version of Windows component or the OS itself.

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
 - Select a company or a group to view the list of patches and Windows updates available for its devices

- Select 'Show all' to view a list of all available patches and Windows updates
- Select the patch(es) to be removed from the devices and click 'Uninstall Patch(es)'





- Click 'OK ' in the confirmation dialog
- The command will be sent to the selected device(s) and a schedule will be created for uninstallation of the selected patch(es) on the devices.

Uninstall command successfully added to uninstall queue. The process may take a while to be completed.


Create a New Patch Procedure

- The 'Patch Management' > 'Operating System' interface lets you create a procedure to deploy OS patches.
- The procedures can be added to profiles and scheduled to run periodically.

Create a new patch procedure

- Click 'Applications' > 'Patch Management'
- · Select the 'Operating System' tab
- Click 'Create Windows Patch Procedure' at the top





The 'Create Windows Patch Procedure' wizard starts.


- Create a name and specify the storage folder for the procedure. Select the categories of OS patches you want to install and configure endpoint restart options.
- See creating an OS patch procedure for more help with the wizard.

Approve / decline a Windows OS patch

You can deploy only approved and auto-approved patches on endpoints. You can disapprove a patch so it cannot be deployed, for example, you want to evaluate whether the patch is required or not.

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
- Select a patch and click 'Approved' or 'Decline' button at the top






Auto Approve – Enable this button so when a new patch is listed here, it is automatically approved. If
disabled, the patch shows its status as 'Waiting for approval'.

Search specific patches in the Patch Management interface

- Click the funnel icon on the right to filter patches by various criteria, including by name, by KB number, by bulletin number, by classification, by severity, and by whether a restart is required for the patches.
- Start typing the name of a patch in the search field to find a particular patch. Select the patch from the search suggestions and click 'Apply'
- To display all items again, clear any filters and search criteria and click 'Apply'.
- EM returns 20 results per page when you perform a search. To increase the number of results displayed per page up to 200, click the arrow next to 'Results per page' drop-down.

Generate Patch Statuses Report

- Click 'Applications' > 'Patch Management'
- Select the 'Operating System' tab
- Click 'Export' at the top.



- The CSV file will be available in 'Dashboard' > 'Reports'
- See 'Reports' in 'Dashboard' for how to view and download reports.




8.2.2. Install 3rd Party Application Patches on Windows Endpoints

Click 'Applications' > 'Patch Management' > 'Third Party Applications'

- This area lets you apply patches and updates to 3rd party applications on Windows devices.
- EM checks the third party applications on endpoints in areas such as program files, registry, start menu, users appdata if any patches are available for them and lists on the interface.
- The interface lists all available patches along with details such as patch category, vendor name, and the number of devices which require the patch.
- Patches need to be approved for deployment. You can choose to decline / approve patches. By default, patches are automatically approved.
- You can filter patches by company and device group.
- You can hide those applications that you do not want to update.
 - Hidden applications will also not be available for update from the 'Device Management' screen. They
 will also be skipped if named in a patch procedure.
 - Click 'Show hidden patch(es)' to view hidden items.
- You can also create new procedures to deploy updates and patches for all or selected 3rd party applications. The procedures can be added them to profiles with a schedule to periodically install new patches and updates available on every execution.

Open the third party applications interface

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices
 Or
 - Select 'Show all' to view a list of all available third party application patches and updates



- Each row shows the name of the software that needs to be updated. It also shows you how many devices have the software installed and how many of those require the update.
- You can apply updates to all devices or to individual devices:
 - Patch All Use the check-boxes on the left to choose the software you want to patch. Click 'Install Patches' to apply the update to all devices which require patching.



 Patch Individual - Click the number in the 'Upgradable Devices' row > Select the devices you want to update > Click 'Install Patches'

Third Party Applications Table - Column Descriptions	
Column Heading	Description
Name	The label of the software. Click the name to view application details. See View Details of an Application for more details.
Vendor	The software publisher.
Category	The type of the application. Possible values include: Comodo Products Runtime applications Utilities Messaging File Compression utilities Developer Tools Documents Online Storage Other
Status	Indicates whether the patch is ready for deployment. The statuses are: • Auto-Approved -You can install the patch • Approved -You can install the patch • Declined – You cannot deploy the patch • Waiting for approval – You cannot install the patch
Installed Devices	Total number of devices on which the application is installed. This figure includes devices with patched and unpatched versions of the software.
Upgradable Devices	Number of devices which need to be patched because they are using an older version of the software.
	Controls
Install Patch(es)	Allows you to install the patches/updates.
Hide Patch(es)	Allows you to hide selected patches that you do not want to update. Hidden patches will not be available for deployment on the 'Device Management' screen and will not be executed as well if added to a patch procedure .
Unhide Patch(es)	Allows you to unlock hidden patches.
Create Patch Procedure	Starts the wizard to create a new 3rd party application patch procedure. You can create a new patch procedures to deploy updates and patches for all supported or selected 3rd party applications. The new procedures can be added to profiles and



	scheduled to install selected updates onto your endpoints. See Create a New 3rd Party Application Patch Procedure for more details.
Schedule Patch Procedure	Takes you to the 'Profiles' interface in Endpoint Manager. You create new or edit an existing Windows profile and add/edit the 'Procedures' component in it to create a schedule for running a patch installation procedure on endpoints on which the profile is active. See Procedure Settings in Profiles for Windows Devices for guidance on this.
Show hidden patch(es)	Allows you to view hidden patches and, if required, install them on endpoints. Use the toggle button to hide / view hidden applications.
Approve	Only permitted patches are installed. See Approve / decline a third party application patch for more details.
Decline	Unapproved patches are not installed. See Approve / decline a third party application patch for more details.
Auto Approve	You can set the patches to be automatically approved.
	Enabled - Newly listed patches are automatically approved
	 Disabled – The status for newly listed patches shows as 'waiting for approval'. Disable this if you want to evaluate the patch and then approve / decline.

- Click any column header to sort items in ascending/descending order of entries in that column.
- Click the funnel icon on the right to search for applications by name, vendor and/or category.
- See 'EM Supported 3rd Party Applications' for a full list of supported 3rd party applications.

The 'Patch Management' > 'Third Party Applications' interface allows you to:


- · View Details of an Application
- Hide Applications
- Restore Hidden Applications
- Update selected applications on all upgradable devices at once
- · Update an application on selected devices
- Create a New 3rd Party Application Patch Procedure
- Approve / decline a third party application patch

View Details of an Application

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices

- Select 'Show all' to view a list of all available third party application patches and updates
- Click the name of any application to open its application details screen





The details of the application are displayed under two tabs:

- **General** Displays the name, software publisher and the category of the application.
- **Device List** Displays the list of managed devices on which the application is installed, with the details like the installed version, installation path and the device owner. You can update the application on the devices where required from this screen. See **Update an Application On Selected Devices** for more details.

Hide Applications


- You can hide those applications that you do not want to update
- These applications will also be not available for update from the 'Device Management' screen and will not be executed as well if added to a patch procedure.
- You can view the hidden applications by using the 'Show hidden patch(es) toggle button and update these
 applications on selected on devices.

Hide upgradable applications

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices

- Select 'Show all' to view a list of all available third party application patches and updates
- Select the application(s) to be hidden from the list and click 'Hide Patch(es)'





A confirmation is displayed. The selected applications are hidden from the list.


- To view the hidden applications, click the funnel icon, select 'Show hidden patch(es)' and click 'Apply'
- To re-add the hidden applications to the list, you have to unhide them.

Restore Hidden Applications

- You can re-add the hidden applications to the 'Third Party Applications' interface.
- Restored applications will also be available for being updated from the **Device Management** interface and can be added to a **patch procedure**.

View hidden upgradable applications and restore them


- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices
 Or
 - Select 'Show all' to view a list of all available third party application patches and updates
- Click the funnel icon on the right, select 'Show hidden patch(es)' and click 'Apply'





The hidden applications are shown with dark gray background stripe.


• Select the hidden app(s) from the list and click 'Unhide Patch(es)'



A confirmation is displayed. The applications are re-added to the list.

Update Selected Applications on All Upgradable Devices at once

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices
 - · Select 'Show all' to view a list of all available third party application patches and updates
- Select the application(s) to be updated, click 'Install Patch(es)' and choose 'Update to Latest Version'



A command is sent to Communication Client (CC) on the devices to commence the update.




- Once the command is received, CC checks whether the update has already been downloaded by other devices in the network.
 - If the update is available, CC establishes a peer-to-peer network with the device and downloads the patch. This reduces bandwidth usage as the update is downloaded from the local network.
 - If the update is not available on any devices in the local network, CC downloads the update from the EM patch portal.

Update an Application on Selected Devices

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
 - Select a company or a group to view the list of third party application patches and updates available for its devices

Or

- Select 'Show all' to view a list of all available third party application patches and updates
- Click the number in the 'Upgradable Devices' column of the application to be updated



The application details screen will appear with the 'Device List' tab open, with a list of devices on which the application can be updated.

- Select the device(s) on which the application is to be updated
- Click 'Install patch(es)' and choose 'Update to Latest Version'

A command will be sent to the endpoint(s) to schedule installation of the patch/update the application to the latest version.

Command «Update to the Latest Version» successfully sent

A command is sent to Communication Client (CC) on the devices to commence the update.

- Once the command is received, CC checks whether the update has already been downloaded by other devices in the network.
 - If the update is available, CC establishes a peer-to-peer network with the device and downloads the patch. This reduces bandwidth usage as the update is downloaded from the local network.




 If the update is not available on any devices in the local network, CC downloads the update from the EM patch portal.

Create a New 3rd Party Application Patch Procedure

- The third party applications interface lets you to create a new patch procedures for periodical updates and deployment of patches for all or selected 3rd party applications.
- The procedures can be added to profiles and scheduled to run periodically.
- The new patches and updates available for the selected applications are deployed on the endpoints to which the profile is applied during every execution of the procedure.

Create a new procedure

- Click 'Applications' > 'Patch Management'
- Select the 'Third Party Applications' tab
- Click 'Create Windows Patch Procedure' at the top



The 'Create 3rd Party Patch Procedure' wizard starts.

- The wizard allows you to set a name for the procedure, select the folder in which it is to be stored, select the applications to be updated and configure the restart options for the endpoints after the installation of the updates.
- Please see the explanation of creating an 3rd party application patch procedure in Create a Custom Procedure for detailed guidance on the wizard.



8.2.2.1. EM Supported 3rd Party Applications

The following table provides the names of third party applications that can be updated on enrolled Windows endpoints:

- 7-Zip
- ActivePresenter
- ActiveState Komodo Edit
- Adblock Plus for IE
- Adobe Acrobat Reader DC
- Adobe AIR
- Adobe Digital Editions
- Adobe Flash Player ActiveX
- Adobe Flash Player NPAPI
- Adobe Flash Player PPAPI
- Adobe Shockwave Player
- Advanced Installer
- Advanced IP Scanner
- AIMP
- AirDroid
- AirParrot
- AirServer Universal
- Amazon kindle
- Ant Movie Catalog
- Ant Renamer
- AnyBurn
- AnvDVD
- AOMEI Partition Assistant Lite Edition
- AppGate Client
- AppInventor Setup
- Apple Application Support
- Apple Application Support (64-bit)
- Apple Mobile Device Support
- Apple Software Update
- Ares
- Audacity
- · Aurora Blu-ray Media Player
- Auslogics Browser Care

- Glary Utilities PRO
- GlassWire
- GlobalMapper
- Google Drive File stream
- GOM Audio
- GOM Player
- GoodSync
- Google Chrome
- Google Drive
- Google Earth
- Google Earth Pro
- Go to connect
- GPL Ghostscript
- Greenshot
- grepWin
- HardCopy Pro
- HeliosPaint
- HelpNDoc Personal Edition
- HipChat
- Honeycam
- Honeyview
- Hotspot Shield
- HttpWatch Basic
- Hugin
- IE7Pro
- iDailyDiary
- IDrive
- IIS
- ImgBurn
- InfoSlips ForMe Viewer
- iReport
- IrfanView
- iTunes
- IZArc
- JabraDirect

- PicPick
- PKZIP for Windows
- Plantronics Hub Software
- Plex Media Server
- PNotes.NET
- Poedit
- PotPlayer
- PrimoPDF
- PrintKey-Pro
- proCertum CardManager
- Progress Telerik Fiddler
- PSPad editor
- PuTTY release
- qBittorrent
- QTranslate
- QuickBooks Desktop File DoctorQuickTime 7
- RD Tabs
- Recuva
- Reflector
- Remote Control by ITarian
- RenWeb.com
- Revo Uninstaller
- Revo Uninstaller Pro
- R for Windows
- Rocketduck
- RingCentral Meetings
- RingCentral Meetings Outlook Plugin
- RingCentral for Windows
- RJ TextEd
- RStudio
- Safari
- Sandboxie
- SciTE Text Editor



- · Auslogics Disk Defrag
- Auslogics Duplicate File Finder
- Auslogics Registry Cleaner
- Auslogics Registry Defrag
- AutoIt
- Avant Browser
- AVS Document Converter
- AVS Image Converter
- AVS Media Player
- AVS Video Editor
- AxCrypt
- AXIS Media Control Embedded Installer
- Bandicut
- Bandizip
- Belarc Advisor
- Beyond Compare
- Bing Desktop
- BitComet
- Bitl ord
- Blender
- Blio
- Bluebeam Vu
- BLUEJ
- Blue Jeans
- BOINC
- Bullzip PDF Printer
- Cabos
- calibre
- CCleaner
- CCleanerPro
- CDBurnerXP
- Charles
- Chilkat ActiveX
- Cisco Webex Meetings Desktop App 39.4.2.103
- · Cisco webex teams
- Citrix Group Policy Management

- Java(TM) Update
- Java SE Development Kit
- jing
- Jitsi
- JRE
- K-Lite Codec Pack Basic
- K-Lite Codec Pack Full
- K-Lite Codec Pack Standard
- K-Lite Mega Codec Pack
- KeePass Password Safe 1
- KeePass Password Safe 2
- Kerio Outlook Connector
- Kingsoft Office 2013
- Kobo
- Krita
- LatencyMon
- LibreOffice
- Lightshot
- Linphone
- Logitech SetPoint
- LogMeIn Client
- LogMeIn Hamachi
- MailStore Client
- MailStore Outlook Add-in
- Malwarebytes
- MathType
- McAfee Security Scan Plus
- MediaInfo
- MediaMonkey
- Media Player Classic Home
- MeshLab 64b 2016
- Microsoft AntiXSS
- Microsoft Baseline Security Analyzer
- Microsoft Power BI Desktop
- Microsoft PowerPoint Viewer
- Microsoft Security Client
- Microsoft Silverlight
- Microsoft SQL Server 2008

- Scilab
- ScreenConnect
- Screenpresso
- Scribus
- SeaMonkey
- ShadowCopy
- Silverjuke
- SimplySign Desktop
- Skype
- Slik Subversion
- SmartCam
- Smart Defrag
- Spark
- Speccy
- Spiceworks Desktop
- · SplashID Safe
- Splashtop Streamer
- Spybot Search & Destroy
- Steam
- Sticky Password
- SugarSync
- SumatraPDF
- SyncBackFree
- Synology Surveillance Station Client
- Tableau Reader
- Taksi Desktop Video Recorder
- TeamSpeak Client
- TeamViewer
- TED Notepad
- Tekla BIMsight
- TenClips
- TeraCopy
- TestNav
- TextPad
- TIBCO Jaspersoft Studio final
- TightVNC
- TomTom HOME



- Citrix Receiver
- Citrix Receiver LTSR
- Citrix ShareFile Sync
- Citrix Workspace 19.5.0.26
- Classic Shell
- Code42 server
- CollageIt
- Collagerator
- Combined Community Codec Pack
- Comodo IceDragon
- <removed Remote Control by ITarian bullet>
- Converber
- CPUID CPU-Z
- CrashPlan
- CryptoPrevent
- CrystalDiskInfo
- CutePDF Writer
- Cyberduck
- D&D Interceptor
- DAEMON Tools Lite
- DC++
- Defraggler
- Desktop Restore
- Dell support assistant
- DisplayCAL
- DriveImage XML
- Druva inSync
- Dual Monitor Tools
- DU Meter
- Duplicate Cleaner Pro
- DVD Flick
- DYMO Label
- Easy 7-Zip
- Easy Thumbnails
- EditPad Lite
- eM Client
- eMuleTorrent
- EncryptOnClick

- R2 Native Client
- Microsoft SQL Server 2017 T-SQL Language Service
- Microsoft Sync Framework Runtime v1.0 SP1
- Microsoft Sync Framework Services v1.0 SP1 (x86)
- Microsoft Visio Viewer 2013
- Microsoft Visual C++ 2008 Redistributable
- Microsoft Visual C++ 2012 Redistributable
- Microsoft Visual C++ 2017 x86 Additional Runtime
- Microsoft Visual Studio Code
- Microsoft Web Deploy
- mimecraft
- MimioStudio
- Miranda IM
- MobaXterm
- MongoDB
- MozBackup
- Mozilla Firefox en-GB
- Mozilla Firefox en-US
- Mozilla Firefox ESR
- Mozilla Thunderbird
- MozyHome
- MozyPro
- Mp3tag
- MSXML 4.0 SP3 Parser
- Mumble
- MX5
- MyDefrag
- MySQL Connector/C
- MySQL Connector/ODBC
- MySQL Installer -Community
- MySQL Notifier
- MySQL Workbench 6.3 CE
- NeoLoad

- Total Commander
- TortoiseSVN
- TortoiseGit
- TOSHIBA Password Utility
- TreeSize Free
- Trillian
- TSPrint Client
- TSR Watermark Image software version - Free version
- TUGZip
- Tux Paint
- UltraVnc
- UniPDF
- Universal Extractor
- Unlocker
- Uplay
- VirtualCloneDrive
- VitalSource Bookshelf
- VLC media player
- VMware Horizon Client
- VMware Player
- VMware vCenter Converter Standalone
- VNC Enterprise Edition
- VNC Server
- VNC Viewer
- VSDC Free Video Editor version
- VulkanSDK
- VyprVPN
- Waterfox
- Wave Editor
- WebStorage
- WildTangent Games App
- Winamp
- WinDjView
- Windows Live Sync
- Windows Movie Maker
- Windows Phone app for desktop



- Enpass
- EPI
- Epic Games Launcher
- EPIM-Outlook Sync
- EssentialPIM
- EssentialPIM pro
- Evernote
- exacqVision Client
- Exact Audio Copy
- Exsate VideoExpress
- FastStone Capture
- FastStone Image Viewer
- FileZilla Client
- Firebird
- FlashGet
- Foobar
- Fotosizer
- Foxit Advanced PDF Editor
- Foxit PhantomPDF
- Foxit Reader
- Free Download Manager
- FreeFixer
- Free RAR Extract Frog
- FrontMotion Firefox Community Edition (en-US)
- Frontmotion Firefox Community Edition ESR
- FSASecureBrowser
- GetGo Download Manager
- glmageReader
- GIMP
- Git version
- · Glary Utilities

- NetBeans IDE
- NetSetMan
- Nextcloud
- Nitro Pro
- Node.js
- NoMachine
- Notepad++
- NoteTab Light
- nPassword
- OCS Inventory NG Agent
- OpenOffice
- OpenVPN
- Opera Stable
- Oracle VM VirtualBox
- Origin
- ownCloud
- paint.net
- Pale Moon
- Parallels Client
- pCloud
- pCon.planner STD
- PDF-Viewer
- PDF-XChange Editor
- PDF24 Creator
- PDFCreator
- PDFill FREE PDF Tools
- PDFsam Basic
- PDFTools Version
- PeaZip
- Personal Backup
- PhotoFilmStrip

- WinHTTrack Website Copier
- WinMerge
- WinRAR
- WinSCP
- WinSnap
- WinZip
- Wireshark
- · Wise AD Cleaner
- Wise Care 365
- Wise Disk Cleaner
- Wise Folder Hider
- Wise Force Deleter
- Wise Memory Optimizer
- Wise Registry Cleaner
- Wiztree
- XAMPP
- XMind
- XnConvert
- XnView
- Xvid Video Codec
- Zimbra Connector for Microsoft Outlook
- Zimbra Desktop
- ZIPI
- Zoiper
- Zoom
- Zoom Player
- Zotero




8.3. View and Manage Applications Installed on Windows Devices

- Click 'Applications' > 'Global Software Inventory'
- The global software inventory shows all applications installed on managed Windows devices.
- The interface also shows details about each application. Details include the software vendor and the number of devices on which the app is installed.
- You can have the option to uninstall applications from all Windows devices at-once

To open the 'Global Software Inventory' interface

- Click 'Applications' > 'Global Software Inventory'
 - Select a company or group on the left to view applications installed on devices in it
 Or
 - Select 'Show all' to view applications on every Windows device enrolled to Endpoint Manager



Global Software Inventory - Column Descriptions	
Column Heading	Description
Title	Label of the application.
	 Click the name of an application to view its details and a list of endpoints on which it is installed.
	The app details screens also lets you uninstall the application from devices.
	See View Details of an Application for more details.
Application Category	The genre of the application. For example, 'Productivity', 'Security', 'Entertainment' etc.
Vendor	The publisher of the software/application
Installed Devices	The number of devices on which the app is installed currently.
Controls	
Uninstall	Uninstalls the selected application from all Windows devices at-once. See Remotely Uninstall an Application from all Devices for more details.

The global software inventory lets you:


View details of an application



- Remotely uninstall an application from selected devices
- Remotely uninstall an application from all devices

Sorting and Filtering Options

- · Click any column header to sort the items in ascending or descending order
- Click the funnel button \(\bar{\cup} \) at the right end to open the filter options.



View Details of an Application


The 'Global Software Inventory' interface allows you to view the information about an application and the list of devices on which it is found. You can also remove the application from selected devices on which it is not required.

Note: The application details is available only for applications supported by EM. See **EM Supported 3rd Party Applications** to view the list of supported applications.

View the details of an application

- Click 'Applications' > 'Global Software Inventory'
 - Select a company or group on the left to view applications installed on devices in it
 Or
 - Select 'Show all' to view applications on every Windows device enrolled to EM
- Click on the name of a supported application to view its details






The application details interface contains two tabs:

- **Application Info** General information about the application. This includes a short description of the application, the vendor, category, the available versions and more.
- **Device List** The devices on which the application was found installed. You can select the devices and uninstall the application from them.





Device List - Column Descriptions	
Column Heading	Description
Name	The label of the Windows device.
	Click the name of a device to open its device details interface
	See Manage Windows Devices for more details
Version	The version number of the application installed in the device
Path	The installation location of the application
Owner	The device user.
	 Click the user name to open the 'View User' interface. See View User Information for more details.
Controls	
Uninstall	Allows your to remotely uninstall the application from selected Windows devices. See Uninstall a Windows Application from Selected Devices for more details.

8.3.1. Uninstall a Windows Application from Selected Devices

The global software inventory lets you remotely remove unwanted applications from selected Windows devices.

Note: You can only remove applications which are supported by EM. See the list at **EM Supported 3rd Party Applications**.


To uninstall an application from selected devices:

- Click 'Applications' > 'Global Software Inventory'
 - Select a company or group on the left Or
 - · Select 'Show all' to view applications on every enrolled device
- · Click the name of an application to open its details interface
- Click the 'Device List' tab





- Select the devices and click the 'Uninstall' button at the top
- An uninstall command will be sent to the selected devices.
- You will see the following message if the software cannot be uninstalled without notifying the device user:



Click 'Proceed' to continue with the uninstall.

The application will be uninstalled from the selected devices.

Tip: You can remove apps from an individual device by using the device's details page. See **View and Manage Applications Installed on a Device** for more details.

8.3.2. Uninstall a Windows Application from All Devices


The global software inventory lets you remove unwanted applications from multiple Windows devices.

Note: You can only remove applications which are supported by EM. See the list at **EM Supported 3rd Party Applications**.


To uninstall an application from all Windows devices

- Click 'Applications' > 'Global Software Inventory'
 - Select a company or group on the left Or
 - Select 'Show all' to view applications on every enrolled device
- Select the application and click the 'Uninstall' button





- The uninstall command is sent to all devices which have the application installed.
- You will see the following message if the software cannot be uninstalled without notifying the device user:



Click 'Proceed' to continue with the uninstall.

The application will be uninstalled from the selected devices.

Tip: You can uninstall an application from an individual Windows device from its Device Details interface. See **View** and **Manage Applications Installed on a Device** for more details.




8.4. Vulnerability Management

- Click 'Applications' > 'Vulnerability Management' to open this interface
- This area lets you view known weaknesses found on your devices, along with their CVE (common vulnerabilities and exposures) rating.
- You can view which devices are affected and install patches as required.

Open the vulnerability management interface

Click 'Applications' > 'Vulnerability Management'



There are two tabs, each of which offers a different view of the vulnerabilities:

Vulnerability List - A list of discovered vulnerabilities and the number of devices affected by each.


Apply corrective patches:

- Click the number in the 'Target Device Count' column
- Select the devices you want to patch
- Click the 'Install Patch' button above the table
- Vulnerable Devices A list of devices affected by listed vulnerabilities. Allows you patch affected device
 with a single click.

Vulnerability List

- Click 'Applications' > 'Vulnerability Management'
- Click the 'Vulnerability List' tab





Vulnerability List - Column Descriptions	
Column Heading	Description
Vulnerability Name	The vulnerability identifier. This is same as the CVE code.
Vendor	Developer of the affected software and the corresponding patch
CVE Addressed	Identification code of the security threat. Click this to view vulnerability details, vendor and affected devices.
Severity	Criticality of the vulnerability. The possible levels are:
	 Critical - Vulnerabilities that can be exploited without warnings or prompts. Examples include remote elevation of privileges exploits that allow attackers to write to the file system, or execute arbitrary code without user interaction. You should patch critical vulnerabilities as soon as possible.
	 Important - A vulnerability which could compromise the confidentiality, integrity, or availability of user data if exploited. The distinguishing factor between critical and important is that important vulnerabilities show some warning or prompt to the user. For example, local escalation of privilege exploits, or the execution of arbitrary code which requires extensive user action. Again, you should patch important vulnerabilities as soon as possible.
	Moderate - The likelihood of exploit is largely mitigated by factors such as default configuration, auditing, or difficulty of exploitation. Moderate vulnerabilities usually require specific scenarios, locations or other prerequisites. We recommend you consider patching moderate vulnerabilities.
	 Low - A vulnerability whose exploitation is extremely difficult, or whose impact is minimal. We recommend applying low severity updates at your discretion.
	Unspecified - The patch was issued without a severity rating.
Target Device Count	Number of devices affected by the vulnerability. Click this to view device details and implement patches.

- Click the funnel icon to filter vulnerabilities by various criteria
- Click a column header to sort in ascending / descending / alphabetical order

From this interface you can:

View details of a vulnerability threat




Run a security patch on devices

View Details of a Vulnerability Threat

- Click 'Applications' > 'Vulnerability Management' then the 'Vulnerability List' tab
- Click the CVE ID number in the CVE Addressed column

The CVE details has three tabs, General, Vendor and Devices. By default the general tab is open in the CVE details screen.

• General - Provides the CVE details such as the name of the vulnerability type, published date and so on.



Click the vendor tab.





- Vendor Name The software publisher's name
- **Support URL** Clicking the link will take you to the technical community page that provides full information about the vulnerability, discussions, solutions and so on.

Click the devices tab.




 Shows the affected devices. You can run security patches for devices from here. See 'Run a Security Patch on Devices'

Run a Security Patch on Devices

You can run security patches targeted to address a particular CVE security threat.

- Click 'Applications' > 'Vulnerability Management' then the 'Vulnerability List' tab
- Click the number in the target device count column or click the CVE ID number in the CVE Addressed column then the 'Devices' tab



- Device Name Clicking the name will take you to the patch management section in the device summary page
- Owner Name Clicking the name will take you to user information page
- Customer The name of the organization the device is assigned to.
- Select the device and click 'Install Patch' above

A confirmation message is shown:




Patch(es) successfully added to install queue.

Vulnerable Devices

This screen lets you view devices that are affected by vulnerabilities and install patches as required. The 'Install Patches' button will install every required patch.

• Click 'Applications' > 'Vulnerability Management' then the 'Vulnerable Devices' tab



- **Device Name** Affected device. Click the name to view the patches available for the device.
- Owner Name User of the device. Click the name to view the user's details.
- Customer The name of the organization to which the device is assigned.

Install security patch(es)

• Select the devices you want to patch then click the 'Install Patch(es)' button.

You will see the following confirmation message:

Patch(es) successfully added to install queue.

All available patches are installed.



9. Application Store

 The 'Application Store' is a repository of useful applications which can be pushed to iOS, Android and Windows devices.


Android and iOS Applications

- You can add both mandatory and optional apps to the repository. You can update all devices with one-click of the 'Inform Devices Now' button.
 - Google Play and Apple App Store Specify the app name or bundle identifier. Endpoint Manager will automatically fetch the app details. The device owner will be taken to the Google Play page/App Store page to install the app.
 - Custom 'Enterprise' applications You can also upload your own .apk (Android) or .ipa (iOS) files to
 the app store. The communication client on the device collects the app from Endpoint Manager and
 installs it.
- Apps in the repository are automatically synchronized with enrolled devices every 24 hours. Notifications
 are sent to devices if new apps are ready to be installed. You can also manually sync apps if required.
 Users will be informed if there are new apps awaiting installation.

Windows Applications

- Endpoint Manager comes with a built-in list of popular Windows applications.
- Applications can be installed on all managed devices or selected devices.
- You cannot edit or remove applications from the list

The 'Application Store' tab contains three sub tabs, iOS Store, Android Store and Windows Application Store.



The following sections contain more details on each app type:


- iOS Apps
 - Add iOS Apps and Installing them on Devices
 - Manage iOS Apps
- Android Apps
 - Add Android Apps and Installing them on Devices
 - Manage Android Apps



- Windows Apps
 - Install Windows Apps on Devices

9.1.iOS Apps

- Click 'Application Store' > 'iOS Store'.
- The iOS store area contains all available iOS apps that have been uploaded to Endpoint Manager. You can
 deploy selected apps to all managed devices or specific devices.
- You can add new apps from the Apple store or upload your own custom enterprise apps. You can synchronize the app list with managed iOS devices and edit existing app parameters.
- You can specify whether an app is a mandatory install or an optional install.




'iOS App Catalog' - Column Descriptions		
Column Heading	Description	
Name	Application label.	
	 Click on the name to view app description, version number, bundle ID, category, supported devices, mandatory/optional setting and download URL. 	
	 You can also edit app details from here. See Manage iOS Apps for more details. 	
Туре	App class as determined by the source of the app. Possible types are:	
	iOS App Store	
	iOS Enterprise (apps uploaded by an admin)	
Application ID	The bundle identifier of the app. This is a unique id used by Apple to identify an app.	
Supported Devices	Types of devices with which the app is compatible.	
License Type	Whether the app is a free, paid or enterprise version.	



Mandatory	Whether or not it is compulsory for managed devices to install the app. Admins can set if an app should be mandatory. See 'Add iOS Apps and Install them on Devices' for more details.	
Added	The date and time at which the app was added to repository.	
Controls		
Add Enterprise Application	Add custom applications to Endpoint Manager by simply uploading the .ipa package files of the apps. See Add iOS Apps and Install them on Devices for more details.	
Add App Store Application	Add applications from the Apple store by typing the app name. See Add iOS Apps and Install them on Devices for more details.	
Inform Devices Now	Synchronize enrolled Android devices with the latest app list.	
Delete Application	Remove an application from the iOS app repository.	
Export	Save a copy of the app list as a comma separated values (csv) file. See Export the List of iOS Applications for more details.	

Export the List of iOS Applications

- Click 'Application Store' > 'iOS Store'.
- Click the 'Export' button above the table then choose 'Export to CSV':




- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Sorting, Search and Filter Options

- Click a column header to sort items in alphabetical order of entries in the column.
- Click the funnel button T to open the filter options.





Click the following links for more help:

- Add iOS Apps and Install them on Devices
- Manage iOS Apps

9.1.1. Add iOS Apps and Install them on Devices

- You can add apps to Endpoint Manager directly from the Apple store or by uploading a custom app.
- Apps can be installed on all or selected iOS devices


Please see the following sections for more help:

- Add iOS Apps from the App Store
- Add Custom/Enterprise iOS Apps




Add iOS Apps from the App Store


- Click 'Application Store' > 'iOS Store'
- Click the 'Add App Store Application' button:



- Type the first few letters of the app in the 'Name' field on the form. Endpoint Manager will search for matching apps from the store.
- Select the correct app from the list of suggestions. The rest of the form will be auto-populated by the app details.
- Click 'Save' after confirming the details.
- The app will be added to the repository and listed in the 'iOS Store' interface. It will be synced to devices during the next cycle.
- Click 'Inform Devices Now' if you want to immediately notify devices to install the app:







	Apple Store Application - Table of Parameters			
Form Element	Туре	Description		
Name	Text Field	The label of the application. • Enter the first few letters of the app name. • EM searches for matching apps in the app store		
Version	Text Field	The version number of the application. This field is auto-populated after entering the app name.		
iTunes Store ID	Text Field	The Apple identification number of the app. This field is auto-populated after entering the app name.		
		Usually, this number will appear after ID in the download URL of the app. For example, in the URL https://itunes.apple.com/us/app/ITSM/id807480077 , the numbers after ID is the iTunes Store ID for this app.		
Application ID	Text Field	The bundle ID of the app. This field is auto-populated after entering the app name.		
		For example, the bundle ID for EM client is com.comodo.ITSM.client		



	Apple S	tore Application - Table of Parameters
Form Element	Туре	Description
License Type	Radio	Specify whether the app is free or a paid version.
	Button	This option is pre-populated by the app chosen in the 'Name' field.
Category	Drop-down	The classification of the application. The category field will be auto-populated depending on the app chosen in the 'Name' field
		The drop-down also enables you to choose the category to which the app belongs.
Supported devices	Drop-down	The category of devices on which the app can run.
		The device type will be auto-selected depending on the app chosen in the 'Name' field.
		The drop-down also enables you to choose the device types to which the app is compatible.
Description	Text Field	The 'Description' filed will be auto-populated with the description of the selected app, from the App Store page.
		The text field also enables you to enter your description or edit the existing description.
Mandatory app	Checkbox	Specify whether or not it is compulsory that devices install this app. If enabled, all enrolled devices will get alerts automatically to install the app.
		See Install Apps on Android/iOS Devices for more details.
Allow backup of the app data	Checkbox	Allows user to backup the application along with its user data to iTunes.
Remove app when device management profile is removed	Checkbox	The app will be deleted from devices if the profile applied to the device is removed.
Remove from device when removed from app catalog	Checkbox	The app will be deleted from devices if it is removed from 'iOS Store'.
Application logo	'Browse' Button	The application logo will be automatically fetched from the App Store for the app chosen in the name field. If you want to change the logo, upload a new logo from the local computer by clicking 'Browse'.
Application screenshots	'Browse' Button	The application screenshots will be automatically fetched from the App Store for the app chosen in the name field. If you want to add new screenshots from the local computer, upload them by clicking 'Browse'.


Add Custom/Enterprise iOS Apps

- · Custom applications can be added to the repository by simply uploading the app .ipa file
- Most app details, such as name, version and ID, will be automatically fetched by parsing the file. You just need to manually enter some remaining details


Add Custom/Enterprise iOS Apps

- Click 'Application Store' > 'iOS Store' to open the interface
- Click 'Add Enterprise Application' from the options at the top.





- Click 'Browse' beside 'Source File', select the .ipa file you want to upload and click 'Open'
- The file will be uploaded. Many form field details are auto-populated from the file itself:






	Add iOS En	terprise Application - Table of Parameters
Form Element	Туре	Description
Name	Text Field	Application label. Auto-populated from the .ipa file Enter the name of the app if not auto-populated
Version	Text Field	The version of the application as obtained from the .ipa file. • Enter the version number, if it is not auto-populated
Application ID	Text Field	The app's unique identifier as obtained from the .ipa file. Usually, this number will appear after ID in the download URL of the app. For example, in the URL https://itunes.apple.com/us/app/ITSM/id807480077, the numbers after ID is the iTunes Store ID for this app.
Category	Drop-down	Select the app classification.
Supported devices	Drop-down	Select the category of the devices to which the app is compatible.
Description	Text Field	Enter a description for the app.
Mandatory app	Checkbox	Specify whether the app should compulsorily be installed on devices. If enabled, all enrolled devices will be alerted to install the app.
		See Install Apps on Android/iOS Devices for more details.
Allow backup of the app data	Checkbox	Allows to backup the application along with its user data to iTunes.
Remove app when device management profile Is removed	Checkbox	The app will be automatically uninstalled if the EM profile applied to the device is removed.
Source file	Browse button	Navigate to the storage location of the .ipa file to be uploaded and select the file.
Application logo	Browse button	Upload the logo image for the app.
Application screenshots	Browse button	Upload screenshots of the app, if required.



- Click 'Save' after confirming all details.
- The app will be added to the repository and listed in the 'iOS Store' interface. It will be pushed to devices on the next sync-cycle.
- Click 'Inform Devices Now' if you want to push the app to devices immediately.




9.1.2. Manage iOS Apps

The 'iOS Apps' interface lets you view and edit app details, and remove unwanted apps from the repository.

- Click 'Application Store' > 'iOS Store'
- Click the name of an app.





The details page contains a product description and various other info about the app. You can edit app details from here too.

To edit the details of an application


Click on the 'Edit' button
 at top right.

The application details edit screen will open. This screen is similar to the interface for adding a new application. See Add iOS Apps and Install them on Devices if you need help with this.



Remove Apps from the store

- Click 'Application Store' > 'iOS Store'
- Select the app(s) you want to remove and click 'Delete Application' above the table.
 - Note. If 'Remove from device when removed from app catalog' is enabled, then the app will also be removed from devices.



Click 'Confirm' in the confirmation dialog to remove the app(s)

9.2. Android Apps

- Click 'Application Store' > 'Android Store'.
- The store contains all Android apps that have been uploaded to Endpoint Manager. You can deploy selected apps to all managed devices or to specific devices.
- You can add new apps from the Google Play Store or upload your own custom enterprise apps. You can synchronize the app list with managed Android devices and edit existing app parameters.
- You can specify whether an app is a mandatory install or an optional install.

Ė	6	•	<\$		₽			೦
	nterprise Add Goo ication Applic		rm Devices Now A	Delete pplication	Export			7
	NAME	TYPE	APPLICATION	D	SUPPORTED DEVICES	LICENSE TYPE	MANDATORY	ADDED
	Dithers Office	Android Enterprise	cn.wps.moffice	_eng	Smartphone, Tablet	Enterprise	Yes	2018/07/20 03:18:08 PM
	Kanchi Sri Sankara Academy	Google Play Store	in.nirals.kssa		Smartphone, Tablet	Free	No	2018/07/20 03:12:27 PM
	Chennai Transit: Offline Metro, Rail, MTC, CMRL	Google Play Store	com.swash.trai	nsitworld.chenna	Smartphone, Tablet	Free	No	2018/07/20 03:11:41 PM
	Chennai Local Train Timetable	Google Play Store	com.miin.chen	naitraintimetable	Smartphone, Tablet	Free	No	2018/07/20 03:10:47 PM
	SHAREit - Transfer & Share	Google Play Store	com.lenovo.any	rshare.gps	Smartphone, Tablet	Free	No	2018/07/20 03:09:55 PM
	Skype - free IM & video calls	Google Play Store	com.skype.raid	er	Smartphone, Tablet	Free	No	2018/07/20 03:09:26 PM



	'Android Store' - Column Descriptions
Column Heading	Description
Name	Label of the application. Click the name to view details of the application. The screen also lets you edit app details. See Manage Android Apps for more details.
Туре	The source type of the app. Possible types are: Google Play Store Application Android Enterprise Application uploaded by the administrator
Application ID	The bundle identifier of the app.
Supported Devices	The types of devices with which the application is compatible.
License Type	Whether the app is a free, paid or enterprise version.
Mandatory	Whether the app has been marked to be installed compulsorily on the devices. See 'Add Android Apps and Install them on Devices' for more details
Added	The date and time at which the app was added to repository.
	Controls
Add Enterprise Application	Add custom applications to Endpoint Manager by uploading the .apk package files. See Add Android Apps and Install them on Devices for more details.
Add App Store Application	Add Android apps from the Play Store by entering the app name. See Add Android Apps and Install them on Devices for more details.
Inform Devices Now	Synchronize the app list with enrolled Android devices.
Delete Application	Remove an application from the Android app repository.
Export	Save the list of Android apps as a comma separated values (csv) file. See Export the List of Android Applications for more details.


Export the List of Android Applications

Export the list of Android applications to a .csv file as follows:

- Click 'Application Store' > 'Android Store'.
- Click the 'Export' button above the table then choose 'Export to CSV':

ITarian Endpoint Manager - Administrator Guide






- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Sort, Search and Filter Options

- Click a column header to sort items in alphabetical order of entries in the column.
- Click the funnel button T to open the filter options.





Click the following links for more help:

- Add Android Apps and Install them on Devices
- Manage Android Apps

9.2.1. Add Android Apps and Install them on Devices

- · You can add apps direct from the Google Play Store or by uploading custom apps
- Apps in the repository can be installed on all or specific managed Android devices.


See the following sections for more details:

- Add an Android App from Google Play Store
- Add a Custom/Enterprise Android App

Add an App from the Google Play Store



- Click 'Application Store' > 'Android Store'
- Click the 'Add Google Play Application' button
- Type the first few letters of the app in the 'Name' field on the form. Endpoint Manager will search for matching apps from the store.
- Select the correct app from the list of suggestions. Most of the form will then be auto-populated from the app details






Google Play Application - Table of Parameters			
Form Element	Туре	Description	
Name	Text Field	Enter the label of the application.	
		Type the first few letters of the app name	
		EM displays matching results	
		Choose the app you want to add from the suggestions	
		 Once you have chosen the app, most other form fields will be auto-populated. 	
Version	Text Field	The version number of the application.	
		This field will be auto-populated after choosing an app in the 'Name' field.	
		 Enter the version number manually if the version number wasn't automatically fetched. 	
Application ID	Text Field	The application ID (bundle identifier) of the app. Usually this is in the reverse DNS format, for example, 'com.comodo.mobile.comodoantitheft'. 'In the Google Play store, the identifier is located after the '=' in the URL. An example is shown below:	
		https://play.google.com/store/apps/details?id=com.comodo.mdm	
		 Click the help icon beside the field displays how to retrieve the application ID for the Play Store Apps. 	
		This field will be auto-populated on entering the correct app name in the 'Name' field.	
License Type	Radio	Whether the app is free or paid.	
	Button	This option will be pre-chosen depending on the app chosen in the 'Name' field.	
Category	Drop-down	The classification of the application.	
		The category will be auto-selected depending on the app chosen in the 'Name' field.	
		 Select the category from the drop-down if it is not auto- populated. 	
Supported devices	Drop-down	The category of devices on which the app can be run.	
		This device type will be auto-selected depending on the app chosen in the 'Name' field.	
		 Select the device type from the drop-down if it is not auto- populated. 	
Description	Text Field	The 'Description' filed will be auto-populated with the description of the selected app, from the Google Play Store page.	
		The text field also enables you to edit the description or enter your own description of the app.	
Mandatory app	Checkbox	Specify whether the app is a compulsorily install. If enabled, the app will be automatically pushed to all enrolled devices.	
Remove from device when removed from app catalog	Checkbox	The app will be uninstalled from devices if it is removed from the EM app store.	



	Google	Play Application - Table of Parameters
Application logo	Button	The application logo will be automatically fetched from the Google Play Store for the app chosen in the 'Name' field. If you want to change the logo, upload a new logo from the local computer by clicking 'Browse'.
Application screenshots	Button	The application screenshots will be automatically fetched from the Google Play Store for the app chosen in the 'Name' field. If you want to add new screenshots from the local computer, upload them by clicking 'Browse'.

- Click 'Save' after entering the details.
- The app will be added to the App repository and will listed in the 'Android Store'. It will be synced to the devices during the next cycle.
- · Click 'Inform Devices Now' if you want to push the app immediately.



Add a Custom/Enterprise Android App


- Custom apps can be added to the repository by uploading the app's .apk file.
- App details will be automatically fetched by parsing the file. You will need to manually enter details which could not be fetched from the .apk file.

Prerequisite: The .apk file of the app should have been saved in the computer or in the network storage accessible through the computer, from which the Endpoint Manager console is accessed.

Add Custom/Enterprise Android Apps

- Click 'Application Store' > 'Android Store'
- Click 'Add Enterprise Application' from the options at the top.





 Click 'Browse' under 'Source File', navigate to the location of the .apk file to be uploaded, select the file and click 'Open'


The file will be uploaded and form details auto-populated. See the previous section if you need advice on the fields in this form.

Click 'Save' after entering the details.

ITarian Endpoint Manager - Administrator Guide



- The app will be added to the repository and listed in the 'Android Store' interface. It will be synced to
 enrolled devices during the next update cycle.
- · Click 'Inform Devices Now' if you want to push the app out immediately.




9.2.2. Manage Android Apps

The 'Android Apps' interface lets you view and edit app details, and remove unwanted apps from the repository.

- · Click 'Application Store' > 'Android Store'
- Click the name of an app





The 'Application Details' page contains a description of the app and various other identifying information. You can also edit app details from here.

To edit the details of an application

Click on the 'Edit' button
 at the top right .




The application details edit screen will be displayed. This screen is similar to the interface for adding a new application. For more details on the parameters, see **Add Android Apps and Install them on Devices**.

Remove Apps from the Android App Catalog

- You can remove unwanted applications from the repository at any time.
- If you also select 'Remove from device when removed from app catalog', the app will also be deleted from devices.

To remove selected Apps

- Click 'Application Store' > 'Android Store'
- Select the app(s) you want to remove and click the 'Delete Application' button:




Click 'Confirm' to remove the app(s).

9.3. Windows Apps

The 'Windows Application Store' is a library of applications which can be deployed to Windows devices. Applications you can install include Adobe Acrobat, CCleaner, Firefox, Thunderbird and more. The list is continuously updated by ITarian.

Click 'Application Store' > 'Windows Application Store' to open the interface





	Windows Application Store - Column Descriptions	
Column Heading	Description	
Title	The name of the application. Click the name to view application details, including version number and any devices on which it is installed. See View Application Details.	
Application Category	The category under which the application is grouped.	
Vendor	The name of the organization / person that distributes the application	
Installed Devices	The number of devices on which the application is installed. Clicking the number will open the 'Device List' screen. See View Application-Installed Devices List .	
	Controls	
Install Selected Application(s)	Allows you to install selected application(s) on managed devices. See Install Windows Apps on Devices for more details.	

- Click any column header to sort items in ascending/descending order of entries in that column.
- Click the refresh icon on the top-right to update the table list
- Click the funnel icon application category.
 on the top-right to search for Windows applications by title, vendor and/or application category.
- To display all the items again, remove the search key from filter and click 'Apply'.
- EM returns 20 results per page when you perform a search. Click the arrow next to 'Results per page' to change the number of results shown.

From the interface you can:

- View Application Details
- View Application-Installed Devices List




Install Applications on Devices

View Application Details

Click an application's name in the list

A new screen with 'Application Info' and 'Device List' tabs will open.




By default, the 'Application Info' tab will be displayed. The details of the application such as name, description, vendor, category including version number(s) will be available.

The 'Device List' tab displays the device details on which the application is installed. This screen is same
that is shown when the number in the 'Installed Devices' column is clicked. See View Application-Installed
Devices List for details.

View Application-Installed Devices List

• Click the number on the far right beside an application's name ('Installed Devices' column)

A new screen with 'Application Info' and 'Device List' tabs will open.



By default, the 'Device List' tab will be displayed. The details of the device such as name, application version, installation path and name of the device owner will be available.




• Click the name of a device to view its **summary** information. See 'Manage Windows Devices' for more information about how to manage devices.

9.3.1. Install Windows Apps on Devices


The 'Windows Application Store' lets you install apps on managed Windows devices.

- Click 'Application Store' > 'Windows Application Store'
- Select the applications you want and click 'Install Selected Application(s)':



- All Devices Install the latest version of the apps on every managed Windows device.
- Selected Devices Install the apps on specific devices:
 - Choose 'Selected device(s)'






- Enter first few letters of the device name and select from the suggestions.
- · Repeat to add multiple devices.

Note - The version number drop-down is not available if you select 'All devices', multiple devices, or multiple apps.

• Select the application version (available for single application/ single device installs only)



Click 'Install'

The install command is sent immediately. The 'Software Inventory' screen shows all apps installed on a particular device. See 'View Applications Installed on a Device' for more information.



10. Security Sub Systems

The 'Security Sub systems' menu lets you:

- View the infection status of managed devices.
- Run antivirus and file-rating scan on devices.
- Update the virus database on devices.
- View and manage quarantined files.
- View and modify the trust rating of files discovered on devices
- · View unknown files currently running in the container on an endpoint.
- View unknown files which were automatically submitted to Valkyrie for analysis
- View a consolidated list of all security events on all managed Windows endpoints.
- View a list of external connection attempts from devices.
- Run data loss prevention (DLP) scans on devices
- View the files containing sensitive information detected by DLP scans

The following sections contain more details on each area:

- Security Dashboards
 - View Security Events by Time
 - View Security Events by File
 - View Security Events by Device
- View Contained Applications
- Manage File Trust Ratings on Windows Devices
- View Valkyrie Analyzed Files
- Antivirus and File Rating scans
 - Run Antivirus and/or File Rating Scans on Devices
 - Handle Malware on Scanned Devices
 - Update Virus Signature Database on Windows, Mac OS and Linux Devices
- View and Manage Identified Malware
- View and Manage Quarantined Items
- View Android Threat History
- View and Manage Autoruns Items
- View History of External Device Connection Attempts
- Data Loss Prevention Scans
 - Run DLP Scans
 - View DLP Scan Results



10.1. Security Dashboards

Click 'Security Sub-Systems' > 'Security Dashboards'

The security dashboard is a list of all security events on managed endpoints. This includes events from the antivirus, containment, application-control, autorun control, and virtual desktop components.

To view threats recorded on Android devices, go to 'Security Sub-Systems' > 'Antivirus' > 'Android Threat History'

Endpoint Manager retains security event logs for 12 months for PCI-DSS compliance.

Events that are captured include:

Antivirus - Windows, Mac OS, and Linux devices

- File blocked, moved to quarantine, or ignored
- File restored/removed from quarantine
- File skipped by a virus scan
- · File rated as trusted, or submitted as a false positive, at the scan results screen
- File added to the exclusions list

Containment - Windows devices

- File blocked, ignored, or run in the container by:
 - · Auto-containment rules in the profile on the device
 - A local user running the file in the container on a one-off basis

Application Control - Windows devices

- Unrecognized or malicious file added to, or removed from, the CCS 'File list'.
- Changes to the trust rating of a file
- See Manage File Trust Ratings on Windows Devices for more details.

Autorun Control - Windows devices

 Records the action taken by CCS on apps that try to modify Windows services, startup entries, and scheduled tasks.

Recorded actions include:

- Ignore
- Terminate
- · Terminated and disabled
- · Quarantined and disabled
- Restored
- Deleted

Virtual Desktop - Windows devices

- Virtual desktop activity on endpoints. Recorded actions include:
 - Launched
 - Terminated
 - Session started
 - Session paused
 - Session continued




- Session terminated
- · Switched to host
- Switched to virtual desktop

The interface also lets you rate files, view file details, and move files in or out of quarantine.

Open the dashboard:

- Click 'Security Sub-Systems' > 'Security Dashboards'
 - Select a company or group to view devices in that group Or
 - · Select 'Show all' to view every device enrolled to Endpoint Manager



The dashboard has three tabs:

- Event View Shows events in chronological order. See View Security Events by Time for more details.
- File View All events concerning a particular file are grouped together. See View Security Events by File
 for more details.
- Device View Shows all events that occurred on a specific device. See View Security Events by Device
 for more information.


10.1.1. View Security Events by Time

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
 - Select a company or group to view events in that group

 Or
 - Select 'Show all' to view all events



Event view shows security events from all managed endpoints in chronological order:



	Security Dashboards - Event View - Column Descriptions			
Column Header	Description			
Date/Time	The time at which the event occurred.			
Components	The CCS module that reported the event. This can be 'Antivirus', 'Containment', 'Application Control', 'Autorun Control' or 'Virtual Desktop'.			
Action	The response to the event. This shows how the file was handled by the component mentioned above.			
	Here are the possible actions per module:			
	Antivirus - Windows, Mac OS, and Linux devices			
	Malware detected			
	Malware quarantined			
	Malware removed from quarantine			
	Malware restored from quarantine			
	Malware removed from infected file			
	The file was skipped by the scan			
	Detected malware ignored			
	Detected malware blocked			
	File added to exclusions			
	File added to trusted files list			
	File reported as a false positive from the results screen			
	Containment - Windows devices			
	File run inside container with different restriction levels:			
	Restricted			
	Virtually			



	Security Dashboards - Event View - Column Descriptions			
Column Header	Description			
	File blocked			
	File ignored			
	Application Control - Windows devices			
	File added to the file list			
	File removed from the endpoint			
	Trust rating updated for a file			
	Autorun Control - Windows devices			
	Detected item ignored			
	Process / service stopped			
	 Auto-run process stopped. Corresponding auto-run entry removed. In the case of a service, CCS disables the service. 			
	 Auto-start process quarantined. Corresponding auto-start entry removed. In the case of a service, CCS disables the service. 			
	Processes restored from quarantine			
	File deleted from the endpoint			
	Virtual Desktop - Windows devices			
	Launched			
	Terminated			
	Session started			
	Session paused			
	Session continued			
	Session terminated			
	Switched to host			
	Switched to virtual desktop			
Device Name	The label of the endpoint on which the event occurred.			
	 Click the name of a device to open its 'Device Details' interface. 			
	See Manage Devices for more details on the interface.			
File Name	The label of the executable file affected by the action			
	Click the name of a file to open its 'File Details' interface.			
	See View the details of a file for more details.			
File Path	The installation location of the executable file on the endpoint			
	Click the icon to copy the path to the clipboard.			
File Hash	The SHA 1 hash value of the executable file			
	 Click the i icon to copy the hash value to the clipboard. 			
Initial Comodo Rating	The trust rating awarded by Comodo File Look-up Service (FLS) to the file before the event.			



	Security Dashboards - Event View - Column Descriptions
Column Header	Description
Current Comodo Rating	The present trust rating of the file as per the Comodo FLS.
Initial Admin Rating	The trust rating of the file as manually set by the admin before the event, if any.
	See Rate Files as Trusted, Malicious or Unrecognized for more details.
Current Admin Rating	The most recent trust rating of the file as manually set by the admin after the event, if any.
	See Rate Files as Trusted, Malicious or Unrecognized for more details.
Additional Info	Provides the current status of the event or the action taken on the affected file.
	Controls
Action on Endpoints	Delete or restore a file from quarantine on the endpoint. Applies to events where malware or autorun items were quarantined.
	See Handle Quarantined Items for more details
Change rating	Assign a new admin rating to a file (trusted, malicious or unrecognized).
	See Rate Files as Trusted, Malicious or Unrecognized for more details.
File Details	View complete information about the file that caused the event. You can also view a history of actions taken by the file.
	See View the details of a file for more details.
Download Valkyrie Report	Get a detailed Valkyrie analysis report for the file as a PDF.
	See Get Valkyrie Report of a file for more details
Check Valkyrie Details	View the Valkyrie analysis on a file.
	See View Valkyrie analysis details of file for more details
Export	Save the list of events as a comma separated values (csv) file.
	See Export the List of Events for more details.


The 'Event View' interface lets you to:

- Handle Quarantined Items
- Rate Files as Trusted, Malicious or Unrecognized
- View the details of a file
- Get Valkyrie Report of a file
- · View Valkyrie analysis details of a file
- Export the List of Events

Sorting, Search and Filter Options

- Click the 'Date/Time', 'File Name', 'File Path' or 'File Path' column header to sort events in ascending or descending order
- Enter the SHA 1 hash value of a file in the search box to filter the events involving the file.
- Click the funnel icon on the top right to open more filter options:





- Use the search fields to filter events by OS, date/time, file rating and other criteria.
- By default, 'Security Dashboards' > 'Event View' does not show the files that are ignored by autocontainment rules.
 - Select 'Show containment ignored events' to include the files ignored by auto-containment rules in the events list
- To display all items again, clear any search filters then click 'OK'.


You can use any combination of filters simultaneously to search for specific apps.



Handle Quarantined Items

You can delete or restore quarantined items from the 'Event View' tab of the security dashboard.

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
 - Select a company or group to view events in that group
 - Or
 - Select 'Show all' to view all events
- Select the events where the files of interest were moved to guarantine.
- Click 'Action on Endpoint' button:



- · Select 'Delete File / Delete Autorun from device' to remove the file from the device
- Select 'Restore from Quarantine' / 'Restore Autorun' to move the file(s) from quarantine to their original location on the device.

Rate Files as Trusted, Malicious or Unrecognized


If required, you can manually rate files as unrecognized, trusted or malicious. The new rating will be sent to endpoints during the next sync.

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
 - Select a company or group to view events in that group

 Or
 - · Select 'Show all' to view all events
- Select the events involving the files of interest.



- Click the 'Change Rating' button
- Set your preferred rating from the options:



The new rating will be propagated to all endpoints during the next synchronization.


View the details of a file

- You can view the complete details of the executable file that effected a security event on a managed endpoint from the 'Events View' interface.
- You can also view the history of actions taken on the file on all endpoints on which it was discovered.

View the details of a file that induced a security event

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
 - Select a company or group to view events in that group Or
 - · Select 'Show all' to view all events
- Select the event involving the file of interest.
- Click the 'File Details' button:
- Alternatively, click the label of the file in the 'File Name' column






The information on the file are shown under two tabs:

- File Details
- File History

File Details

- The 'File Details' tab shows the particulars of the file.
- The interface also allows you to:
 - Change the admin trust rating of the file
 - Delete the file from the endpoints or restore the file from quarantine, if the file has been moved to quarantine by antivirus on the endpoints.
 - Get a Valkyrie analysis report of the file as a PDF
 - · View Valkyrie analysis details of the file






The 'File Summary' pane shows the following details:

- Last detected file name Label of the file when it was most recently scanned
- SHA1 SHA1 hash value of the file
- First Seen by Comodo Date and time at which the file was first reported to Comodo threat labs
- First Seen on my Network Date and time at which the file was first detected on one of your devices
- Number of endpoints The count of Windows devices on which the file was found
 - · Click 'Calculate' to update the number of devices on which the file is currently found
- Comodo Rating The trust verdict on the file from Comodo threat labs
- Last Update of Comodo Rating Date and time at which the Comodo rating last changed
- Admin Rating The trust rating most recently assigned to the file by an administrator, if any.
- Version The version number of the executable file

Handle a quarantined file

Click 'Action on Endpoint' on the top






- Select 'Delete File' to remove the file the device, on which the selected event occurred.
- Select 'Restore from Quarantine' to move the file from quarantine to their original location on the device.

Assign or change the admin rating of the file

- Click 'Change Rating' on the top
- Set your preferred rating from the options:



The new rating will be propagated to all endpoints during the next synchronization.

Download Valkyrie report of a file

- Click the 'Download Valkyrie Report' button
- See Get Valkyrie Report of a file for more details on the report

View the Valkyrie analysis results of the file


- Click the 'Check Valkyrie Details' button
- See View Valkyrie analysis details of file for more details on the results

File History

- This tab shows a timeline of events caused by the file. You can see the devices on which the file was found, the security module which detected the activity, and the action that was taken on the file
- The interface also allows you to:



- Change the admin trust rating of the file
- Delete the file from the endpoints or restore the file from quarantine, if the file has been moved to quarantine by antivirus on the endpoints.



Sec	urity Dashboards - Event View - File History - Column Descriptions		
Column Header	Description		
Date/Time	The time at which the event occurred.		
Components	The module that reported the event. This can be 'Antivirus', 'Containment', 'Application Control' or 'Autorun Control'.		
Action	The nature of the event showing the how the file was handled by the CCS component. The possible actions are:		
	Antivirus:		
	Detection of malware		
	Malware quarantined		
	Malware removed from quarantine		
	Malware restored from quarantine		
	Malware removed from infected file		
	Detected item ignored		
	Detected file blocked		
	File added to exclusions		
	File added to trusted files list		
	File reported as false positive from the results screen		
	Containment		
	File run inside container with different restriction levels:		




Security Dashboards - Event View - File History - Column Descriptions	
Column Header	Description
	 Restricted Virtually File blocked File ignored Application Control: File added to the file list File removed from the file endpoint Trust rating updated for a file Autorun Control: Detected item ignored Process / service stopped Auto-run process stopped. Corresponding auto-run entry removed. In the case of a service, CCS disables the service. Auto-start process quarantined. Corresponding auto-start entry removed. In the case of a service, CCS disables the service. Processes restored from quarantine File deleted from the endpoint
Device Name	The label of the Windows endpoint on which the event occurred. Click the name of a device to open its 'Device Details' interface. See Manage Windows Devices for more details on the interface.
Additional Info	Provides the current status of the event or the action taken on the affected file.
Controls	
Action on Endpoints	Allows you to delete a file or restore a file from quarantine on the endpoint. Applicable only for events involving 'Malware quarantined' action.
Change rating	Allows you to change the rating of the affected file to trusted, malicious or unrecognized.

Handle a quarantined file

Click 'Action on Endpoint' on the top






- Select 'Delete File' to remove the file the device, on which the selected event occurred.
- Select 'Restore from Quarantine' to move the file from quarantine to their original location on the device.

Assign or change the admin rating of the file

- Click 'Change Rating' on the top
- Set your preferred rating from the options:



The new rating will be propagated to all endpoints during the next synchronization.

Get the Valkyrie Report on a file

Background:

- Valkyrie is a cloud-based file analysis service that tests unknown files with a range of static and behavioral checks. The service helps Comodo establish whether an unknown file is malicious or safe
- You can configure Comodo Client Security on endpoints to automatically upload unknown files to Valkyrie
- You can schedule the upload of unknown files in the 'Valkyrie' section of a Windows profile. See Valkyrie Settings if you need help with this.


ITarian Endpoint Manager - Administrator Guide



Download a Valkyrie report

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
 - Select a company or group to view events in that group Or
 - · Select 'Show all' to view all events
- · Select the event involving the file of interest
- Click the 'Download Valkyrie Report' button






- The PDF opens in a new browser tab.
- The report contains granular details of various tests on the file



View Valkyrie analysis on a file

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
- Select the event involving the file of interest.
- Click the 'Check Valkyrie Details' button



- The Valkyrie 'file verdict' page opens in a new tab.
- The page contains the results of various tests, and a trust verdict from each test.




For more details on Valkyrie tests, see http://help.comodo.com/topic-397-1-773-9563-Introduction-to-Comodo-Valkyrie.html.

Export the List of Events

You can save the list of events as a comma separated values (CSV) file for future analysis.

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'Event View'
- · Apply any filters that you require.
- Click 'Export' > 'Export to CSV'



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.


10.1.2. View Security Events by File

Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'


'File view' groups together all events that involve a particular file.

- A file can generate events in different security modules, on multiple devices, at different times.
- All these events are grouped together and shown as a single row:





- You can expand the row to view individual events:
- Click '+' at the left of the row to view all events related to the file:





	Security Dashboards - File View - Column Descriptions
Column Header	Description
Date/Time	The time at which the event occurred.
Components	The security module that reported the event. This can be 'Antivirus', 'Containment', 'Application Control' or 'Autorun Control'.
Action	The response to the event. This shows how the file was handled by the CCS component mentioned above.
	List of possible actions:
	Antivirus:
	Detection of malware
	Malware quarantined
	Malware removed from quarantine
	Malware restored from quarantine
	The file was skipped by a virus scan
	Malware removed from infected file
	Detected item ignored
	Detected file blocked
	File added to exclusions
	File added to trusted files list
	File reported as false positive from the results screen
	Containment:
	File run inside container with different restriction levels:
	Restricted
	Virtually
	File blocked
	File ignored
	Application Control:
	File added - An unrecognized or malicious file was added to the 'File List' in CCS on the endpoint.
	 File deleted - A file was removed from the 'File List' in CCS on the endpoint. This is because it rating was changed to 'Trusted', or because the file was deleted from the endpoint.
	File updated - A file's rating changed in the 'File List' in CCS on the endpoint. The rating may have changed from 'Unrecognized' to 'Malicious', or vice-versa.
	Autorun Control:
	Detected item ignored
	Process / service stopped
	Auto-run process stopped. Corresponding auto-run entry removed. In the case of a service, CCS disables the service.
	Auto-start process quarantined. Corresponding auto-start entry removed. In the



	case of a service, CCS disables the service. • Processes restored from quarantine
	File deleted from the endpoint
Number of devices	On how many devices the event was detected
File Name	The label of the executable file affected by the action
	Click the name of a file to open its 'File Details' interface.
	See View the details of a file for more details.
File Path	The installation location of the executable file on the endpoint
	Click the icon to copy the path to the clipboard.
File Hash	The SHA 1 hash value of the executable file
	Click the i icon to copy the hash value to the clipboard.
Current Comodo Rating	The present trust rating of the file as per the Comodo File Look-up Service (FLS).
Current Admin Rating	The most recent trust rating of the file as manually set by the admin, if any.
	See Rate Files as Trusted, Malicious or Unrecognized for more details.
	Controls
Action on Endpoints	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events.
Action on Endpoints	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware
Action on Endpoints Change rating	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events.
	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details
	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized).
Change rating	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a
Change rating File Details Download Valkyrie	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a history of actions taken by the file.
Change rating File Details	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a history of actions taken by the file. • See View the details of a file for more details.
Change rating File Details Download Valkyrie	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a history of actions taken by the file. • See View the details of a file for more details. Get a detailed Valkyrie analysis report for a file as a PDF.
Change rating File Details Download Valkyrie Report	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a history of actions taken by the file. • See View the details of a file for more details. Get a detailed Valkyrie analysis report for a file as a PDF. • See Get Valkyrie Report of a file for more details
Change rating File Details Download Valkyrie Report	Delete or restore a file from quarantine on the endpoint. Applies only to 'Malware quarantined' events. • See Handle Quarantined Items for more details Assign a new admin rating to a file (trusted, malicious or unrecognized). • See Rate Files as Trusted, Malicious or Unrecognized for more details. View complete information about the file that caused the event. You can also view a history of actions taken by the file. • See View the details of a file for more details. Get a detailed Valkyrie analysis report for a file as a PDF. • See Get Valkyrie Report of a file for more details View the Valkyrie analysis on a file.

- Use the search fields to filter events by component, date, file name, and other criteria.
- Click the funnel icon at top-right to view more filter options:

The file view interface lets you:

- Handle Quarantined Items
- Rate Files as Trusted, Malicious or Unrecognized
- View the details of a file
- Get Valkyrie Report of a file




- View Valkyrie analysis details of file
- Export the List of Files

Handle Quarantined Items

- You can delete or restore quarantined items from the 'Security Dashboards' interface.
- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
 - Select a company or group to view events in that group

Or

- Select 'Show all' to view all events
- Select the event(s) in which the file(s) of interest are moved to guarantine.
- Click 'Action on Endpoint' on top



- Select 'Delete File' / 'Delete Autorun from device' to remove the file from the respective devices
- Select 'Restore from Quarantine' / 'Restore Autorun' to move the files back to their original location.

Rate Files as Trusted, Malicious or Unrecognized


If required, you can rate the files affected by the events as unrecognized, trusted or malicious. Please make sure before marking a file as trusted. Any new file ratings will be sent to endpoints during the next sync.

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
 - Select a company or group to view events in that group

Or

- Select 'Show all' to view all events
- Select the event(s) involving the file(s) of interest.
- Click the 'Change Rating' button
- Set your preferred rating from the options:





The new rating will be propagated to all endpoints during the next synchronization.

View the details of a file

- You can view the complete details of the executable file that effected security events on managed endpoints from the 'File View' interface.
- You can also view the history of actions taken on the file on all endpoints on which it was discovered.


View details about the file that caused an event

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
 - Select a company or group to view events in that group

Or

- Select 'Show all' to view all events
- Select the event involving the file of interest.
- Click the 'File Details' button:
- Alternatively, click the label of the file in the 'File Name' column






File information is shown in two tabs:

- File Details
- File History



File Details

- The 'File Details' tab shows the particulars of the file.
- The interface also allows you to:
 - Change the admin trust rating of the file
 - Delete the file from the endpoints or restore the file from quarantine, if the file has been moved to quarantine by antivirus on the endpoints.
 - Get a Valkyrie analysis report of the file as a PDF
 - · View Valkyrie analysis details of the file



The 'File Summary' pane shows the following details:


- Last detected file name Label of the file when it was most recently scanned
- SHA1 SHA1 hash value of the file
- First Seen by Comodo Date and time at which the file was first reported to Comodo threat labs
- First Seen on my Network Date and time at which the file was first detected on one of your devices
- Number of endpoints The count of Windows devices on which the file was found
 - Click 'Calculate' to update the number of devices on which the file is currently found
- Comodo Rating The trust verdict on the file from Comodo threat labs



- Last Update of Comodo Rating Date and time at which the Comodo rating last changed
- Admin Rating The trust rating most recently assigned to the file by an administrator, if any.
- Version The version number of the executable file

To handle a quarantined file


Click 'Action on Endpoint' on the top



- Select 'Delete File' to remove the file the device, on which the selected events occurred.
- Select 'Restore from Quarantine' to move the file from quarantine to their original location on the device.

To assign or change the admin rating of the file

- Click 'Change Rating' on the top
- Set your preferred rating from the options:



The new rating will be propagated to all endpoints during the next synchronization.

To download Valkyrie report of a file

- Click the 'Download Valkyrie Report' button
- See Get Valkyrie Report of a file for more details on the report

To view the Valkyrie analysis results of the file


Click the 'Check Valkyrie Details' button



See View Valkyrie analysis details of file for more details on the results

File History

- The 'File History' tab shows the timeline of events induced by the file and actions taken on it at all devices in which it was found.
- The interface also allows you to:
 - · Change the admin trust rating of the file
 - Delete the file from the endpoints or restore the file from quarantine, if the file has been moved to quarantine by antivirus on the endpoints.



Sec	Security Dashboards - Event View - File History - Column Descriptions	
Column Header	Description	
Date/Time	The time at which the event occurred.	
Components	Whether the 'Antivirus', 'Containment' or 'Application Control' that reported the event.	
Action	The nature of the event showing the how the file was handled by the CCS component. The possible actions are:	
	Antivirus:	
	Detection of malware	
	Malware quarantined	
	Malware removed from quarantine	
	Malware restored from quarantine	
	Malware removed from infected file	
	Detected item ignored	
	Detected file blocked	
	File added to exclusions	




Security Dashboards - Event View - File History - Column Descriptions	
Column Header	Description
	File added to trusted files list
	File reported as false positive from the results screen
	Containment
	File run inside container with different restriction levels:
	Restricted
	Virtually
	File blocked
	File ignored
	Application Control:
	 File added - An unrecognized or malicious file was added to the 'File List' in CCS on the endpoint.
	 File deleted - A file was removed from the 'File List' in CCS on the endpoint. This is because it rating was changed to 'Trusted', or because the file was deleted from the endpoint.
	 File updated - A file's rating changed in the 'File List' in CCS on the endpoint. The rating may have changed from 'Unrecognized' to 'Malicious', or vice-versa.
	Autorun Control:
	Detected item ignored
	Process / service stopped
	 Auto-run process stopped. Corresponding auto-run entry removed. In the case of a service, CCS disables the service.
	 Auto-start process quarantined. Corresponding auto-start entry removed. In the case of a service, CCS disables the service.
	Processes restored from quarantine
	File deleted from the endpoint



Security Dashboards - Event View - File History - Column Descriptions	
Column Header	Description
Device Name	The label of the Windows endpoint on which the event occurred. Click the name of a device to open its 'Device Details' interface. See Manage Windows Devices for more details on the interface.
Additional Info	Provides the current status of the event or the action taken on the affected file.
Controls	
Action on Endpoints	Allows you to delete a file or restore a file from quarantine on the endpoint. Applicable only for events involving 'Malware quarantined' action.
Change rating	Allows you to change the rating of the affected file to trusted, malicious or unrecognized.

Handle a quarantined file

Click 'Action on Endpoint' on the top




- Select 'Delete File' to remove the file the device, on which the selected event occurred.
- Select 'Restore from Quarantine' to move the file from quarantine to their original location on the device.

Assign or change the admin rating of the file

- Click 'Change Rating' on the top
- Set your preferred rating from the options:





The new rating will be propagated to all endpoints during the next synchronization.

Get the Valkyrie Report on a file

Background:

- Valkyrie is a cloud-based file analysis service that tests unknown files with a range of static and behavioral checks. The service helps Comodo establish whether an unknown file is malicious or safe
- You can configure Comodo Client Security on endpoints to automatically upload unknown files to Valkyrie
- You can schedule the upload of unknown files in the 'Valkyrie' section of a Windows profile. See Valkyrie
 Settings if you need help with this.


Download the Valkyrie report on a file


- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
 - Select a company or group to view events in that group

Or

- Select 'Show all' to view all events
- Select the event involving the file of interest.
- Click the 'Download Valkyrie' button







- The PDF opens in a new browser tab.
- The report contains granular details of various tests on the file


View Valkyrie analysis of a file

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
 - Select a company or group to view events in that group



Or

- · Select 'Show all' to view all events
- Select the event involving the file of interest.
- Click the 'Check Valkyrie Details' button



- The Valkyrie 'file verdict' page opens in a new tab.
- The page contains the results of various tests, and a trust verdict from each test.




For more details on Valkyrie tests, see http://help.comodo.com/topic-397-1-773-9563-Introduction-to-Comodo-Valkyrie.html.

Export the List of Files

You can save the list of events as a comma separated values (CSV) file for future analysis.

- Click 'Security Sub-Systems' > 'Security Dashboards' > 'File View'
- Apply any filters that you require.
- Click 'Export' > 'Export to CSV'



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.


10.1.3. View Security Events by Device

Click 'Security Sub-Systems' > 'Security Dashboards' > 'Device View'

Device view shows all events that occurred on a particular device.

 Multiple security modules can create events on a device at different times. All these events are grouped together and shown as a single row:





Click '+' to view all events on the device



Security Dashboards - Device View - Column Descriptions	
Column Header	Description
Date/Time	The time at which the event occurred.
OS	The operating system of the device.
Device Name	The device label. Click a link to view its device details.
Components	The security module that reported the event. This can be 'Antivirus', 'Containment', 'Application Control' or 'Autorun Control'.
Action	The response to the event. This shows how the file was handled by the CCS component mentioned above.
	List of possible actions:
	Antivirus - Windows, Mac OS, and Linux devices
	Detection of malware
	Malware quarantined
	Malware removed from quarantine
	Malware restored from quarantine
	File was skipped by a virus scan
	Malware removed from infected file




	Detected item ignored
	Detected item ignored Detected file blocked.
	Detected file blocked
	File added to exclusions
	File added to trusted files list
	File reported as false positive from the results screen
	Containment - Windows devices
	File run inside container with different restriction levels:
	Restricted
	 Virtually
	File blocked
	File ignored
	Application Control - Windows devices
	File added to the file list
	File removed from the file endpoint
	Trust rating updated for a file
	Autorun Control - Windows devices
	Detected item ignored
	Process / service stopped
	 Auto-run process stopped. Corresponding auto-run entry removed. In the case of a service, CCS disables the service.
	 Auto-start process quarantined. Corresponding auto-start entry removed. In the case of a service, CCS disables the service.
	Processes restored from quarantine
	File deleted from the endpoint
Last Action	Indicates what was done last on the device related to a security component, for example, file added, file deleted and so on. See above row for list of actions.
Number of Files	Shows how many file events were logged for the device. Click the number to view a list of the events.
Additional Info	Provides the current status of the event or the action taken on the affected file.
	Controls
Device Details	View general information about the device.
	Select a device and click 'Device Details' above.
	 You will be taken to the 'Device List' screen of the device showing information such as device summary, operating system summary and so on.
	See 'View Summary Information' for more details.

Sort, Search and Filter Options

- Click the 'Date/Time' column header to sort events in ascending or descending order
- Enter the device name in the search box to filter events involving the device



Click the funnel icon at top-right to view more filters:



- Use the search fields to filter events by device, date/time, action and other criteria.
- By default, 'Security Dashboards' > 'Device View' does not show files which are ignored by autocontainment rules.
 - Select 'Show containment ignored events' to include these files.
- To display all items again, clear any search filters and click 'OK'.

You can use any combination of filters simultaneously to search for specific devices.

10.2. View Contained Applications

Click 'Security Sub-Systems' > 'Containment'

- The container is a secure environment in which files with an 'unknown' trust rating are run. 'Unknown' files have not yet been classified as either 'safe' or 'malware'.
- Contained applications are not permitted to modify files, user data or other processes on the host machine.
- You can also submit unknown applications to Valkyrie, Comodo's file analysis system. Valkyrie will test the
 file and attempt to classify it as 'safe' or 'malware'.

An application could be run inside the container because:

It was auto-contained by rules in the EM configuration profile applied to the endpoint. See 'Containment Settings' in Create Windows Profiles for more details about containment rules in a profile.




- It was auto-contained by local Comodo Client Security rules on the endpoint
- The endpoint user ran the program inside the container on a 'one-off' basis. This can be helpful to test the behavior of new executables that have they downloaded.

You can view all programs that ran inside the container from the 'Containment' interface. Admins can also view the activity of processes started by contained applications. Admins have the option to rate a contained file as trusted or malicious.

Open the containment list interface:

- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained programs in that group
 Or
 - Select 'Show all' to view all contained programs



Containment - Column Descriptions	
Column Heading	Description
File Name	The executable that was run in the container. Click the name of the file to view its details. See View details of a contained application for more details.
File Path	The location of the contained file on the local endpoint. • Click the iii icon to copy the path to the clipboard.
File Hash	SHA1 hash value of the file. • Click the iii icon to copy the hash value to the clipboard.
Number of Devices	 The quantity of endpoints on which the item was identified. Click the number to view a list of endpoints on which the item was found. This also allows you to view the activities of processes started by the item. For more details, see Device List Screen below.
Contained By	The reason the file was contained.
Parent Process Name	The program or service that launched the contained application.

ITarian Endpoint Manager - Administrator Guide



Action	The permission level at which the file was executed in the container, or the action that was taken upon it. The possible values are:
	 Restricted - The file was run inside the container but had limited access to the operating system resources.
	 Virtually - The file was completely isolated from the operating system and files on the computer.
	Blocked - The file was not allowed to run at all.
	 Ignored - The file was allowed to run outside the container without any restrictions.
	Unknown - The containment status was not determined.
Status	The execution state of the file inside the container. The possible values are:
	Running
	Complete
	Failed
Comodo Rating	The present trust rating of the file as per the Comodo File Look-up Service (FLS).
Admin Rating	The trust rating of the file as set by the administrator. Files can be rated as trusted, malicious or unrecognized.
Date and Time	Date and time the file ran in the contained environment.
	Controls
File Details	View full information of the contained file including the devices on which it was contained and its activity.
Change Rating	You can change the rating of the contained file as trusted, malicious or unrecognized.
Hide file(s)	Conceal contained file record(s) from the list.
Unhide file(s)	Reveal concealed file record(s).
Export	Export the list of contained files to a .csv file.
	The exported file can be viewed in 'Dashboard' > 'Reports'.
Download Valkyrie report	Valkyrie is Comodo's advanced file analysis and verdicting system. Each report contains an in-depth breakdown on the activity an unknown file, along with an overall verdict on its trustworthiness.
Check Valkyrie details	View Valkyrie file analysis of the contained file at https://valkyrie.comodo.com.

- Click any column header to sort items in ascending/descending order of entries in that column.
- Click the funnel icon on the right to search for contained applications by name, file path, SHA1 file hash, admin rating, action, status and/or execution date.
- To display all the items again, remove / deselect the search key from filter and click 'Apply'.
- EM returns 20 results per page when you perform a search. To increase the number of results displayed per page up to 200, click the arrow next to 'Results per page' drop-down and choose the number.

Manage Contained Items



The 'Containment' interface allows you to:

- View details of a contained application
- Rate the files
- Hide file(s)
- Restore hidden file(s)
- Export file records as CSV file
- Download Valkyrie report
- View Valkyrie fie analysis report online

View details of a contained application

- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained programs in that group Or
 - · Select 'Show all' to view all contained programs
- Click on a specific file-name in the list OR select a file and click file details
- This will open the file details interface which shows:
 - File Info General information such as file-name, path, age, hash and file-size.
 - Device List Shows endpoints upon which the file was found. This tab also tells you the device owner
 and lists any activities by the file.

Device List Screen

- Click 'Security Sub-Systems' > 'Containment'
- Click on a specific file name in the list OR select a file and click file details
- · Click the 'Device List' tab

The 'Device List' shows endpoints on which the file was discovered and its activities. Admins can view processes executed by the file with details on data handled by each process.



Rate files as trusted / malicious

If required, admins can rate contained files as unrecognized, trusted or malicious. Please make sure before marking a file as trusted. Any new file ratings will be sent to endpoints during the next sync.


- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained files in that group

Or

- Select 'Show all' to view all contained files
- Select the file(s) whose rating you wish to change
- Click the 'Change Rating' button



Set your preferred rating from the options:



The new rating will be propagated to all endpoints during the next synchronization.

Export file records as a CSV file

- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained files in that group
 Or
 - · Select 'Show all' to view all contained files
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button and choose 'Export to CSV':



The report is generated in .csv file format.

Report has been created. Please, check «<u>Reports</u>» in dashboard

You can access the report in the 'Dashboard' > 'Reports' interface. See **Reports** if you need more help with this interface.


Hide File(s)

You can hide records of contained apps from the list. For example, you can hide unimportant hash records.



Hide contained file record(s)


- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained files in that group
 Or
 - · Select 'Show all' to view all contained files
- Select the files that you want to hide and click 'Hide file(s)'



To view the hidden files again, you have to unhide them.


Restore Hidden File(s)

- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained files in that group
 Or
 - Select 'Show all' to view all contained files
- Click the funnel icon on the right, select 'Show hidden files' and click 'Apply'



- The hidden files are shown with dark gray background stripe.
- Select the hidden files from the list and click 'Unhide file(s)'





A confirmation message is displayed. The files are re-added to the list.

Valkyrie Reports


Files running in the container are analyzed and rated by Comodo's behavior analysis system, Valkyrie. Valkyrie tests unknown files with a range of static and dynamic behavioral checks to identify whether they are malicious or safe.

You can view the file rating in the 'Application Control' interface also. You can download a Valkyrie report or view it online at https://valkyrie.comodo.com/


Download Valkyrie report

- Click 'Security Sub-Systems' > 'Containment'
 - Select a company or group to view contained files in that group
 Or
 - · Select 'Show all' to view all contained files
- Select any file
- Click 'Download Valkyrie report':





This will open the Valkyrie report on the contained file in PDF format:




You can also download and view the report at https://valkyrie.comodo.com/ after signing into your Valkyrie account.


View Valkyrie fie analysis report online

Select the file from the list and click 'Check Valkyrie Details' at the top.





You will be taken to the report summary page of the selected file at https://valkyrie.comodo.com/.



- View a more detailed version of the Valkyrie analysis by logging in at https://valkyrie.comodo.com/. You can use your ITarian username and password to login.
- See https://help.comodo.com/topic-397-1-773-9563-Introduction-to-Comodo-Valkyrie.html for help to use the Valkyrie online portal.

10.3. Manage File Trust Ratings on Windows Devices

- Click 'Security Sub-Systems' > 'Application Control' to open the 'Application Control' interface.
- Comodo Client Security (CCS) monitors all file activity on Windows devices. Every new executable is scanned against the Comodo white and blacklists then awarded a rating of 'Unrecognized', 'Trusted' or 'Malicious'.
- Files that have a rating of 'Unrecognized' or 'Malicious' are reported to the 'Application Control' interface. Admins can change the rating of a file as required.
- You can configure file analysis in the 'File Rating settings' section of the configuration profile applied to the device. See File Rating settings in Creating a Windows Profile for more details.
- See File Ratings Explained for background information on file ratings.

The Application Control Interface



The 'Application Control' interface lets you view the trust rating of files on an endpoint. Possible ratings are 'Unrecognized', 'Trusted' or 'Malicious', with 'Unrecognized' and 'Malicious' files being reported to this interface. You can manually set the rating of a file at your discretion.


- Files rated as 'Trusted' are allowed to run as normal on the endpoint.
- Files rated as 'Malicious' are quarantined and not allowed to run.
- Files rated as 'Unrecognized' are run inside the container an isolated operating environment. Contained applications are not permitted to access files or user data on the host machine.

Any rating you set for a file is pushed to all managed endpoints on which the file is installed.

- You can also view a history of purged files. Purged files are those which existed on devices at one point in time, but are not currently present on any device.
- Apply the 'Show Purged Files' filter to view these files. See the explanation of Filter Options below.

You can also hide items as required.

• Click 'Security Sub-Systems' > Application Control' to open the application control interface:




Application Control - Table of Column Descriptions	
Column Heading	Description
File Name	The label of the application/executable file. Click the name of a file to view its details. See View file details given below for more details.
File Path	The installation location of the application on the endpoint. • Click the icon to copy the path to the clipboard.
File Hash	The SHA1 hash value of the executable file. • Click the icon to copy the hash value to the clipboard.
Size	The size of the executable file.
# of Devices	 The count of endpoints on which the item was found. Click the number to view the the 'Device List' interface with a list of endpoints containing the item. You can also view the activities of the item from here. For more details, refer to the description under Device List Screen below.
Comodo Rating	The rating of the file as per the Comodo File Look-up service, reported by the CCS installations at the endpoints. See File Ratings Explained for more details.



Admin Rating Indicates the rating of the file as manually set by the administrator, if any.

Sorting, Search and Filter Options

- · Click any column header to sort items in alphabetical order
- Click the funnel icon to open more filter options:



- · Use the check-boxes to show or hide purged, non-executable, hidden or unrecognized files.
- Use the search fields to filter by file name, file path or SHA1 hash value. You can also filter by file size and the number of devices on which the file is present.
- · Use the drop-down boxes to filter items by Comodo and/or Admin rating



To display all items again, clear any search filters and click 'OK'.

You can use any combination of filters simultaneously to search for specific apps.

Manage Applications

The Applications Control interface allows you to:


- View the details of files in the list
- View Process Activities of a File
- Assign Admin rating to a file
- Hide/Display selected files in the list
- Export the list of selected files to a CSV file
- · Remove files from the list

View file details

Simply click on a file in the list or select a file and click 'File Details' at the top. The 'file info' screen shows
basic file details and the devices on which the file is present. You can also change the trust rating of the file
in this area.

File information


- The file info screen shows file name, installation path, file type, version, size, hash values and the date the file was first encountered. The screen also shows the file's trust rating and the number of endpoints on which the file is present.
- The 'Change Rating' button allows you to manually set the file's rating as 'Trusted', 'Malicious' or 'Unrecognized':



The new rating will be sent to all endpoints.

The 'Record' button lets you hide, display or remove the file from the 'Application Control' list





Device List Screen

- Click 'Security Sub-Systems' > 'Application Control' then click on a file in the list.
- Next, select the 'Device List' tab to see a list of all devices on which the file is present
- The 'Device List' Screen can also be opened by clicking on the number in the 'Number of Devices' column in the 'Application Control' table.
- The device list screen shows each endpoint on which the item was discovered. The screen also shows the
 installation path, the installation date and the file rating assigned by Comodo Client Security. The Viruscope
 column shows detailed info on processes started by the file.



You can remove the file from device(s) by selecting a device then clicking 'Delete'

View Process Activities of a File


Note: In order to fetch process activity data, VirusScope should be enabled in the profile in effect on the endpoint. See **VirusScope Settings** in **Create a Windows Profile** for more details.

View the activities of a file on an endpoint


- Open the 'Device List' screen by clicking the file name or the number in the 'Number of Devices' column
- Click the 'View Processes' link in the 'Activity' column in the row of the device name.



This will open a list of processes executed by the file on the selected endpoint:




- Click 'View Activity' to see detailed information about each process. The 'Process Activity' interface has two tabs:
 - Summary Displays the name of the device and the installation path of the executable
 - Activity Displays a chronological list of activities by the selected process, including details of files
 modified by the process.





The 'Activity' - Table of Column Descriptions	
Column Heading	Description
Date	Indicates the date and time of process execution
Action	Indicates the action executed by the process on the target file
Path	Indicates the path of the target file
Details	Contains a link to view details of the action

You can inspect a particular activity by clicking the 'Details' link:



Assign Admin Rating to a File


- Each file on an endpoint is automatically scanned and assigned a trust rating by Comodo Client Security on the endpoint.
- These ratings can be either 'Unrecognized', 'Trusted' or 'Malicious'. The rating for each file is shown in the 'Comodo Rating' column of the 'Application Control' interface.
- The file rating determines whether or how the file is allowed to run:
 - Trusted The file will be allowed to run normally. It will, of course, still be subject to the standard protection mechanisms of Comodo Client Security (behavior monitoring, host intrusion prevention etc).
 - Malicious The file will not be allowed to run. It will be automatically quarantined or deleted depending on admin preferences.



- **Unknown** The file will be run inside the container. The container is a virtual operating environment which is isolated from the rest of the endpoint. Files in the container write to a virtual file system, use a virtual registry and cannot access user or operating system data.
- Automatic file rating can be configured in the 'File Rating' section of the configuration profile active on the endpoint. See File Rating settings in Create a Windows Profile for more details.
- Click 'Change Rating' in the 'Application Control' interface to manually set a rating for a selected file or files. The new rating will be propagated to all endpoints on which the item was identified and will determine the file's run-time privileges. Admin assigned ratings will be shown in the 'Admin Rating' column of the interface:

Assign a file rating to a file


- Select the file(s) whose rating you want to change and click 'Change Rating'.
- Choose the rating you want to from the drop-down:



As mentioned, the admin rating will be set and sent to all endpoints. The admin rating will determine the file's runtime privileges.

Hide/Display Selected Files

Select the file(s) you want to hide and click 'Record' at the top




Select 'Hide / Unhide / Delete Record' as required.



View hidden files


- · Click the funnel icon at the top-right to open the filter options
- Select 'Show with hidden file(s)' and click 'Apply'



The hidden files will be included to the 'Application Control' interface. These files will be highlighted with a gray stripe.

Restore hidden files

- · Click the funnel icon at the top-right to open the filter options
- Enable 'Show with hidden file(s)'
- Select the hidden files you want to restore click 'Record' and choose 'Unhide Record' from the drop-down




The files will be displayed in the file list permanently.



Export a Report of the Files List

You can export a file-rating report in .csv format as follows:

- Click 'Security Sub-Systems' > 'Application Control'
- Click the funnel icon to apply any filters you require
- · Click the 'Export' button and choose 'Export to CSV':



The report will be generated in .csv file format.


Report has been created. Please, check «<u>Reports</u>» in dashboard

The report will be available in the 'Dashboard' > 'Reports' interface. See **Reports** if you need more help with this interface.

Remove files from the list

You can hide files that you no longer wish to see in the list. The files will be removed from the list but will not be deleted from the endpoints.

- Select the files you want to remove and click 'Record' at the top
- · Choose 'Delete Record' from the drop-down





10.3.1. File Ratings Explained

Comodo Client Security (CCS) rates files on Windows devices as follows:

Unrecognized Files

Files that could not be identified as 'Trusted' or 'Malicious' by Comodo Client Security (CCS). You can review these files and can manually rate them as 'Trusted' or 'Malicious' as required.

Trusted Files

Files that are safe to run. Files can be classed as safe by the following:

- **File lookup service (FLS)** Whenever a file is accessed, Comodo Client Security (CCS) checks the file's reputation on Comodo's online file database.
- Vendor rating The app was created by a vendor who has a 'Trusted' status in the local vendor list. Open CCS > Click 'Settings' > 'File Rating' > 'Vendor List'.
- Admin rating You can assign a trusted rating to files in Endpoint Manager at 'Security Sub-Systems >
 'Application Control'.
- User rating Users can assign a trusted rating to a file in the CCS interface. There are two ways to do this:
 - Security alert If an executable is unknown then it may generate a HIPS alert on the local endpoint. Users could choose 'Treat this as a Trusted Application' at the alert
 - File List From the CCS home screen, click 'Settings' > 'File Rating' > 'File List'

CCS creates a hash of all files that a user classifies as 'Trusted'. So, even if the file name is changed it will keep its trust status because the hash remains same. This is particularly useful for developers creating new applications which, by their nature, are unknown to the Comodo.

Malicious Files

Files on the Comodo blacklist will be quarantined or deleted by CCS. These files are reported to Endpoint Manager as malware.

10.4. View List of Valkyrie Analyzed Files

Click 'Security Sub-Systems' > 'Valkyrie'

- The Valkyrie interface lists unknown files identified on all endpoints, along with their trust ratings.
- Valkyrie is a cloud-based file analysis service that tests unknown files with a range of static and behavioral checks. The service helps ITarian establish whether an unknown file is malicious or safe.
- You can configure Comodo Client Security on endpoints to auto-upload unknown files to Valkyrie.
- You can also view Valkyrie statistics by clicking 'Dashboard' > 'Valkyrie'.
- You can schedule the upload of unknown files in the 'Valkyrie' section of a Windows profile. See Valkyrie
 Settings if you need help with this.

Note: The version of Valkyrie that comes with the free version of Endpoint Manager is limited to the online testing service. The 'Premium' and 'Managed' versions of EM also includes manual file testing by ITarain research labs. This helps enterprises quickly create definitive whitelists of trusted files. Valkyrie is also available as a standalone service. Contact your ITarain account manager for further details.


- The Valkyrie interface
- View file details



Export the Valkyrie file list

The Valkyrie interface

• Click 'Security Sub-Systems' > 'Valkyrie'




Column Heading	Description
Name	The label of the unknown item
Path	The install location of the file on the endpoint.
	Click the icon to copy the file path to the clipboard.
Hash	The SHA1 hash value of the unknown file. Hash values uniquely identify a file, even if the file name changes.
	Click the icon to copy the hash value to the clipboard.
File Rating	The file's trust verdict from Valkyrie. The possible values are:
	Clean - The file is safe to run
	No Threat Found - No malware found in the file, but cannot 100% say it is safe to run
	Malware - The file is malicious and should not be allowed to run.
	Potentially Unwanted Application - Applications such as adware, browser toolbars etc. These applications are often bundled as an 'extra utility' with freeware applications. Users might not be aware they are installed, or may not be aware of their full functionality. For example, a browser toolbar may also contain code that tracks a user's activity on the internet. It is up to your discretion whether you allow these files to run.
First Seen by Comodo	Date and time at which the file was first received by Valkyrie.
View File Details	Complete information about a selected item. See View the details of files in the list for more.
Export	Save the list of analyzed files as a comma separated values (csv) file. See Export the List of Valkyrie Analyzed Files for more details.



View file details

Select a file and click the 'View File Details' button:





The details screen shows file name and version, installation path, size, hash value and trust ratings assigned by ITarian and by an EM admin.

Export the List of Valkyrie Analyzed Files

Export the list of files to a .csv file as follows:

- Click 'Security Sub-Systems' > 'Valkyrie'.
- Click the 'Export' button above the table then choose 'Export to CSV':




- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

10.5. Antivirus and File Rating Scans

Click 'Security Sub-systems' > 'Antivirus' to open this area.

This area allows you to:

- View the infection status of managed Windows, Mas OS, Linux and Android devices.
- · Run antivirus and file rating scans on devices.
- · View a consolidated list of all malware on all endpoints.
- View all quarantined files on Windows, Mac OS and Linux devices
- · View an all-time history of threats discovered on all endpoints
- Manually delete, quarantine or ignore malicious files



The 'Antivirus' interface has five tabs:

- Device List Shows the status of all managed devices with regards to antivirus health. The interface shows:
 - The date and type of the most recent virus scan
 - Whether or not the device is using the latest virus database
 - The malware status of the device (clean, infected or unknown)

You can also run an on-demand scan on a device, and delete/quarantine/ignore threats.

See The Device List Interface for more details.

- Current Malware List Lists all unprocessed malware residing on managed devices. You can delete, ignore or quarantine specific pieces of malware on specific devices, or apply these actions to multiple threats at once. See Viewing and Managing Identified Malware for more details.
- Quarantined Files Malware which has been quarantined by Comodo Client Security on Windows, Mac and Linux devices. You can delete or restore quarantined items, or assign a trust rating to items. See View and Manage Quarantined Items for more details.
- Android Threat History A log of all malicious items found on Android devices over time. See View Android Threat History for more details.
- Autorun Items List of files that tried to modify Windows services, auto-start entries or scheduled tasks.
 See View and Manager Autorun Items for more details.

The Device List Interface

The 'Device List' screen displays the infection status of Android, Mac OS, Windows and Linux devices. From here you can:

- Run on-demand antivirus scans on selected devices
- Run file rating scans on Windows devices
- Choose the action to be taken on malware discovered by scans.




- Update the AV database on endpoints
- Export device list data from the table

Note: You can run virus scans on specific areas of a device and setup ongoing, scheduled scans. These tasks are configured in the 'Antivirus' section of the device's configuration profile. See:

- Windows see Custom Scans and Create Windows Profiles.
- MAC see Scan Profiles and Create a Mac OS Profile.
- Linux see Create and Manage Scan Profiles and Create a Linux Profile

Open the 'Device List':

- Click 'Security Sub-Systems' > 'Antivirus'
- Select the 'Device List' tab
- Select a company and group on the left to view all devices in it Or
- · Select 'Show All' to view all devices enrolled to EM



The list shows all Android, Windows, Mac OS and Linux devices along with their last scan details, infection status and antivirus database update state.

Antivirus Device List - Column Descriptions	
Column Heading	Description
OS	The operating system of the device.
Name	 The label of the device on which the threat was found. If no name was assigned then the model number of the device is used. Gray text color shows the device has been offline for the past 24 hours. Click the name of the device to open its device details interface. See Manage Windows Devices, Manage Mac OS Devices, Manage Linux Devices and Manage Android / iOS Devices for more details.
Logged in User	The name of the user currently signed-in to the device. • The user name is prefixed with the active directory (AD) domain or workgroup that the user is currently logged-in to: • Active Directory - Name is shown as <ad domain="" name="">\<user name=""> • Workgroup - Name is shown as <workgroup name="">\<user name=""></user></workgroup></user></ad>



No network - Name is shown as <device name="">\<user name=""></user></device>
Click the icon to copy the username to the clipboard.
The update status of the virus signature database on the device.
The version number of the virus signature database on the device
The date and time at which the AV database was last updated
The source that initiated the last scan. An antivirus scan or a file rating scan can be initiated in the following ways:
 Portal - Manually run by an admin from the EM interface. See Run Antivirus and/or File Rating Scans on Devices for more details.
User - Manually run by the end-user at the device itself.
 Scheduled - Automatically run as per the schedule defined in the configuration profiles effective on the device.
Indicates the kind of the last scan ran on the device. The possible types of scan are: • Antivirus Full Scan - Applies to Windows, Mac OS and Android devices.
 Antivirus Quick Scan - Applies to Windows, Mac OS and Android devices.
 File Rating Quick Scan - Applies only to Windows devices.
 Custom Scan - Applies to Windows and Mac OS devices.
Manual Scan - Applies to Windows and Mac OS devices
SD Card Scan - Applies only to Android devices.
Status of the last scan run on the device. Possible states are:
Not scanned yet
Complete
Scanning
Failed
Viruses found
Canceled
Command sent
The date and time at which the last scan was run.
The infection status of the device.
Devices with untreated malware are listed as 'Infected'.
Click the 'Infected' link to view a list of malware on all managed devices.
You can remove, quarantine or ignore the malware direct from this list.
 See View and Manage Identified Malware if you want more help on this.
 Alternatively, you can also view/manage malware from the device details screen. Click "Security Sub-Systems' > 'Antivirus' > 'Device List'. See Handle Malware on Scanned Devices for more details.
Controls
Run a manual scan on selected devices. See Run Antivirus and/or File Rating Scans



	on Devices for more details.
Stop Scan	Terminate any type of on-going scans on selected devices. This includes on-demand scans run from the EM console, scheduled scans run by the security profiles active on the device and any on-demand scan run by the local user from the Comodo Client - Security (CCS) application on the device.
	See Run Antivirus and/or File Rating Scans on Devices for more details.
Protective Action	Remove, quarantine or ignore threats found on infected devices. See Handle Malware on Scanned Devices for more details.
Update Antivirus DB	Manually run a virus signature update on selected devices. See Update virus signature database on Windows , Mac OS and Linux Devices for more details.
Export	Save the device list, including current statuses, as a .csv file.
	The exported .csv is available in 'Dashboard' > 'Reports'
	See Export the List of Devices for more details.

The 'Antivirus' > 'Device List' interface allows you to:

- Run Antivirus and/or File Rating Scans on Devices
- Handle Malware on Scanned Devices
- Update virus signature database on Windows, Mac OS and Linux Devices


Sorting, Search and Filter Options

- Click any column header except 'Antivirus DB version' to sort items in ascending/descending order
- Click the funnel icon on the right to filter items by various criteria.
 - Start typing or select the search criteria in the search field to find a particular item and click 'Apply'
 - To display all items again, clear any filters and search criteria and click 'Apply'.
- EM returns 20 results per page when you perform a search. Click the arrow next to the 'Results per page' drop-down to increase results up to a maximum of 200.
- Use the left and right arrows and the page numbers to navigate to the page you want to view.

Export device list records as a CSV file

- Click 'Security Sub-Systems' > 'Antivirus' > 'Device List'
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button and choose 'Export to CSV':





- The .csv file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

10.5.1. Run Antivirus and/or File Rating Scans on Devices

- Click 'Security Sub-Systems' > 'Antivirus' > 'Device List'.
- The interface lets you run virus and file rating scans on Android, Mac OS, Windows and Linux devices.

Note: The scans interface lets you manage on-demand scans only. For automated scans, please create a scan schedule in a configuration profile then push it to selected devices/groups. See **Create Configuration Profiles** for more details.

Launch an on-demand scan

- Click 'Security Sub-Systems' on the left then select 'Antivirus'
- Click the 'Device List' tab
 - Select a company or a group to view their devices
 Or
 - Select 'Show All' to view all devices enrolled to EM
- Select the devices you wish to scan
- Choose a scan type from the 'Scan' drop-down
- The scan command will sent to the target devices and the scan will commence immediately

Tip: You can access filters by clicking the funnel icon at the top right. For example, you may want to display only devices with Last Scan States of 'Unknown', 'Scan Failed' and 'Scan Canceled'.


The scan types available depend on the OS of the selected device(s). The scan type defines the areas to be scanned on the selected device(s). The following sections explain the scan process for:

- Android Devices (Quick Scan, Full Scan, SD Card Scan)
- Windows Devices (Quick Scan, Full Scan, Quick Rating Scan)
- Mac OS Devices (Quick Scan, Full Scan)
- Linux Devices (Quick Scan, Full Scan)

Android Devices



• Click 'Scan' and choose the scan type from the drop-down to select the area to be scanned on the device.



The available scan profiles are:


- Antivirus Quick Scan Scans critical areas of the device which are highly prone to attack from viruses, rootkits and other malware. Areas scanned include RAM, hidden services and other significant areas like system files. These areas are of great importance to the health of the device so it is essential to keep them free of infection.
- Antivirus Full Scan Scans all folders/files in both the system internal memory and the SD card.
- SD Card Scan Scans all folders/files in the Secure Digital (SD) memory card mounted on the device.

The scan command will be sent to the selected device(s) and the scan status will be displayed in the 'Last Scan State' column for each device.

- If you want to terminate the scan, choose the devices and click 'Stop Scan' from the options at the top.
- If malware is found after the scan then the 'Last Scan State' will say 'Infected'. Infections identified after the scan will be treated according to settings in 'Settings' > 'Portal Set-Up' > Android Client Configuration' > 'Antivirus'. See **Configure Android Client Antivirus Settings** for more details.
- If 'Manual control' is chosen, then you have the option to uninstall or ignore from the 'Current Malware List'. See View and Manage Identified Malware for more details.
- You can also choose to uninstall or ignore the identified malware by clicking the respective buttons at the top. See Handle Malware Identified from Scanned devices section for more details.

Windows Devices

Click 'Scan' and choose the scan type from the drop-down to select the area to be scanned on the device.



The available scan types/profiles are:

- Antivirus Quick Scan Scans critical areas of the device which are highly prone to attack from
 viruses, rootkits and other malware. Areas scanned include. Areas scanned include include system
 memory, auto-run entries, hidden services, boot sectors and other significant areas like important
 registry keys and system files. These areas are of great importance to the health of each computer so it
 is essential to keep them free of infection.
- Antivirus Full Scan Scans every local drive, folder and file on each computer. Any external devices like USB drives, digital camera and so on are also scanned.
- Quick Rating Scan Runs a cloud-based assessment of files on the device to determine the trust rating of each file. The 'Quick' rating scan checks commonly infected areas and memory.

Files are rated as:

- Trusted the file is safe
- Unknown the trustworthiness of the file could not be assessed
- Bad the file is unsafe and may contain malicious code

The scan command will be sent to the selected device(s) and the scan status will be displayed in the 'Scan State' column for each device.


- If you want to terminate the scanning on selected devices, choose the devices and click 'Stop Scan' from the options at the top.
- If malware is found on completion of scan the Scan State will indicate 'Viruses Found'. You can choose to
 uninstall, ignore, delete the identified malware or to move them to quarantine at the endpoint for later
 analysis. See Handle Malware Identified from Scanned devices for more details.
- Items moved to quarantine are encrypted and saved in the endpoint itself, so that they are isolated from the
 rest of the system.
- You view the quarantined items from the 'Quarantine' interface. The Quarantine interface allows you to:
 - Delete an item, if it is identified as malicious



- Restore the file to its original location on the endpoint if the item is a false-positive. You can also
 rate a file as 'Trusted' to restore it to the endpoint. Doing so will effectively white-list the file by
 giving it a 'Trusted' rating in the local CCS database.
- See View and Manage Quarantined Items for more details.

Mac OS Devices

Click 'Scan' and choose the scan type from the drop-down to select the area to be scanned on the device.



The available scan profiles are:

- Antivirus Quick Scan Scans important operating system files and folders including system memory, auto-run entries, hidden services.
- **Antivirus Full Scan** Scans every local drive, folder and file on your system including external devices, storage drives, digital cameras.


The scan command will be sent to the selected device(s) and the scan status will be displayed in the 'Last Scan State' column for each device.

- If you want to terminate the scan on certain devices, choose the devices and click 'Stop Scan' from the options at the top.
- If malware is found on completion of scan the Last Scan State will indicate 'Viruses Found'. You can choose
 to uninstall, ignore, delete the identified malware or to move them to quarantine at the endpoint for later
 analysis. See Handle Malware Identified from Scanned devices for more details.
- Items moved to quarantine are encrypted and saved in the device itself, so that they are isolated from the rest of the system.
- You view the quarantined items from the 'Quarantine' interface. The Quarantine interface allows you to:
 - Delete an item, if it is identified as malicious
 - Restore the file to its original location on the endpoint if the item is a false-positive.
- See View and Manage Quarantined Items for more details.

Linux Devices

• Click 'Scan' and choose the scan type from the drop-down menu:





- Antivirus Quick Scan Scans important areas which are frequently targeted by malware. Areas scanned include system memory, important registry keys, auto-run entries, operating system folders and hidden services.
- Antivirus Full Scan Scans every local drive, folder and file on your system. Connected devices like USB sticks and external drives are also scanned.

The status of current, or previous, scans is shown in the 'Last Scan State' column.

- **Terminate a scan** Select target devices then click 'Stop Scan' from the options at the top.
- 'Viruses Found' You can uninstall, ignore, quarantine or delete the identified malware. See Handle Malware Identified on Scanned devices for more details.

10.5.2. Handle Malware on Scanned Devices

- Click 'Security Sub-Systems' > 'Antivirus' > 'Device List'
- Click the 'Protective Action' button to remove, ignore or quarantine the malware.

Note:

- This interface lets you apply actions to all malware found on specific devices.
- If you instead want to apply actions to individual malware, please use the 'Current Malware List'.
 - Click 'Security Sub-Systems' > 'Antivirus' > 'Current Malware List'.
 - See View and Manage Identified Malware if you need more help with this interface.

Apply actions to ALL malware on selected devices

- Click 'Security Sub-Systems' > 'Antivirus'
- Click the 'Device List' tab


ITarian Endpoint Manager - Administrator Guide



- Click a company name/group on the left to view their devices
 Or
- Select 'Show All' on the left menu to view every device enrolled to EM
- Select device(s) with a malware status of 'Infected' using the check-box(es) on the left.

Tip: You can filter the list to search for specific devices by clicking the funnel icon at the top right of the table.

• Click 'Protective Action' above the table and select your desired action:




The actions available depend on the OS of the device chosen:

For Android Devices:

- Delete Removes the malicious app
- **Ignore** Ignores malware found by the last scan. The item will be identified as malware again on the next scan.


For the 'Delete' operation, a notification will be sent to the selected devices to uninstall the apps:






The notification shows the number of threats which will be removed from the device.

Touch the alert to view all items which are ready for removal.



• Tap on the malware to be removed, confirm the removal in the next dialog and follow the uninstall wizard.





For Windows. Mac OS and Linux Devices

- Delete Instructs CCS on the endpoint to clean the malware.
 - If a disinfection routine is available, CCS will disinfect it and retain the original file.
 - If a disinfection routine is not available, CCS will delete the application.
- Quarantine Moves the malware to quarantine on the device.
 - Click 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files' to manage guarantined files.
 - Based on their trustworthiness, you can remove them from the device or restore them to their
 original locations. See View and Manage Quarantined Items for more details.

10.5.3. Update Virus Signature Database on Windows, Mac OS and Linux Devices

- Click 'Security Sub-Systems' > 'Antivirus' > 'Device List'
- Select a device using the check-boxes on the left > Click the 'Update Antivirus DB' button
- You can update the database manually or according to a schedule.

Automatic Updates

- Windows devices Configure the 'Update' component of the Windows profile applied to a device. See
 Client Security Update in Creating Windows Profiles for more details.
- MAC OS devices Configure the 'Antivirus' component of the Mac OS profile applied to a device. See
 Configure Antivirus Settings in Antivirus Settings for Mac OS Profile for more details.
- Linux devices Configure the 'Antivirus' component of the Linux profile applied to a device. See Antivirus
 Settings for Linux Profile for more details.

Manual Updates


- Click 'Security Sub-Systems' on the left then select 'Antivirus'
- Click the 'Device List' tab



- Click a company or a group to view only their devices
 Or
- Select 'Show All' to view every device enrolled to EM
- Select the Windows, Mac OS and/or Linux device(s) on which you wish to update the virus database

Tip: You can filter the list or search for specific device(s) by clicking the funnel icon at the top right of the table.

Click 'Update Antivirus DB' from the options at the top:



A command is sent to target devices to start downloading the updates.

10.6. View and Manage Identified Malware

Click 'Security Sub-Systems' > 'Antivirus' > 'Current Malware List'

- The 'Current Malware List' shows malicious items on which no action has yet been taken. This is malware
 that has NOT been quarantined or deleted.
- You can also assign a 'Trusted' rating to an item. Use this option if you think the item is a false positive. The item will not be flagged by future scans.

How do files get on this list?

View the malware list

Take action on the malware

- Android devices
- Windows devices
- Mac OS devices
- Linux devices
- Export malware list

Background. This box explains the conditions under which a file will appear in the current malware list.



Windows Devices:

Real-time virus monitor:

- Threats are shown in the list if:
 - Show antivirus alerts' is disabled and 'Block Threats' is chosen as the default action in the profile
 active on the device

OR

- Show antivirus alerts' is enabled and the user decides to click 'Ignore' at the alert.
- Threats are NOT shown in the list if:
 - Show antivirus alerts' is disabled and 'Quarantine Threats' is set as the default action OR
 - Show antivirus alerts' is enabled and the user quarantines the threat at an alert.
- To view the settings above:
 - Click 'Configuration Templates' > 'Profiles' > Click the name of any Windows profile > 'Antivirus' tab > Open the 'Realtime Scan' tab.
- See Realtime Scan settings in Antivirus Settings if you need more help with this.

Scheduled and manual scans:

- Threats are shown in the list only if 'Automatically clean threats' is disabled in the profile active on the device.
- To view the setting above:
 - Click 'Configuration Templates' > 'Profiles' > Click the name of any Windows profile > 'Antivirus' tab > 'Scans' tab > Click the 'Edit' icon beside a profile > Click the 'Options' bar.
- See Custom Scans in Antivirus Settings if you need more help with this.

Mac OS Devices:

- Threats only appear in this list if 'Auto-Quarantine' is disabled in the profile on the device.
- Threats will NOT appear in this list if:
 - 'Auto quarantine' is enabled in 'Realtime scanning', 'Manual Scanning' and 'Scheduled Scanning'
 - 'Auto quarantine' is disabled but the user chooses to quarantine the item from an alert

Linux Devices:

- Threats only appear in this list if 'Auto-Quarantine' is disabled in the profile on the device.
- Threats will NOT appear in this list if:
 - 'Auto quarantine' is enabled in 'Realtime scanning' and 'Scheduled Scanning'
 - 'Auto guarantine' is disabled but the user chooses to guarantine the item from an alert
- See 'Configure Scanner Settings for CCS for Linux' in Antivirus Settings for Linux Profile in Create a Linux Profile for more details.

Android Devices:


- Threats are shown in the list if the threat is ignored on the device. This can be because:
 - 'Manual control' is selected in Android client antivirus settings, or
 - 'Automatic response' is selected with 'Ignore' as the response in Android client antivirus settings.



- To view the settings above:
 - Click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Android' > 'Antivirus'
 - Click here for more information on this setting

View the malware list

- Click 'Security Sub-Systems' > 'Antivirus'
- · Click the 'Current Malware List' tab
 - Click a company or a group to view malware identified on their devices
 Or
 - Select 'Show All' to view malware identified on every device in EM



Current Malware List - Column Descriptions	
Column Heading	Description
OS	The operating system of the device on which the malware was identified.
Device Name	The label of the device on which threats were found. If no name was assigned then the model number of the device is used. Gray text color shows the device has been offline for the past 24 hours. Click the name of the device to open its device details interface. See Manage Windows Devices, Manage Mac OS Devices, Manage Linux Devices and Manage Android / iOS Devices for more details.
Application Name	The label of the infected file.
Package Name / File Path	Windows, Linux and Mac OS devices - Shows the location of the malware Android devices - Shows the package name or identifier. • Click the icon to copy the package name/ file path to the clipboard.
File Hash	The SHA1 hash value of the file. • Click the iii icon to copy the hash value to the clipboard.
Signature	The malware signature.



	 Signatures enable the scanner to identify viruses. Each malware signature represents a snippet of malicious code unique to a virus.
	 The signatures of known-malware are stored in the local antivirus database. This is also known as the 'blacklist'.
	 If the scanner finds a file with a signature that matches one on the blacklist then it raises a virus alert.
Detection Date	Date and time that the malware was discovered.
	Controls
Delete Malware	Uninstalls/removes the malware infected item from the device.
	Applies to items identified from devices of all operating systems.
Ignore Malware	The item will be allowed to remain on the device.
	Applies to items identified from Android devices only.
Quarantine Malware	Moves the selected items to quarantine on the respective devices.
	Applies to items identified from Windows, Mac OS and Linux devices.
Rate as Trusted	Awards 'Trusted' file rating to the selected items. Please make sure before marking a file as trusted. Use this option only for false positives and genuine items.
	 Applies only to items identified from Windows devices.
Export	Save the list of currently displayed threats as a comma separated values (CSV) file.
	The exported .csv is available in 'Dashboard' > 'Reports'
	See Export the List of Malware for more details.


- · Click any column header to sort items in ascending/descending order.
- Click the funnel icon on the right to filter items by various criteria.
 - · Start typing or select the search criteria in the search field to find a particular item and click 'Apply'
 - To display all items again, clear any filters and search criteria and click 'Apply'.
- EM returns 20 results per page when you perform a search. You can increase results up to a maximum of 200

Take action on the malware

- You can uninstall/delete malicious items from the devices on which they were found.
- Alternatively, if you think an item is a false positive, you have the following options:
 - Ignore malware Applies to items identified on Android devices only. The item will not be uninstalled and will be skipped in the future scans.
 - Rate as 'Trusted' Applies to items identified on Windows devices only. The item will be allowed to run and will be skipped in future scans.
- If an item is found to be suspicious, you can choose to move it to quarantine for later analysis and removal.

The options at the top of the table let you take actions on selected items. The available actions depend on the operating system of the device(s).






Threats identified on Android Devices

Action on malware depends on the Android device type. Knox and non-Knox devices. Knox is a security technology used by Samsung for its devices.


First, select the items on which you want to take the action. Then click one of the following:

- **Ignore Malware** Select if the item is a false positive. The item will remain on the device and skipped in future scans.
- Delete Malware Select if you want to remove the malware from the device.
 - Knox devices Applications with viruses or infected files on the devices and from the SD card are deleted without any alert on the device.
 - Non-Knox devices Infected files on the SD card are deleted without any alert. The following notification is sent to the affected device for removal of malware on the device.






Touch the alert to view a list of all items which are ready to be removed:



• Tap on the malware to be removed, confirm the removal in the next dialog and follow the uninstall wizard.



Threats identified on Windows Devices:

First, select the items on which you want to take the action. Then click one of the following:

- **Delete Malware** Will remove the malware from the device.
- Quarantine Malware The items will be moved to quarantine on the respective devices. You can delete the
 items from quarantine later, or restore them to their original locations. See View and Manage Quarantined
 ltems for more details.
- Rate as Trusted Trusted files are considered safe to run. Trusted items can run outside the container on devices and will be skipped in future scans. See File Ratings Explained for more details on trust ratings of files.



Threats identified on Mac OS Devices:

First, select the items on which you want to take the action. Then click one of the following:

- Delete Malware Will remove the malware from the device.
- Quarantine Malware The items will be moved to quarantine on the respective devices. You can delete the
 items from quarantine later, or restore them to their original locations. See View and Manage Quarantined
 ltems for more details.


Threats identified on Linux Devices:

First, select the items on which you want to take the action. Then click one of the following:

- Delete Malware Will remove the malware from the device.
- Quarantine Malware The items will be moved to quarantine on the respective devices. You can delete the
 items from quarantine later, or restore them to their original locations. See View and Manage Quarantined
 ltems for more details.

Export the List of Malware

- Click 'Security Sub-Systems' > 'Antivirus' > 'Current Malware List'
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button then choose 'Export to CSV':



- The .csv file is available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

10.7. View and Manage Quarantined Items

Click 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files'

- Quarantine is a secure holding area for potentially dangerous files. Quarantined files pose no threat to your system.
- You can delete or restore quarantined items, or assign a file rating to them.
- File ratings determine how CCS handles the file:



- Files rated as 'Malicious' will stay in guarantine on the device.
- Files rated as 'Unrecognized' will be restored to their original locations on the device. Future virus scans may flag them as malicious again.
- Files rated as 'Trusted' will be restored to their original locations on the device. These files are skipped in future virus scans.

How do threats get quarantined?

Windows Devices

Real time scans - Threats are placed in quarantine if:

- 'Show antivirus alerts' is disabled and 'Quarantine Threats' is set as the default action in the profile on the device. This setting is in the 'Realtime Scan Settings' area of the profile's antivirus section.
- 'Show antivirus alerts' is enabled and the end-user quarantined the threat at an alert.
- See **Realtime Scan settings** if you want to read more about the antivirus section of a profile.

On-demand / Scheduled scans - Threats are placed in quarantine if:

- 'Automatically clean threats' is enabled and 'Quarantine' is set as the action in the profile on the device.
- See Custom Scans in Antivirus Settings if you need more help with this.

DLP Scans

- Documents quarantined by a Data Loss Prevention (DLP) scan are NOT shown in this interface. They are placed in a different quarantine area.
- You can view DLP quarantined files at 'Security Sub-Systems' > 'Data Loss Prevention' > 'Logs'
- You cannot restore DLP quarantined files remotely using Endpoint Manager. You can only restore them through Comodo Client Security on the endpoint.

Manual quarantine:

- Admins can move threats to quarantine from the 'Current Malware List' interface.
- End-users can move files to guarantine on their endpoint.
- See View and Manage Identified Malware for more details.

MAC OS Devices

Real time scans - Threats are placed in quarantine if:

- 'Automatically quarantine threats found during scanning' is enabled in the profile on the device. This setting is in the 'Realtime Scan Settings' area of the profile's antivirus section.
- The end-user chooses to quarantine the threat at an alert
- See the explanation of Realtime Scanner settings in the section Antivirus Settings for Mac OS Profile under Create a Mac OS Profile

On-demand / Scheduled scans - Threats are quarantined if:

- 'Automatically quarantine threats found during scanning' is enabled in the profile on the device
- See Manual Scanner settings and Scheduled Scanner settings for more help with this.

Manual quarantine:

- An administrator moved a threat to guarantine from the 'Current Malware List' interface
- An end-user moved a file to guarantine on the endpoint
- See View and Manage Identified Malware for more details.



Linux Devices

Real time scans - Threats are quarantined if:

- 'Automatically quarantine threats found during scanning' is enabled in the profile on the device. This setting is in the 'Realtime Scan Settings' area of the profile's antivirus section.
- The end-user chooses to quarantine the threat at an alert
- See Realtime Scanner settings for more help with this under Create a Linux Profile

On-demand / Scheduled scans - Threats will be placed in quarantine if:

- · 'Automatically quarantine threats found during scanning' is enabled in the profile on the device
- See Realtime Scanner settings and Scheduled Scanner settings to view help on these settings.


Manual quarantine:

- An administrator moved a threat to guarantine from the 'Current Malware List' interface
- An end-user moved a file to quarantine on the endpoint
- See View and Manage Identified Malware for more details.

Items moved to quarantine are encrypted and not allowed to run.

Open the quarantine interface

- Click 'Security Sub-Systems' > 'Antivirus'
- Click the 'Quarantined Files' tab
 - Select a company or a group to view malware identified on their devices
 Or
 - · Select 'Show All' on the left menu to view malware identified on all devices enrolled to EM



'Quarantine Files' - Table of Column Descriptions	
Column Heading	Description
OS	The operating system of the device at which the item was quarantined.
File Name	The file that was moved to quarantine. Click the name of a file to view its details. See View details of a quarantined item for more details.
Hash	The SHA1 hash value of the quarantined file • Click the icon to copy the hash value to the clipboard.




Signature	The name of the identified malware. 'User Item' indicates the file was moved to quarantine manually by the user on the endpoint.
Comodo Rating	The file's trust level as rated by CCS.
Admin Rating	The trust rating of the file as set by the administrator. Files can be rated as trusted, malicious or unrecognized.
Devices Detected On	The number of devices on which the item was quarantined. Click the number to view the list of devices on which the item was quarantined See the explanation of Device Details given below
First Quarantined	Date and time at which the malware was identified and quarantined the first time.

The quarantine interface allows you to:

- · View details of a quarantined item
- Restore False Positives from Quarantine
- Remove Malware files from the devices
- · Rate files as 'Unrecognized', 'Trusted' or 'Malicious'
- Export the list of quarantined files as a CSV file

View Details of a Quarantined Item

- Click 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files'
- Click on the file name of an item in the list:



- This will open the file details interface which shows:
 - **File Info** General information such as OS, file-name, hash, file rating, number of devices on which the file was quarantined, and more.



Device List - Shows list of endpoints upon which the file was found with heir details like installation
path of the file on each device, the device owner and the date and time at which the file was
quarantined.

Device Details



The options on the top let you to:

- · Restore False Positives from Quarantine on a device
- Remove the item from a device
- Rate files as 'Unrecognized', 'Trusted' or 'Malicious'
- · See the following sections for more details


Manage Quarantined Items

- If your review confirms that a quarantined item is a genuine threat then it can be deleted from endpoints.
- Conversely, if an item is is found to be a false positive, you can restore it to its original location.
- You can also rate a file as unrecognized, trusted or malicious based on your assessment. The new verdict
 will be sent to all endpoints and will be reflected in the 'Unrecognized' and 'Trusted' interfaces.

Restore False Positives from Quarantine

• If the identified item is a false positive, select the item from the list and click 'Restore File(s) on Devices' from the options at the top.


The item will be restored to its original location on all devices and removed from the list.



Remove Malware files from the devices



Select the item(s) from the list and click 'Delete File(s) From Device' from the options at the top.




Click 'Confirm' in the confirmation dialog.

The file will be deleted from all devices at which it was quarantined and removed from the list.

Rate files as 'Unrecognized', 'Trusted' or 'Malicious'

- If the rating of a quarantined file is changed to 'Trusted' or 'Unrecognized', the file is restored to its original location. The new rating is also stored in the CCS database on the devices.
- To change the rating of a quarantined file, select it and click the appropriate button at the top:



A confirmation will be displayed and the information will also be sent to the devices.



- Files rated as 'Malicious' will stay in quarantine on the device.
- Files rated as 'Unrecognized' will be restored to their original locations on the device. Future AV scans may flag them as 'malicious' again.
- Files rated as 'Trusted' will be restored to their original locations in the device. These files will be white-listed and skipped by future antivirus scans.

Export guarantined files records as a CSV file

- Click 'Security Sub-Systems' > 'Antivirus' > 'Quarantined Files' tab
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button and choose 'Export to CSV':



The report will be generated in .csv format.

Report has been created. Please, check «<u>Reports</u>» in dashboard

The file will be available in 'Dashboard' > 'Reports'. See **Reports** if you need more help with this interface.

10.8. View Android Threat History


Click 'Security Sub-Systems' > 'Antivirus' > 'Android Threat History'

- The threat history area is a record of all malicious events on your Android devices since you deployed Endpoint Manager.
 - To view threats recorded on Windows, Mac OS and Linux devices go to 'Security Sub-Systems' > 'Security Dashboard'
- The Android threat history list shows old events caused by malware which has been removed, and new
 events by malware which is still present.
- Endpoint Manager retains logs of malicious events for 12 months for PCI-DSS compliance.
- You can remove unnecessary entries from the list as required

View threat history

- Click 'Security Sub-systems' > 'Antivirus'.
- Click the 'Android Threat History' tab.
 - Select a company or a group to view events on their devices
 Or
 - Select 'Show All' on to view events on all devices added to EM






Column Heading	Description
Device Name	The label assigned to the device. If no name was assigned by the end-user, the model number of the device is used. A gray text color indicates the device has been offline for the past 24 hours.
	Click the device name to view granular details about the device.
	See Manage Android / iOS Devices for more details.
Application Name	The name of the infected application.
Package Name / File	Malware detected on installed application – Shows the package name
Path	Malware detected in APK file system – Shows the file path to the app
Signature	The name of the identified malware.
Status	Whether the malware was uninstalled, yet to be uninstalled or ignored.
First Detection	Date and time of the scan which first discovered the malware on the device.
Last Detection	Date and time of the last scan to discover the malware.

Remove unwanted entries from the Android threat history interface

• Select the log entries you want to remove then click 'Clean History for File(s)' at the top






- Click 'Confirm' to remove the entries from the list
- Deleting file history will only remove the log entry. The file isl not removed from the device or from any other interfaces in which it is listed (for example, the quarantine list).

Sorting, Search and Filter Options

- Click any column header to sort items in ascending/descending order of the entries in that column
- Click the funnel icon on the right to filter items by various criteria, including by OS, device name, application name, package name/file path, signature, status and first/last detection dates.
- Start typing or select the search criteria in the search field to find a particular item and click 'Apply'
- To display all items again, clear any filters and search criteria and click 'Apply'.
- EM returns 20 results per page when you perform a search. Click the arrow next to the 'Results per page' drop-down to increase results up to a maximum of 200.
- Use the left and right arrows and the page numbers to navigate to the page you want to view.

Export threat history records as a CSV file

- Click 'Security Sub-Systems' > 'Antivirus' > 'Antivirus Threat History' tab
- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button and choose 'Export to CSV':





The report is generated in .csv file format.

Report has been created. Please, check «<u>Reports</u>» in dashboard

Click 'Dashboard' > 'Reports' to view the report. See **Reports** if you need more help with this interface.

10.9. View and Manage Autorun Items

- Click 'Security Sub-Systems' > 'Antivirus' > Click the 'Autoruns Items' tab
- This area lets you view and take action on items blocked by the boot protection feature of Comodo Client Security (CCS).
- This includes unrecognized Windows services, auto-start entries and scheduled tasks.

From this interface, you can:

- Assign a rating to quarantined auto-run items (trusted, malicious or unrecognized)
- Delete them permanently
- Restore them to their original location

How do unrecognized autoruns items get terminated?

Unrecognized auto-runs will be terminated if:

'Apply this action to suspicious auto-run processes' is enabled

with

'Terminate', 'Terminate and Disable' or 'Quarantine and Disable' set as the action.


You can implement this setting in two places:

- 1) The 'miscellaneous' section of a profile. This applies the action to the real-time virus scanner. See **Miscellaneous Settings**
- 2) The 'Options' section when you create a custom virus scan. See **custom scans** in **Antivirus Settings** https://help.comodo.com/topic-399-1-786-10202-antivirus-settings.html#custom scans.

Open the interface

- Click 'Security Sub-Systems' > 'Antivirus'
- Click the 'Autoruns Items' tab
 - Select a company or a group to view auto-runs on their devices
 Or
 - Select 'Show All' to view all terminated auto-runs





Column Heading	Description	
Date	The date and time the auto-run was terminated on the device	
Туре	The auto-run category:	
Action	How the unrecognized autorun was treated on the endpoints: Terminated Terminated and Disabled Quarantined and Disabled	
# of Devices	The number of devices on which the item was terminated Click the number to view the list of devices on which the item was terminated See the explanation of Device Details given below	
File Name	The file whose auto-run entry was terminated Click the name of a file to view its details See View details of a terminated autorun item for details	
File Hash	The SHA1 hash value of the quarantined file. The hash value uniquely identifies the item even if its filename is changed. • Click the icon to copy the hash value to the clipboard.	
File Path	The location of the file on the endpoint	
Comodo Rating	The file's trust level as rated by CCS.	
Admin Rating	The trust rating of the file as set by the administrator. Files can be rated as trusted, malicious or unrecognized.	
Last Action Group	Indicates the latest action taken by the admin.	
Autorun Status	Shows whether the auto-run is enabled or disabled on the endpoint	




- · Click a column header to sort items in ascending / descending / alphabetical order
- · Click the funnel icon at top-right and search by various parameters

You can perform the following tasks from the auto-runs page:

- View details of a terminated autorun item
- Restore autorun item on devices
- Delete autorun item from devices
- Rate autorun items as unrecognized, trusted or malicious
- Export the list of autorun items as a CSV file

View Details of a Terminated Autorun Item


- Click 'Security Sub-Systems' > 'Antivirus' > 'Autoruns Items'
- Click the file name of an item in the list:



- This will open the file details interface which shows:
 - **File Info** General information such as file-name, hash, file rating, number of devices on which the file was terminated, and more.
 - **Device List** Shows a list of the endpoints on which the file was found, along with details like file installation path.

Device Details





The options on the top let you to:


- Restore terminated autorun on a device
- Remove the item from a device
- Rate files as 'Unrecognized', 'Trusted' or 'Malicious'
- See the following sections for more details

Manage Terminated Autorun Items

- If your review confirms that an autorun item is a genuine threat then it can be deleted from endpoints.
- Conversely, if an item is is found to be a false positive, you can restore it to its original location.
- You can also rate a file as unrecognized, trusted or malicious based on your assessment. The new verdict will be sent to all endpoints and will be reflected in the 'Unrecognized' and 'Trusted' interfaces.

Restore Autorun Items on Devices


• If the identified item is a false positive, select the item from the list and click 'Restore Autorun on Devices' from the options at the top.



Delete Autorun Items from Devices



• Select the item(s) from the list and click 'Delete Autorun from Device' from the options at the top.




Click 'Confirm' to remove the files

The file will be deleted from all devices on which it was terminated and removed from the list.

Rate Autorun Items as 'Unrecognized', 'Trusted' or 'Malicious'

• To change the rating of a file, select it and click the appropriate button at the top:



A confirmation will be displayed and the information sent to the devices.


- Files rated as 'Trusted' will be restored to their original locations in the device. These files will be whitelisted and skipped by future antivirus scans.
- Files rated as 'Unrecognized' or 'Malicious' will be quarantined or their processes will be terminated per the profile settings.

Export Terminated Autorun Items as a CSV File

Click 'Security Sub-Systems' > 'Antivirus' > 'Autoruns Items' tab



- Click the funnel icon to filter which records are included in the report.
- · Click the 'Export' button and choose 'Export to CSV':



The report will be generated in .csv format.

Report has been created. Please check «<u>Reports</u>» at the Dashboard

The file will be available in 'Dashboard' > 'Reports'. See **Reports** if you need more help with this interface.


10.10. View History of External Device Connection Attempts

- Click 'Security Sub-Systems' > 'Device Control' to view all connection attempts from external devices to your Windows endpoints
- Endpoint Manager can create a log entry when an external device attempts to connect to a Windows endpoint. External devices include USB devices, DVD drives, printers, Bluetooth devices etc.
- These logs are created when the Windows profile contains the 'External Devices Control' section. See
 External Devices Control Settings for more details.
- You can also generate a report of external device connection attempts.

View a history of device connections:

Click 'Security Sub-Systems' > 'Device Control'





Device Control - Column Descriptions		
Column Header	Description	
Hardware Name	Displays the name of the external device which attempted to connect to a managed Windows device	
Date Detected	The date and time at which the device was first detected	
Hardware Class	The Globally Unique Identifier (GUID) of the device class which attempted to connect.	
Hardware Path	The Device Instance Identifier of the external device which attempted to connect.	
Host Device	The name of the Windows device to which the connection attempt was made. This column also shows the host's current connection status (connected or removed)	
Status	Indicates whether the connection was allowed or blocked. This depends on the settings in the 'External Devices Control' section of the profile active on the host device.	

Sorting, Search and Filter Options


- Click any of the 'Hardware Name', 'Hardware Class', 'Host Device' or 'Status' column headers to sort the items based on alphabetical order of entries in that column.
- Click the funnel button at the right end to filter the items based on device name, hardware class, hardware path, host, status and/or detection date.
 - Enter the search criteria in the respective field and click 'Apply'.
- To display all the items again, remove / deselect the search key from filter and click 'OK'.
- EM returns 20 results per page when you perform a search. To increase the number of results displayed per page up to 200, click the arrow next to 'Results per page' drop-down.
- Use the left and right arrows and the page numbers at the bottom to navigate to the page you want to view.

Generate a report containing log of device connection attempts

• Click 'Security Sub-Systems' > 'Device Control'



- Click the funnel icon to apply filters to the report.
- Click the 'Export' button and choose 'Export to CSV':



The report will be generated in .csv file format.

Report has been created. Please, check «<u>Reports</u>» in dashboard

The report can be accessed in the 'Dashboard' > 'Reports' interface. See **Reports** in **The Dashboard** if you need more help with this interface.

10.11. Data Loss Prevention Scans


Click 'Security Sub-systems' > 'Data Loss Prevention'

DLP scans let you search managed endpoints for sensitive data like card numbers, social security numbers and bank account numbers.

- You first create the discovery scan rules at 'Configuration Templates' > 'Data Loss Prevention'
- You then add a 'Data Loss Prevention' section to a profile:
 - Click 'Configuration Templates' > 'Profiles' > click on the name of a Windows profile
 - Click 'Add Profile Section' > 'Data Loss Prevention'
 - Click the 'Add' button, then add the discovery rules you created in step 1.
 - Save the profile. The scan will run on all devices on which the profile is active.

'Security Sub-systems' > 'Data Loss Prevention' lets you view the results of those scans:





The area lets you:

- View devices on which DLP scans are active
- Manually run DLP scans on selected devices
- View log files that contain sensitive information
- · View files quarantined by the DLP system on endpoints

Click the following links for help with each tab:


- Device List
- Logs
- Quarantined Files

Device list

- Click 'Security Sub-systems' > 'Data Loss Prevention'
- · Select the 'Device List' tab
- The interface shows devices on which DLP scans are active:

ITarian Endpoint Manager - Administrator Guide








Column Heading	Description		
Name	The label of the device on which the scan was run. Click the name to view its details See Manage Windows Devices for more details.		
Logged in User	The name of the user currently signed-in to the device. The username is prefixed with the active directory (AD) domain or workgroup to which the user belongs: • Active Directory - Name is shown as <ad domain="" name="">\cuser name> • Workgroup - Name is shown as <workgroup name="">\cuser name> • No network - Name is shown as <device name="">\cuser name></device></workgroup></ad>		
Rule Name	The DLP rule under which the last scan was run DLP rules set the conditions of the scan itself. See Create DLP Discovery Rules and Add them to Profiles for more.		
Rule State	The status of the last scan. The possible values are: Not scanned yet In progress Canceled Failed Completed		
Scan Date	Date and time of the last scan.		
Details	View files containing sensitive information that were found on the device. Click 'Security Sub-systems' > 'Data Loss Prevention' > 'Logs interface' to view files found on all devices. See DLP Logs to read more about the scan results.		
	Controls		
Action on Endpoint	Run a manual scan on selected devices. See Run DLP Scans for more details.		

Run a manual DLP scan

- Select your target devices
- Click 'Action on Endpoint' > 'Run all discoveries':





- The scan command is sent to the selected devices.
- Click the 'Details' link when the scan finishes to view files containing sensitive information
- See **DLP Logs** to read more about the scan results.

10.11.1. DLP Logs


Click 'Security Sub-systems' > 'Data Loss Prevention' > 'Logs'

- · The logs tab shows DLP events on endpoints.
- Log details include the name of the file, its location on the device, the rule that discovered the file, and the type of sensitive information in the file.
- You can use the 'Remote Tools' feature to connect to the target device and access the files at the path provided. You can then move/ remove/ edit file permissions as required.

View DLP scan logs

- Click 'Security Sub-systems' > 'Data Loss Prevention'
- · Click the 'Logs' tab.
- The interface shows all monitoring and discovery rule events:






Column Heading	Description
Date Time	The date and time the file was discovered
Component	The type of rule that generated the log. This can be either a discovery rule or a monitoring rule.
Action	The CCS response when the rule was triggered. You can use the remote tools feature to access and take actions on files found by discovery rules.
	See Remotely Manage Folders and Files on Windows Devices for help to do this.
Device Name	The affected endpoint.
	Click the name of the device to view its details.
Rule	The name of the DLP rule for which the event is logged.
File Name – Discovery	The file in which sensitive data was found.
rule only	Click the copy the file name to clipboard.
File Path – Discovery	The location of the file on the device.
rule only	Click the clipboard.
Pattern – Discovery rule only	The type of data contained in the file. For example, 'Name + Social Security Number'.
Match Count – Discovery rule only	Number of instances of the pattern that were found in the file.
Details - Discovery rule only	Click this to view the sensitive file found on the endpoint. See below for an example.

- Click the details link in a discovery rule log row
- An example of file details is shown below:





The 'match' column shows the first and last two characters of the discovered data. The option to show this should be enabled in the discovery rule.

Click 'Ok' to return to logs screen.

Take action on the files

After identifying sensitive information, there are two ways you can connect to the device to manage the files:

- Endpoint Manager Click 'Devices' > 'Device List' > select a running Windows device > Click 'Remote Tools' > 'File Explorer'.
 - See Remotely Manage Folders and Files on Windows Devices for help to do this.
- Remote Control app Click 'Devices' > 'Device List' > 'Device Management' > select a Windows device > Click the 'File Transfer' button.
 - You need to download and install the remote control app to do this
 - See Transfer Items to / from the Remote Computer for help to do this


10.11.2. DLP Quarantined Files

Click 'Security Sub-systems' > 'Data Loss Prevention' > 'Quarantined Files'

The DLP quarantined files screen shows files that were quarantined on endpoints by a discovery rule.

- Click 'Security Sub-systems' > 'Data Loss Prevention'
- · Click the 'Quarantined Files' tab.






Column Heading	Description	
Date	The date and time the file was quarantined.	
File Name	The file in which sensitive data was found. • Click the iii icon to copy the file name to clipboard.	
	Click the name to view file details.	
File Path	The location of the file on the device.	
	Click the clipboard.	
File Hash	The SHA1 hash value of the executable file.	
	 Click the icon to copy the hash value to the clipboard. 	
Rule Name	The discovery rule that quarantined the file	
Pattern Name	The data format that the rule searched for. For example, an 'ABA routing number' is a nine digit code.	
Device Count	Number of devices on which the file was quarantined. Click the number to view the device details.	
Status Action	The admin's response to the quarantined file. It can be deleted, restored or none.	
Controls		
Delete Files from Devices	Remove files from the endpoints. Select file(s) and click this link above.	
Restore File on Devices	Move files to original locations on the endpoints. Select file(s) and click this link above.	

File Details

Click the file name to view its details:






The details of the file such as its name, date quarantined and more are shown.

- **Delete File from Device** Remove the file from the endpoint
- Restore File on Devices Move the file from quarantine back to its original location
- 'Device List' tab Shows endpoints on which the file was quarantined. See below for more.

Device Details

Click the device number to view its details:






- Device Name The name of the endpoint. Click the name to view its full details.
- File Path The original location of the quarantined file.
- Owner Name Logged in user name.
- Date Date and time the file was quarantined.
- User's Last Action The response to the quarantined item by the admin.
- User's Last Action Status The success or failure of the response.

Export DLP quarantined files list

- Click 'Security Sub-systems' > 'Data Loss Prevention'
- Click the 'Quarantined Files' tab.
- Click the 'Export' button above the table then choose 'Export to CSV':




- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

11. Configure Endpoint Manager

Click 'Settings' in the left-hand menu.

- The settings area lets you configure email notifications, active directory, Google and Apple device certificates, and more.
- You can also manage subscriptions, renew/upgrade licenses and view support information.





The following sections provide more details on each area:


- Email Notifications, Templates and Custom Variables
 - Configure Email Templates
 - Configure Email Notifications
 - Create and Manage Custom Variables
 - Create and Manage Registry Groups
 - Create and Manage COM Groups
 - Create and Manage File Groups
 - View and Manage Pattern Variables
 - View and Manage Keyword Groups
- Endpoint Manager Portal Configuration
 - Import User Groups from LDAP
 - Configure Communication and Security Client Settings
 - Configure the EM Android Client
 - Configure Android General Settings
 - Configure Android Client Antivirus Settings
 - Add Google Cloud Messaging (GCM) Token
 - Add Apple Push Notification Certificate
 - Configure EM Windows Client
 - Configure Communication Client Settings
 - Configure Client Security Settings
 - Manage Endpoint Manager Extensions
 - Configure Endpoint Manager Reports
 - Device Removal Settings
 - Account Security Settings
 - Set-up Administrator's Time Zone and Language
 - Configure Audit Log Settings
- Integrate Apple DEP with Endpoint Manager
- View Version and Support Information



11.1.Email Notifications, Templates and Custom Variables

Click 'Settings' > 'System Templates'

The templates, variables and file groups in this section are used / referenced by various Endpoint Manager modules. For example, a custom variable which represents a user's name can be inserted into an email template. The notifications tab lets you choose the recipients of alerts, and the events upon which they should be sent.



The following sections explain how to:

- Configure Email Templates
- Configure Email Notifications
- Create and Manage Custom Variables
- Create and Manage Custom Variables
- Create and Manage COM Groups
- Create and Manage File Groups
- View and Manage Pattern Variables
- View and Manage Keyword Groups



11.1.1. Configure Email Templates

- Click 'Settings' > 'System Templates' > 'Email Templates'
- Email templates contain the content for Endpoint Manager's system emails. Examples include templates for account activation, device enrollment and password resets.
- Due to their importance, you cannot delete these templates or create new templates. You can, however, modify the contents of a template. The preset email templates are:
 - Activate account Sent only to new admins to activate their account. These mails are not sent to
 people with the 'User' role (your end-users/device owners). Users receive a different enrollment
 mail which you can disable during the csv user import process if required.
 - Password reset Sent to any user that requests a new password.
 - Device enrollment Sent to end-users. Contains instructions on how to add their device to Endpoint Manager.
 - **Email notification** Sent on the occurrence of certain events. You can configure the recipients of these mails, and the events that generate them, in the 'Email Notifications' tab.
 - Device enrollment via Active Directory Sent to users imported from Active Directory when you enroll their devices. You can enable or disable this mail in 'Settings' > 'Portal Set-Up' > 'Active Directory' > click the name of an LDAP domain > 'Enroll' > 'Edit'.

View and manage email templates

- Click 'Settings' > 'System Templates'.
- Click the 'Email Templates' tab

Email Templates	Email Notifications	Custom Variables	Registry Vari	ables	COM Variables	File Groups Variable
NAME		SUBJECT		INCLUDE	ED VARIABLES	
Activate account		Endpoint Manager	- Account		me% - Name of regist eLink % - Link for Activ	ered user vate and set password
Password reset		Endpoint Manager	r - Passwor	%linkRes %suppor	me% - Name of regist setPass% - Link for re: tEmail% - Support em tDate% - Current date	set password
Device enrollment		Endpoint Manager	- Device E	%linkEnr	oll% - Link of enrollme	ent the client
Email notification		Endpoint Manager	r - Email No	%eventT %device	atetime% - Event time itle% - Event title Url% - URL device deta otion% - Additional da	ail view
Device enrollment via A	ctive Directory	Endpoint Manager	- Device E	%linkEnr	oll% - Link to enrollme	ent page

Email Templates- Column Descriptions	
Column Heading	Description
Name	The label of email template. This cannot be changed. • Click the name of a email template to view and edit its content and variables.




	See View and Manage an Email Template for more details	
Subject	The email subject. You can modify this as required.	
Included Variables	Email variables are dynamic fields which reference data held elsewhere. For example, the %username% variable will actually show the real username of the email recipient.	
	The 'Included Variables' column tells you the name and purpose of each variable in a template.	
	You can add or remove variables if you edit the template.	
	 You can create your own variables in 'Settings' > 'System Templates' > 'Custom Variables' 	
	You can view other variables in the 'Registry variables', 'COM variables' and 'File Group variables' tabs.	

View and Manage an Email Template

- Click 'Settings' > 'System Templates'
- · Click the 'Email Templates' tab
- · Click the name of the template that you want to edit


This opens the full email text. The 'Activate Account' template is shown below:



Click the edit button

if you want to modify the subject line, body text or variables.





- Edit the subject line and/or email content as required
- You can remove variables by simply deleting the %variable% from the body text.
- Insert a variable Place your mouse cursor where you want the variable to appear. Click the 'User Variables' button to insert the variable.

Note: Each email template has a limited selection of user and device variables.

Click 'Save'. You changes will take effect immediately.

11.1.2. Configure Email Notifications

Click 'Settings' > 'System Templates' > 'Email Notifications'

- Endpoint Manager can send alert emails to admins and users when certain events happen.
- Example events include detection of a new threat, or when a mobile device is removed from management.
- The 'Email Notifications' tab lets you set alert recipients and specify which events are covered.
 - Note the 'Email Notification' template contains the actual content of the mail. Click 'Settings' > 'System Templates' > 'Email Templates' if you want to view and edit this content.

Configure email notifications

- Click 'Settings' > 'System Templates'.
- Click the 'Email Notifications' tab






The interface has two tabs:

- Send to Settings Configure alert recipients
- Alert Settings Select which events generate an alert

Send to Settings

· Click the 'Edit' button at top-right to modify the list of recipients




- EM Administrators Send alerts to every Endpoint Manager admin
- Send to Email List Type the email addresses of additional recipients. Press space after each address to enter another email address.
- Send to User List Select users that have been added to endpoint manager. You can view a list of current users in 'Users' > 'User List'.

Alert Settings

The alerts interface lets you select the events for which alerts are sent.






- **New Infection Detected** Sends an alert if untreated malware is found on a managed device. This is malware that was blocked, but has NOT been quarantined or deleted. This can happen, for example, if the user clicked 'Ignore' at the threat alert.
 - You can view all such malware in Endpoint Manager at 'Security Subsystems' > 'Antivirus' > 'Current Malware List'.
 - Click here if you want to view the 'Current Malware List' guide page. This page also includes a more detailed explanation of the conditions under which a file will appear in the list.
- iOS Device Removal Detected Sends an alert if an iOS device is removed from management.
- Mac OS Device Removal Detected Sends an alert if a MAC is removed from management.
- Security Vulnerability Notification Sends an alert if a common vulnerability and exposure (CVE) patch is available for devices.
- Click the 'Edit' button at top-right to enable/disable specific alerts.

11.1.3. Create and Manage Custom Variables

- Click 'Settings' > 'System Templates' > 'Custom Variables'
- A variable is a string of text which references a piece of data. For example, '%u.mail% is the variable for a
 user's email address.
- Variables can be added to email templates and profiles. They will dynamically populate the field with the piece of data requested.
- There are three types of variable 'User', 'Device' and 'Custom'. The first two types, 'user' and 'device', are preset and cannot be edited.
 - User variables Fetch data about a specific user. For example, the user's login name or email address
 - **Device variables** Fetch data about a specific device. For example, the IMEI number or phone number of a mobile device.
 - Custom variables Fetch data about an item of your choice. For example, you could create a
 custom variable called 'secure_mail_port' with a value of '2525'. You can then use this variable in
 the 'Email' section of an Android or iOS profile. If you decide to change the port number in future,
 you can easily update all devices by changing the variable value instead of editing multiple
 profiles.




• Illustration - Click 'Configuration Templates' > 'Profiles' > open an Android profile > Click 'Add Profile Section' > 'Email'. Click the 'Variables' button in any field to view available variables:



View, manage and create custom variables

- Click 'Settings' > 'System Templates'
- Click the 'Custom Variables' tab



Custom Variables - Column Descriptions	
Column Heading	Description
Key	Friendly name which identifies the variable.



	 You select a variable you want to use by choosing the key name. Click the key name to edit the key value.
Value	The value to be substituted for the key
Author	The admin who created the custom variable.
	 Click the admin name to view their details. See View User Details if you need help with this.
Last Modified By	The admin who most recently edited the variable.
	 Click the admin name to view their details. See View User Details if you need help with this.
Created	The date and time the custom variable was added.

Sorting, Search and Filter Options


- Click on any of the column headers to sort the items in ascending/descending order of entries in that column
- Click the funnel icon to search for custom variables based on filter parameters



To create a new custom variable

- Click 'Settings' > 'System Templates' > 'Custom Variables' tab
- Click 'Add Variable'






- Key Enter a name for variable as it should appear in the Variables drop-down
- Value Enter the value to be fetched for the key
- Click 'Save' to add the variable to EM.
- Repeat the process to add more variables.

To edit a Custom Variable

• Click on the name of the 'Custom Variable' to be edited.

The 'Update Custom Variable' screen will appear.



• Edit the 'Key' and 'Value' as required and click the 'Save' button.

To remove a Custom Variable




• Select the custom variable to be removed from the list and click the 'Delete' button at the top

11.1.4. Create and Manage Registry Groups

- Click 'Settings' > 'System Templates' > 'Registry Variables'
- The 'Registry Variables' tab contains references to pre-defined and custom registry groups.
 - A registry group is a collection of registry keys with similar attributes or scope.
 - For example, the 'Important Keys' group contains keys which are essential to the security and stability of the operating system. The 'Automatic Startup' group contains keys which load at Windows boot.
- Registry groups are useful when you want to apply an action to an entire class of keys. For example, you can exclude a registry group from containment when creating a profile.
- You can add new groups and edit existing groups as required.
- Groups in this interface are available for selection when configuring a Windows profile.

Open the 'Registry Groups' interface

- Click 'Settings' > 'System Templates'
- Click the 'Registry Variables' tab



Add a new Registry group


Enter the name of the group in the 'New Registry Group' field and click the '+' button.



The new group will be added to the list. The next step is to add registry keys to the group.

· Click the '+' at the left of the group name






Enter the path of the registry key/value in the New Registry Entry field and click 'Add'




The key will be added to the group.



- Repeat the process to add more keys and values to the group.
- Click the 'Edit' icon if you want to modify the value:






- Edit the entry and click 'OK' to save your changes
- Click the trash can icon to remove a key:



Click 'OK' in the confirmation dialog.


The new registry group is now available for selection when configuring a Windows Profile. For example, in 'Containment' > 'Settings' > 'Do not virtualize access to the specified registry keys/values' > 'Exclusions'.





Edit the name of a Registry Group

Click the 'Edit' icon beside the Registry Group




• Enter the new name for the group in the 'Rename Registry Group' dialog and click 'OK'

Remove a Registry Group

• Click the trash can icon beside the Registry Group





A confirmation dialog will appear.


Click OK in the confirmation dialog.

11.1.5. Create and Manage COM Groups

- Click 'Settings' > 'System Templates' > 'COM Variables'
- Each COM group is a handy collection of COM interfaces falling under a certain category.
- Endpoint Manager ships with a set of predefined COM Groups that are available for use in configuration profiles, for example to add a COM group to the 'Protected Objects' list in the HIPS settings of a Windows profile. If required, You administrators can add new COM Groups, edit and manage them.
- The 'COM Variables' tab in the 'System Templates' interface lets you view and manage pre-defined and custom COM groups.
- The groups added to this interface will be available for selection while configuring Windows profiles from the 'Profiles' interface.

Open the 'COM Groups' interface

- Click 'Settings' > 'System Templates'
- Click the 'COM Variables' tab




The list of pre-defined and user-defined COM groups will be displayed. The default groups are indicated by 'Default' at their right and cannot be edited or deleted.

Sorting, Search and Filter Options




- Click the 'COM Groups' column header will sort the items in ascending/descending order of the names of the groups.
- To filter or search for a specific COM group, click the search icon at the top right and enter the name of the group on part or full



Add a new COM group

• Enter the name of the new COM group and click the '+ ' button:



The new group will be added to the list. The next step is to add COM classes to the group.

Click the '+' at the left of the group name




• Enter the COM classes to be added to the group, in the 'New COM Component' field and click 'Add'




The COM class will be added to the group.






Repeat the process to add more COM classes to the group.

Once a COM group is added, it will be available for selection while configuring a Windows Profile, for example in the 'HIPS' > 'Protected Objects' > 'Groups List' interface.




Click the pencil icon beside the class name to edit a class in the group,





- Edit the entry and click 'OK' to save your changes
- Click the trash can icon beside the COM component name to remove the COM class added by mistake or an unwanted class




• Click 'OK' in the confirmation dialog.

Edit the name of a COM Group

Click the pencil icon beside the COM Group






• Enter the new name for the group in the Rename COM Group dialog and click 'OK'

Remove a COM Group

• Click the Trash can icon beside the COM Group



• Click 'OK' in the confirmation dialog.




11.1.6. Create and Manage File Groups

- Click 'Settings' > 'System Templates' > 'File Groups Variables'
- File groups are handy, predefined groupings of one or more file types. You can select a file group as the
 target of various functions and rules. For example, you scan specify that a file group is excluded from AV
 scans, or that everything in a file group is auto-contained when run.
- Endpoint Manager ships with a set of predefined file groups, and allows you to create your own.
- After creating a group, it becomes available for selection when configuring a Windows profile.

Open the 'File Groups' interface


- Click 'Settings' > 'System Templates'
- Click the 'File Groups Variables' tab



'Default' groups cannot be edited or deleted.

Sort, Search and Filter Options

- Click the 'File Groups' column header to sort the items in ascending/descending order of the names of the groups.
- To filter or search for a specific file group, click the search icon at the top right and enter the name of the group on part or full



Add a new File group

• Enter a name for the group and click the '+'.button. The group name should ideally identify the content or purpose of the group:





The new group will be added to the list. The next step is to add files to the group.

Click the '+' at the left of the group name



 Enter the full standard folder/file path of the file to be added to the group in the 'New File Group Path' field and click 'Add'

Tip: To include all the files in a folder, place the wildcard character in the place of file name in the folder path. For example: " C:\My Files* "


The file(s) will be added to the group.



Repeat the process to add more files to the group.


Once a File Group is added, it will be available for selection in applicable settings interfaces for defining the File Groups, example, for adding to 'Exclusions' list in 'Antivirus Settings' panel , in the 'Windows Profile' interface.






• Click the pencil icon beside the file name to edit the files in the group





- Edit the file path in the 'Rename Path' dialog and click 'OK'.
- Click the trash can icon beside the file name to remove the file added by mistake or an unwanted file from the group.




• Click OK in the confirmation dialog

Edit the name of a File Group

Click the 'Edit' icon beside the file group






Enter the new name for the group in the 'Rename File Group' dialog and click 'OK'

Remove a File Group

Click the trash can icon in the group row:



A confirmation dialog will appear.

Click 'OK' in the confirmation dialog.

11.1.7. View and Manage Pattern Variables


- Click 'Settings' > 'System Templates' > 'Pattern Variables'
- A 'pattern' is the format used by the type of sensitive data that you want to find. For example, DLP identifies social security numbers by searching for a name and a 9 digit number in a 3-2-4 format, like '123-45-6789'.



- For example, the social security number pattern is a name and a 9 digit number in a 3-2-4 format (like '123-45-6789').
- Patterns are used in DLP search rules which you add to a device profile. The rules detect data which
 matches the pattern.
 - See Data Loss Prevention Rules for more about creating and adding rules to profiles
 - See Data Loss Prevention Scans for more about running DLP scans and viewing the results
- You can also create custom patterns according to your requirements.

Open the DLP data patterns screen

- Click 'Settings' > 'System Templates'
- Click the 'Pattern Variables' tab
- The interface shows all available patterns including predefined and custom patterns:



- A keyword group is a list of specific items that EM will search for. For example, the 'Name' group contains a
 list of common first names. EM ships with a set of pre-defined keyword groups.
- You MUST add keywords to a keyword group or the pattern will not work. For example, you should add all names you want to search for to the 'Names' keyword group.
- You can configure keywords and groups at 'Settings' > 'System Templates' > 'Keyword Variables'
- See View and Manage Keyword Groups for help to manage keyword groups

The following table shows available patterns:


Pattern	Description
Name with 5 Digit Account Number	Consists of Keyword Group 'Names' and 5 digit bank account number
Name with 6 Digit Account Number	Consists of Keyword Group 'Names' and 6 digit bank account number
Name with 7 Digit Account Number	Consists of Keyword Group 'Names' and 7 digit bank account number
Name with 8 Digit Account Number	Consists of Keyword Group 'Names' and 8 digit bank account number
Name with 9 Digit Account Number	Consists of Keyword Group 'Names' and 9 digit bank account number
Name with 10 Digit Account Number	Consists of Keyword Group 'Names' and 10 digit bank account number



Name with SSN	Consists of Social Security Number and Keyword Group 'Names'
ABA Routing number	Consists of American Bankers Association (ABA) routing number. This is the nine digit bank code printed in negotiable instruments in the US.
Date of birth	Consists of Birth Date
Credit Card Number	Consists of Credit Card Number
IP Network	Consists of IPv4 and IPv6 IP Addresses
	Examples: 192.0.2.0/24 198.51.100.0 2001:0db8:85a3:0000:0000:8a2e:0370:7334 2001:db8:1234::/48
Network Address	Consists of URLs, and domain names Examples: http://domain.name https://domain.name www.domain.name domain.com local.net
IBAN Code	Bank account number in International Bank Account Number (IBAN) format.
MAC Address	Searches for mac addresses, the unique identifier assigned to network cards.

Create a new custom pattern

- Click 'Settings' > 'System Templates'
- · Click the 'Pattern Variables' tab
- Click 'Create Pattern'





Name - Enter a label for the pattern and click 'Create'

The pattern is saved and lets you add pattern types:




General - Click 'Edit' and update pattern label if required.

Pattern Elements – Lets you configure the pattern types.



Click 'Add Element'






Click a pattern type to select it

The details of each pattern type is explained above in the **table** except for the following:

- Keyword Enter a keyword as a parameter
- Keyword Groups Select either 'Names' or 'Network Terms' groups
- Custom Mask Specify what CCS should search for.

Keyword

Select 'Keyword' from the 'Add Element' drop-down




Predefined Keyword – Enter a keyword and click 'Add'

Keyword Groups

Select 'Keyword Groups' from the 'Add Element' drop-down






Select a group from the drop-down and click 'Add'

Custom Mask

Select 'Custom Mask' from the 'Add Element' drop-down



- Search Mask Specify the placeholders that should be added to the custom pattern type. See below:
 - A any symbol or letter
 - D digits
 - L- letters
 - S any ASCII symbols.
- Match All Specify if you want DLP rules to check information type fully or partially.
 - Enabled DLP rule is triggered only if all data defined are true.
 - Disabled DLP rule is triggered even if partial data defined are true.


Click 'Add'

You can add only two pattern elements to a pattern. You can select the pattern when creating DLP discovery rule. See **Create DLP Discovery Rules and add them to Profiles** for more details.

Rules

The 'rules' tab shows the DLP rules that use the pattern.






11.1.8. View and Manage Keyword Groups

Click 'Settings' > 'System Templates' > 'Keywords Variables'

- Keyword groups are used by DLP scans to identify sensitive data. They are a list of specific items which the scan will search for. For example, the 'Names' group contains a list of common first names and surnames.
- Keyword groups are used in combination with an information format to form a 'pattern'. An information format is the notation used by the type of data you want to find. For example, the information format of an SSN is a nine digit number in a 3-2-4 formation, like '123-45-6789'.
- The keyword group cannot be empty. It must contain all keywords that you want to search for. Patterns that have an empty keyword group will not locate any data.
- You add the search pattern to a DLP rule, then you add the rule to a DLP scan in your configuration profiles.
 - See View and Manage Patterns Variables to see the components of each pattern.
 - See Data Loss Prevention Rules for more on creating and adding rules to profiles
 - See Data Loss Prevention Scans for more on running DLP scans and viewing the results
- The 'Keywords Variables' area lists all available keyword groups and lets you add keywords to the groups.

View and manage keyword groups


- Click 'Settings' > 'System Templates'
- Click the 'Keyword Variables' tab





Add keywords to a group

• Click '+' at the left of a group name



There are two ways you can add keywords:

- 1 Type them in the field provided. Click 'Add' after each keyword.
- 2 Import them from .csv file. Click the import icon on the right then browse to your .csv file:

Note:

- The scan searches for an exact match on the keywords you add.
- In the case of 'Name' keywords, we advise you add only surnames to the list at first. This will detect the most variants of the subject's name.
- For example, the keyword 'Bowman' will catch the following variants in an SSN pattern search:

Robert T Bowman 123-45-6789 Rob Bowman 123-45-6789 Robert Bowman 123-45-6789 R. Bowman 123-45-6789 Bowman Robert 123-45-6789 etc.

11.2. Endpoint Manager Portal Configuration

Click 'Settings' > 'Portal Set-up'


The portal set-up area lets you configure core settings which are important to the operation of Endpoint Manager.

From here you can:

- Integrate Active Directory so you can import users and devices from your domain
- Add Apple and Google certificates so Endpoint Manager can communicate with iOS and Android devices



Configure client settings, reports, two-factor logins, admin time-zones, and more.



Use the following links to learn more about each setting:

- Import User Groups from LDAP
- Configure Communication and Security Client Settings
 - Configure the EM Android Client
 - Configure Android General Settings
 - Configure Android Client Antivirus Settings
 - Add Google Cloud Messaging (GCM) Token
 - Add Apple Push Notification Certificate
 - Configure EM Windows Client
 - Configure Communication Client Settings
 - Configure Client Security Settings
- Manage Endpoint Manager Extensions
- Configure Endpoint Manager Reports
- Device Removal Settings
- Configure Two-Factor Authentication Settings
- Set-up Administrators Time Zone and Language
- Configure Audit Log Settings

11.2.1. Import User Groups from LDAP

There are two ways to add users to Endpoint Manager:

- 1. Manually add users:
 - Enroll one user at a time
 - Import multiple users from a .csv file
- 2. Import user groups from Active Directory (AD) servers

Endpoint Manager can be configured to access your AD server through the Lightweight Directory Access Protocol (LDAP). You can add multiple LDAP accounts.




Process in brief:

- Add an LDAP server by specifying its IP address, domain and the login credentials of the AD server:
 - Click 'Settings' > 'Portal Set-Up' > select the 'Active Directory' tab > Click 'Add'
- Once added, users and user groups in the AD directory will be visible in the 'Active Directory' interface:
 - Click 'Settings' > 'Portal Set-Up' > select the 'Active Directory' tab > Click on an AD domain name >
 Click the 'User Groups' tab
- Select the users and groups you wish to import
- Assign roles to users/user groups as required
- Synchronize LDAP with Endpoint Manager
- The selected users/user groups will be imported and placed into respective groups in EM
- The 'User List' and 'User Groups' interfaces let you view/manage users and enroll user devices. See Users
 and User Groups for more details.

Open the Active Directory interface

- Click 'Settings' > 'Portal Set-Up'
- · Click the 'Active Directory' tab



LDAP Accounts - Column Description	
Column Heading	Description
Account Domain	The Active Directory domain name. Click the domain name to: View and import user groups Configure device enrollment for imported users Configure the connection between the AD server and Endpoint Manager See Manage LDAP Accounts for more details.
Customer Name	The organization associated with the AD domain
Enable LDAP	Whether or not the LDAP account is active
Server Host	The LDAP hostname or IP address of the AD server
Author	The admin who added the LDAP account • Click the admin name to view their details. See View User Details if you need help with this.
Created	The date and time at which the LDAP account was added




Note: Endpoint Manager communicates with Comodo servers and managed devices in order to update data, deploy profiles, synchronize LDAP server via devices and so on. You need to configure your firewall accordingly to allow these connections. The details of IPs, hostnames and ports are provided in **Appendix 1**.

To add an LDAP account

Click 'Add' at the top

The 'Login to Active Directory' wizard opens:

Step 1 - Enter LDAP account details




'Login to Active Directory - Settings' Form - Table of Parameters	
Form Element	Description
Туре	



LDAP Server Host	The IP address or hostname of the Active Directory (AD) server
LDAP Account Domain	The Active Directory domain name.
Company	Choose the company to which the AD server belongs. ITarian MSP customers can add AD servers for multiple companies. Type the first few characters of the company name and select from options. ITarian Enterprise and EM stand-alone customers can only select the default company.
LDAP Account Login	The admin username and password required to access the AD server.
LDAP Account Password	

Click 'Next' after completing the settings form.

Step 2 - Configure Synchronization Settings



Sync Settings

- Enable Sync at Business Days Endpoint Manager will automatically sync with the LDAP server once per day Monday through Friday to check for and import new users
- Enable Sync At Weekend Endpoint Manager will automatically sync with the LDAP server once a day on Saturdays and Sundays to check for and import new users on weekends.

Note - you can manually sync at any time by clicking the 'Sync with LDAP' button.

Connection Type

ITarian Endpoint Manager - Administrator Guide




The connections setting determine how Endpoint Manager connects to the LDAP server. You can connect directly from the EM server or via the enrolled devices.

If you choose the second option, you should specify the names of enrolled Windows devices which are in the same network as the AD server.

Click 'Next'


Step 3 - Finish



- Do not send any enrollment notifications No notification mails are sent to imported users
- Send enrollment notifications to all synchronized new users Device enrollment emails are sent to imported users. These mails include instructions which tell the user how to add their device to Endpoint Manager.
- Specify email address to send enrollment notifications for all synchronized new users Add the
 recipients who should receive a notification mail when new users are added. Usually sent to an
 administrator, the mail contains instructions on how to enroll devices for the new users. You can add
 multiple email addresses here.
- Click 'Finish'

Endpoint Manager will connect to the LDAP server per the configuration. A summary of account settings is shown if the connection is successful:





Click 'Edit' if you want to change any details, edit the details and click 'Save' to save your settings.

The synchronization task will run as scheduled in step - 2, and the user groups will be added.


- Click 'Sync with LDAP' to instantly sync the user groups between the AD server and EM
- Repeat the process to add more AD servers to import user groups from.

Manage LDAP Accounts

The Active Directory interface lets you view and edit the details of integrated AD servers, synchronize users between AD and EM, and more.

- Click 'Settings' > 'Portal Set-up' > 'Active Directory'
- Click the AD domain name from the list of LDAP accounts to view or edit its details






The Active Directory details will be displayed under four tabs:

- Settings
- User Groups
- Enroll
- Connection Type

Settings tab

The 'Settings' tab displays AD configuration details:






Click 'Edit' to update any LDAP details and click the 'Save' button

User Groups tab

The 'User Groups' tab shows groups that were identified on the AD server. This includes users/groups created in the root folder and all sub-folders/custom folders on the AD server. This interface allows you to:


- Selectively enable/disable AD synchronization for groups. Synchronization allows EM to update its user list
 whenever users are added/removed from the AD sever.
- Select the roles to be applied to users in each AD group.
- Manually synchronize groups before importing to EM





Enable/disable synchronization


• Select user group(s) from the list and click 'Synchronization' at the top:



Select whether synchronization should be enabled or not from the drop-down. If enabled, EM will
periodically synchronize with the group to import new users and remove deleted users.


Assign roles to imported users

- Select the user(s)/user group(s).
- Select 'Set Default Role' to assign the default EM user role to the users. See **Set a role as the default role** if you need help with this.



• Select 'Change Role' if you want to assign a different role to imported users.





Type the first few characters of the name of the role to be assigned and select the role from the
options.


The selected role will be displayed in the 'Role' column for the users/user groups.

Repeat the process to apply different roles to different users/user groups.

See 'Manage Roles Assigned to a User' for more details on roles.


To import users from selected user group

Click 'Sync with LDAP'




 The LDAP user/user groups are synchronized with EM and new users are imported. The 'User List'/'User Groups' interfaces will update appropriately. See 'Users and User Groups' if you need more help with users and groups.






Enroll tab

The 'Enroll' tab displays the current setting of enrollment notification sent to imported users.



Click 'Edit' to change the enrollment notification type






- Do not send any enrollment notifications No enrollment mails will be sent to users imported via LDAP
- Send enrollment notifications to all synchronized new users Device enrollment emails will be sent to new users enrolled via LDAP.
- Specify email address to send enrollment notifications for all synchronized new users Specify
 email recipients who should receive a notification mail when new users have been added. Usually sent
 to an administrator, the mail will contain instructions on how to enroll devices for the new users. You
 can add multiple email addresses here.
- Update the notification type from the options and click 'Save'


Connection Type Tab

The 'Connection Type' tab displays how the AD server currently connects to Endpoint Manager.



Click the 'Edit' button to change the connection type.






If the first option is selected, EM will connect to the configured LDAP server directly. The second option enables the EM server to connect to the LDAP server via enrolled devices. Multiple devices can be configured for the second option.

Click 'Save' after selecting the option.

You can add multiple LDAP servers for the account from the Active Directory interface. Click 'Add' and follow the same procedure explained above.

Active Directory Interface - Sorting, Search and Filter Options

- · Click on the column headers sorts items in alphabetical, ascending/descending order
- Click the funnel button \(\cdot \) to open filter options:






- You can search for a specific LDAP account based by domain name, host, company and/or author. Enter
 your search criteria in the respective text boxes and click 'Apply'.
- You can also filter by the date the account was created. Use the calendar buttons at the bottom to select start and end dates then click 'Apply'.

You can use any combination of filters to search for specific LDAP accounts.

11.2.2. Configure Communication and Security Client Settings

- Click 'Settings' > 'Portal Set-up' > 'Client Settings'
- This section allows you to configure Android, Windows communication clients and install Apple Push Notification (APN) certificates on your Endpoint Manger.
- Configure default Windows communication and security clients that will be deployed on endpoints



Use the following links to learn more about each setting:

- Configure the EM Android Client
 - Configure General Settings
 - Configure Android Client Antivirus Settings
 - Add Google Cloud Messaging (GCM) Token
- Add Apple Push Notification Certificate
- Configure EM Windows Clients
 - Configure Communication Client Settings
 - Configure Comodo Client Security (CCS) Settings

11.2.2.1. Configure the EM Android Client


- Click 'Settings' > 'Portal Set-up' > 'Client Settings' > Open the 'Android' tab.
- You need to install the communication client on each Android device that you want to manage. The client allows Endpoint Manager to pass updates and commands to the device, and to run antivirus scans.
- You also need to add a Google Cloud Messaging (GCM) token for the EM server to communicate with the clients.



This area also lets you configure client general settings and antivirus settings.

Open the Android Client Config Screen

- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click the 'Android' tab



The interface has three tabs:

- Client Configuration General settings like client and AV database updates, polling intervals, client uninstall protection and more. See Configure Android Client General Settings.
- Antivirus Specify how viruses identified by client should be dealt with. If 'Automatic' is chosen you can
 also specify whether the AV should remove the threat or ignore it. See Configure Android Client Antivirus
 Settings.
- Android Cloud Messaging Create a Google Cloud Messaging (GCM) token to facilitate communications between EM and Android devices. See Add Google Cloud Messaging (GCM) Token.


11.2.2.1.1. Configure Android Client General Settings

- Click 'Settings' > 'Portal Set-up' > 'Client Settings'
- Open the 'Android' tab then click 'Client Configuration'
- This area lets you configure various settings for the Endpoint Manager Android client. Settings include update frequency, device alarms, uninstall protection and more.

Configure the Android client

- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click 'Android' > 'Client Configuration'





The current settings for various parameters of Client Configuration is displayed.



Android Client Configuration - Table of parameters	
Parameter	Description
Time-out for collecting basic device information	The maximum time allowed for EM to collect essential information such as battery level, CPU usage, GPS location and WiFI SSID.
Time-out for collecting full device information	The maximum time allowed for EM to collect all device information. This includes memory status, device name, IMEI number, roaming status, bluetooth MAC address and WiFi MAC address.



Interval between antivirus database update	The frequency at which the antivirus database should be updated on the device.
Devices should check for new EM events every	The frequency at which the device should contact Endpoint Manager to receive new push notifications.
EM should check device restrictions are active every	The frequency at which the client should confirm that its device restrictions (as per the applied profile) are in place.
Siren Playing Duration	Length of time that the device alarm will play for when remotely activated by an admin.
Enable client uninstall protection	Whether or not a password is required in order to remove the client from a device. • Select the 'Enable client uninstall protection' check box and specify a password in the text box. The EM client can be uninstalled from any enrolled device only after entering the password.
Allow devices to access application repositories	If enabled, an 'Applications' bar will be visible on Android devices which will open a list of Android apps in the 'Application Store'.

Click 'Save' to apply your changes.

11.2.2.1.2. Configure Android Client Antivirus Settings


The Android antivirus provides real-time protection against malware and malicious apps. You can also launch ondemand scans on Android devices from Endpoint Manager.

The antivirus settings area lets you configure whether threats are automatically removed or handled manually.

- **Automatic Response** You have the choice to auto-uninstall or ignore the threat. If you choose 'Ignore' then the item will appear in the current malware list ('Security Sub-Systems' > 'Antivirus' > 'Current Malware List').
- Manual Control All threats are ignored on the device. You can manage these ignored threats at 'Security Sub-Systems' > 'Antivirus' > 'Current Malware List'.

Configure antivirus settings

- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click 'Android' > 'Antivirus'




The current antivirus settings are displayed.



Click the edit button

Edit

at the top to modify settings.



Android Client Antivirus Settings - Table of Parameters	
Description	
Choose the type of action taken if malware is discovered on the device. The options are: 1) Manual control - Discovered malware is ignored and its details are sent to Endpoint Manager (current malware list and Android threat history). No alerts are shown on the device. • You must enable 'Terminate Malware' in the Android profile if you also want stop the malware running. • Click 'Configuration Templates' > 'Profiles' > open your Android profile > Open or add the 'Antivirus' section. • Click here to view help on this in the online guide 2) Automatic response - Two options are available. • Uninstall: • Knox devices - Applications with viruses or infected files on the devices and from the SD card are deleted without any alert on the device. • Non-Knox devices - An alert is shown to the user on the device for removal of malware. Infected files on the SD card are deleted without any alert. • Ignore: • No action is taken on malware files and details are sent to portal (current)	

• Click 'Save' for your settings to take effect.


11.2.2.1.3. Add Google Cloud Messaging (GCM) Token

- Endpoint Manager requires a Google Cloud Messaging (GCM) token in order to communicate with enrolled Android devices.
- EM ships with a default token. However, you can also generate a unique Android GCM token for your EM portal.
- To get a token, you must first create a project in the Google Developers console.
- Please follow the steps given below to create a project and upload a token.

Step 1 - Create a New Project




Login to the Google Firebase API Console at https://console.firebase.google.com, using your Google account



Click 'Add Project'







- Type a name for the new project in the 'Project name' field
- Click the pencil icon beside the 'Locations' field and select your country and Google Cloud Firestore server location nearest to you.
- Leave 'Use the default settings for sharing Google Analytics for Firebase data' selected
- Read Agree to the terms and conditions by selecting respective checkboxes
- Click 'Create Project'.

Your project is created.






Click 'Continue' to go to the project dashboard



Step 2 - Obtain GCM Token and Project number


- Click the hamburger button
- Click the gear icon beside 'Project Overview' and choose 'Project settings' from the options.





The 'Settings' screen for the project appears.

Click the 'Cloud Messaging' tab.




Note down the 'Server key' and 'Sender ID' in a safe place


Step 3 - Enter GCM Token and Project number

- Login to Endpoint Manager
- Click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Android' > 'Android Cloud Messaging' tab






Click the edit button at the top right of the 'Cloud Messaging Token' column, to view the GCM token and project number fields



- Paste the 'Server key' into 'Android (GCM) Token' field.
- Paste the 'Sender ID' into 'Android (GCM) Project Number' field.





Click 'Save'.

Your settings will be updated and the token/project number will be displayed in the same interface.


Your EM Portal will be now be able to communicate with Android devices using the unique token generated for your EM portal.

11.2.2.2. Add Apple Push Notification Certificate

- You need to install an Apple Push Notification (APN) certificate on your Endpoint Manager portal in order to communicate with iOS and Mac devices.
- You can enroll for an APN certificate using your Apple account. If you do not have an Apple account then please create one at https://appleid.apple.com. A free account is enough.
- The certificate is valid for one year. EM will remind you when your certificate is nearing expiry. It is free to renew the certificate each year
- Please follow the steps below to obtain and implement an APN certificate:

Step 1- Generate your PLIST


- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click the 'macOS / iOS' tab.






Click the 'Create APNs Certificate' button to open the APNs application form.

The fields on this form are for generating a Certificate Signing Request (CSR):



- Complete all fields marked with an asterisk and click 'Create'.
- This will send a request to Comodo to sign the CSR and generate an Apple PLIST.
- You will need to submit this to Apple in order to obtain your APN certificate.
- Usually your request will be fulfilled within seconds and you will be taken to a page which allows you to download the PLIST:





 Download your Apple PLIST from the link in step 1 on this screen. This will be a file with a name similar to 'COMODO_Apple_CSR.csr'. Please save this to your local drive.


Step 2 -Obtain Your Certificate From Apple

- Login to the 'Apple Push Certificates Portal' with your Apple ID at https://identity.apple.com/pushcert/.
- Once logged in, click 'Create a Certificate'.




You will need to agree to Apple's EULA to proceed.






 On the next page, click 'Choose File', navigate to the location where you stored 'COMODO_Apple_CSR.csr' and click 'Upload'.



Apple servers will process your request and generate your push certificate. You can download your certificate from the confirmation screen:





 Click the 'Download' button and save the certificate to a secure location. It is a .pem file with a name similar to 'MDM_COMODO GROUP LTD._Certificate.pem'

Step 3 - Upload your certificate to Endpoint Manager


- Return to EM, click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'macOS / iOS'
- Click the 'Browse' button, locate your certificate file and select it.



Click 'Save' to upload your certificate.

The APNs Certificate details interface opens:





Endpoint Manager can now communicate with iOS and Mac OS devices. You can enroll iOS devices and Mac OS devices for management.

- The certificate is valid for 365 days. EM will remind you when your certificate is due to expire.
- We advise you renew your certificate at least 1 week before expiry. If it is allowed to expire, you will need to re-enroll all your iOS and Mac devices.
 - Click 'Renew' in the APNs certificate details interface to renew the cert:




• Click 'Delete' only if you wish to remove the certificate so you can generate a new APNs certificate.



11.2.2.3. Configure Windows Clients

- Click 'Settings' > 'Portal Set-up' > 'Client Settings' then open the 'Windows' tab
- This area lets you configure settings such as the interval between device updates, the default client version and more.



Click the following links for help with each client's settings:

- Configure Communication Client Settings
- Configure Client Security Settings

11.2.2.3.1. Configure Communication Client Settings


Click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Windows' tab > 'Communication Client'

- The communication client is an agent installed on your managed devices. It receives commands and tasks from Endpoint Manager and implements them on those devices. The client also informs Endpoint Manager of the endpoint's status.
- The settings area lets you:
 - · Configure update intervals
 - Set the 'Default client version' which is installed on your endpoints. This is set to fetch and install the latest version unless you specify otherwise.
 - Specify whether admins can change the version of the client installed on an endpoint.
 - Choose whether to use an endpoint as the source from which other endpoints collect their updates.
 This can save time and bandwidth compared to every endpoint downloading direct from the server.

Configure the Windows communication client

- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click the 'Windows' tab > 'Communication Client'






The default values of the settings are displayed.

Click the edit button
 Edit on the top right to modify these settings





- **Device dynamical information update** How often the client should provide Endpoint Manager with device status updates. This includes, for example, available memory, name of the device, OS summary, CCS configuration, and network information.
 - Use the slider to set the update interval. (**Default = 15 minutes**)
- Requesting device commands The frequency at which the client should query Endpoint Manager for new tasks and updates.
 - Use the slider to set the update interval. (**Default = 15 minutes**)
- Sending device online status confirmations The frequency at which the client should send a message confirming the device is online and connected. Endpoint Manager changes the device status to 'Offline' if it does not receive a confirmation in the set time period.
 - Use the slider to set the update interval. (**Default = 15 minutes**)
- **Default Client Version** Determines which agent version should be installed on endpoints.
 - Choose the default agent version from the drop down. (Default = 'Latest').
- Enable change of version while installing Whether admins can install a version of the client that is different to the 'Default client version'. (Default = Disabled)

If enabled, admins can choose the version of the client they want to install in the following interfaces:

- Enroll devices 'Devices' > 'Device List' > 'Enroll Device'
- Bulk installation 'Devices' > 'Bulk Installation Package'
- Enable change of version while updating Whether admins can update a client to a version that is
 different to the 'Default client version'. (Default = Disabled)



If enabled, admins can choose the version of the client they want to update to in the following interfaces:

- **Update additional packages** 'Devices' > 'Device List' > 'Install or Manage Packages' > 'Update Additional Packages'
- Updates section of Windows profile 'Configuration Templates' > 'Profiles' > 'Windows Profile' > 'Updates' profile section

Note - Make sure to upgrade to a higher version. Installing a lower version than the existing agent is not supported.

• Enable Communication Client to distribute update packages among the clients in the same network to reduce network inbound traffic - Download updates to a managed endpoint, then use that endpoint as the source from which other endpoints collect their updates.

This saves internet bandwidth usage and accelerates updates in large networks.

If enabled, your endpoint clients will follow this process at update time:

- The endpoint first checks other endpoints to see if the update is installed on them
- · If available, the client fetches the update from the local endpoint
- If not available, the client downloads the update from the default download servers
- This endpoint then becomes the source from which other endpoints collect their updates.

You can choose the type of updates that use this mechanism:

- Communication Client updates (Version 6.29 or higher)
- Comodo Client Security updates (Version 11.4 or higher)
- Antivirus Database updates (Version 11.4 or higher)

■ Enable change of version while updating
Enable Communication Client to distribute update packages among the clients in the same network to reduce network inbound traffic CC v.6.29 and higher SOURCES.ANGULAR.MODULES.PORTAL_SETUP.MODULES.CLIENT_SETTINGS.MODULES.WINDOWS.MODULES.COMMUNICA,ADDITIO
Communication Client packages
Comodo Client - Security packages CCS v.11.4 and higher
Comodo Client - Security Antivirus Database packages CCS v.11.4 and higher
Settings
☐ Enable Network traffic limitation This setting enables you to define maximum amount of network traffic to be used for distribution of packages
Less than or equal to, %
Enable device count limitation This setting enables you to define maximum number of devices to be used for distribution of packages
Less than or equal to
Use download servers directly in case of any communication issue This option enables you to use download servers that is listed in Download Servers Tab in profiles under Updates section in case of any communication issue with ditribution mechanism. Please note that if this is not selected, in any communication issue, the clients will not update selected packages above until communication is restored



- Enable Network traffic limitation The maximum % of network bandwidth that can be used to share updates. (*Default* = 30%)
- **Enable device count limitation** The maximum number of devices with which the client is allowed to share updates. Default = 10.
- Use download servers directly in case of any communication issue If the endpoint cannot contact other endpoints it will collect the update from the main server.
- Click 'Save' to apply your changes.

The following table shows how clients will collect updates in different scenarios:

	Enable Communication Client to distribute	Select specific devices to be proxy	Use download servers directly in case	Will download from:
Scenario 1	✓	×	×	Any local device which already has the update
Scenario 2	✓	✓	×	Only from selected devices
Scenario 3	✓	*	✓	Any device in the local network Download servers
Scenario 4	✓	✓	✓	Selected devices Download servers

Additional Notes:

- The settings described in this section are 'global' settings which apply to all endpoint clients. However, you can also configure client update settings by adding an 'Updates' section to profile.
- There is one overlapping item between these two 'Enable the communication client to distribute packages to other clients in the network'.
- Endpoint Manager prioritizes this setting as follows:
 - If you do not add an update section to the profile, then the global settings apply
 - If you do add an update section, then Endpoint Manager will ignore the '...distribute...' settings in global settings

11.2.2.3.2. Configure Client Security Settings

Click 'Settings' > 'Portal Set-Up' > 'Client Settings' > 'Windows' tab > 'Client Security'

• Comodo Client Security (CCS) provides endpoint protection such as antivirus, threat containment, firewall and more.

The client security settings area lets you:


- Set the default client version which should be installed on your endpoints. This is set to fetch and install the latest version, unless you specify otherwise.
- Specify whether admins can change the installed version of the client from a command elsewhere in Endpoint Manager.




- In other words, can admins choose to install a different version of the client in a 'Bulk Installation Package', for example?
- If you leave the 'Enable change...' options deselected then admins will not have the option to install a different client version.

Configure client security

- Click 'Settings' > 'Portal Set-Up' > 'Client Settings'
- Click the 'Windows' tab > 'Client Security'



Click the edit button
 Edit to modify the default settings:



Parameter	Description			
Default Client Version	Determines which security client should be installed or updated on endpoints. You can choose the default security client version from the drop down.			
	The system default is to install the latest version.			
Enable change of version while installing	Can admins install a version of the client that is different to the 'Default client version'?			
	If enabled, admins can choose the version of the client they want to install in the following interfaces:			
	Enroll devices - 'Devices' > 'Device List' > 'Enroll Device'			
	Bulk installation - 'Devices' > 'Bulk Installation Package'			
	 Install additional packages - 'Devices' > 'Device List' > 'Install or Manage Packages' > 'Update Additional Packages' 			



	Default = Disabled			
Enable change of version while updating	Can admins update to a client version that is different to the 'Default client version'?			
	If enabled, admins can choose the version of the client they want to update to in the following interfaces:			
	 Update additional packages - 'Devices' > 'Device List' > 'Install or Manage Packages' > 'Update Additional Packages' 			
	 Updates section of Windows profile - 'Configuration Templates' > 'Profiles' > 'Windows Profile' > 'Updates' profile section 			
	Default = Disabled			
	Note - Make sure to upgrade to a higher version. Deployment of a lower version than the existing security agent is not supported.			

Click 'Save' to apply your changes.

11.2.3. Manage Endpoint Manager Extensions

- Click 'Settings' > 'Portal Set-up' > 'Extensions Management'
- Endpoint Manager Extensions are additional software modules which administrators can add to EM to
 expand its functionality. Once added, each extension can be controlled and managed from the EM
 interface.
- The 'Extensions Management' interface lets you enable or disable modules.

The extension currently available is:

Comodo Client Security - Comodo Client Security is the remotely managed Client Security software
installed on managed Windows devices. It offers complete protection against internal and external threats
by combining a powerful antivirus, an enterprise class packet filtering firewall, an advanced host intrusion
prevention system (HIPS) and Containment feature that runs unknown and unrecognized applications in an
isolated environment at the endpoints. CCS can be installed on the endpoints from the 'Devices' interface.
 See Remotely Install and Update Packages on Windows Devices for more details.

Once installed, CCS can be configured for optimal security by applying configuration profiles. See **Profiles for Windows Devices** for more details.


- Remote Control by ITarian 'Remote Control by ITarian' lets you to take control of managed Windows and Mac OS endpoints through remote desktop connection. This allows you to solve issues, install third party software, run system maintenance and more. There are two ways to remote control of a device:
 - Remote Control by ITarian (recommended) Install the client viewer software on your Windows
 or Mac OS admin computer to take control of any managed Windows endpoint.

You can take remote control of a Windows or Mac OS device from the 'Device Management' interface. For more details, see **Remote Management of Windows and Mac OS Devices**.

To enable or disable EM extensions

- Click 'Settings' > 'Portal Set-Up'
- Click the 'Extensions Management' tab





- Use the toggle switch in a tile to enable or disable an extension. Only extensions which are enabled will be available in the 'Device Management' interface.
- See Remotely Install and Update Packages on Windows Devices and Remote Management of Windows and Mac OS Devices for more details.

11.2.4. Configure Endpoint Manager Reports

Endpoint Manager undergoes rigorous Quality Assurance testing before release to ensure that the software is as stable and reliable as possible. However, in rare situations, EM may run into an exception which needs to be addressed. If the report setting is enabled, an exception report will automatically be sent to ITarian if EM encounters a problem.


Exception reports are a valuable and constructive means of feedback that help ITarian to debug our products and improve the service we provide to our customers.

These reports contain only the line of code that failed with additional information about the circumstances of the exception. They do not contain any private information about your company or your users.

The 'Reports' interface allows you to enable or disable automated sending of exception reports. Automatic report submission is disabled by default.


To configure exception reporting

- Click 'Settings' > 'Portal Set-Up'
- Click the 'Reports' tab



To edit the settings click the edit button





- Allow sending of exception reports Send anonymous reports to the Endpoint Manager team if the application encounters errors
- Click 'Save' for your settings to take effect.

11.2.5. Device Removal Settings

Click 'Settings' > 'Portal Set-up' > 'Device Removal Settings' tab


Endpoint Manager can detect and automatically remove inactive and duplicate devices.

- Old devices are marked with a icon in 'Devices' > 'Device List' > 'Device Management'.
- Duplicate devices are marked with a icon in 'Devices' > 'Device List' > 'Device Management'.

You can choose whether to auto-remove old/duplicate devices, and how long EM should wait before removing them.


Device removal settings

- Click 'Settings' > 'Portal Set-up'
- Select the 'Device Removal Settings' tab:



Click the 'Edit' button at top-right





Mark devices as 'Old' - Use the slider to choose how many consecutive days of inactivity must pass before EM marks a device as 'Old'. A device is considered 'inactive' if it isn't connected to Endpoint Manager.

- Remove after Choose how many days the device should stay marked as 'Old' before EM removes it
- If a device connects to EM within this period then it loses the 'old' status and is not removed.
- The 'Remove after' counter starts after the 'Mark devices as old' period ends. So if you leave both at '90 days', then the device will be removed after 180 days.

Mark devices as 'Duplicate' – A duplicate device is one that has the same name and / or MAC address as one or more other devices.

- Mark by Device Name EM detects duplicates by their label.
- Mark by Mac Address EM detects duplicates by their unique MAC address.
- If you select both, then EM marks duplicates *only* if both conditions are true.

Primary Device - Endpoint Manager designates *the most recently added device* as the 'Primary' device in a set of duplicates. The primary device is kept/not deleted if you enable the 'remove' option. All other duplicates are removed.

- Remove duplicate devices Use the slider at the bottom to choose how many days must pass before EM removes the devices. The primary device is retained.
- Uninstall Comodo Client Security The CCS app is also uninstalled when the device is removed from EM.




- Uninstall Communication Client The CC app is also uninstalled when the device is removed from EM.
- Remove online duplicate devices Forcibly remove a duplicate device even it is online and connected to EM
- Remove after Specify how many days EM should keep duplicates before removing them. The counter starts 1 day after a device is identified as a duplicate.

You have the option to simply rename a duplicate to remove the 'Duplicate' flag and prevent deletion. Click 'Save' to apply your changes.

11.2.6. Account Security Settings

Click 'Settings' > 'Portal Set-up' then the 'Account Security' tab

- This interface lets you configure security settings for EM admins that were created in Endpoint Manager itself ('Users' > 'User List' > 'Create User').
- You can configure to compel users to change their password periodically and use two-factor authentication.



Click the following links for more information about each setting:

- Password Expiry
- Two-factor Authentication


Configure Password Expiry Setting

Click 'Settings' > 'Portal Set-up' > 'Account Security' tab then the 'Edit' button at top-right

- This area lets you enable password expiration policy for admins that were created in Endpoint Manager itself ('Users' > 'User List' > 'Create User').
 - This area does not implement password expiration policy for ITarian logins. If you created your admins
 in the ITarian portal, then please enable password expiration policy in ITarian instead ('Click user icon
 at top-right > 'Settings' > 'Password and Account Policies').
 - You can create roles which allow users to login to Endpoint Manager if required. You can view and edit the privileges in each role at 'Users' > 'Role Management'. Click here if you want help with roles.



 The password expiration policy applies to EM and Remote Control tool. See Remote Management of Windows and Mac OS Devices for details using RC tool.



- Force Password Expiry Select this to enable password expiration policy
- Password Expiry Period Select the number of days after which the user is compelled to change his login EM login password. The maximum expiry period is 90 days for Comodo partners and up to 3 years for nonpartners.


Click 'Save' to apply your changes. Users will receive alerts during every login to EM and Remote Tool to change password from seven days before the expiry date.

Configure Two-factor Authentication Setting

Click 'Settings' > 'Portal Set-up' > 'Account Security' tab then the 'Edit' button at top-right

- Two-factor authentication adds additional security by requiring admins to present two forms of authentication before they can login to endpoint manager. They will need to enter their regular UN/PW + a unique code generated on their mobile device.
- This area lets you enable two-factor authentication (2FA) for admins that were created in Endpoint Manager itself ('Users' > 'User List' > 'Create User').
 - This area does not implement 2FA for ITarian logins. If you created your admins in the ITarian portal, then please enable 2FA in ITarian instead ('Management' > 'Account' > 'Account Security Details').
 - You can create roles which allow users to login to Endpoint Manager if required. You can view and edit the privileges in each role at 'Users' > 'Role Management'. Click here if you want help with roles.





- Force user to use 2FA If enabled, admins will need to set-up 2FA on their next login to the EM console. Setup involves installing the Google Authenticator app on their device. This app generates the codes that form the 2nd layer of authentication.
- Click 'Save' to apply your changes


The following explains the admin user-experience to configure 2FA at first login:

Admin enters his UN/PW in the EM login screen and clicks 'Login':




The two factor authentication activation screen is shown:





- Step 1 Download the 'Google Authenticator' app and install it on your iOS or Android device
 - Open the 'Authenticator' app and tap the '+' icon
- Step 2 Scan the QR code with the device camera. This will cause the Google app to generate the six digit code you need to complete pairing.
 - Alternatively, enter the key shown below the QR code in the Google Authenticator app.
- **Step 3** After completing steps 1 and 2, a six digit authentication code is generated in the Google app. This code changes frequently and is unique to your account.
 - · Enter the verification code in the field provided
- · Click 'Enable'
- A success message is shown along with 10 backup codes





- You can use the backup codes to complete two-factor authentication if you do have the authentication device with you. Please make a copy of the codes. Each code can only be used once.
- Click 'Done'. You will be logged in to your account.

Two-factor authentication is now configured.

 During next login to EM console, the two-factor authentication screen is shown after entering your username and password






- Code Open the Google Authenticator app on your paired device and enter the displayed code. Please
 note the code changes frequently.
- Click 'Login'

Use Backup Codes

Endpoint Manager two-factor authentication allows you to use your backup codes in case you do not have your paired device with you during a login attempt.

Click 'I don't have an authenticator app now' link






- Enter backup code 1 from the saved backup codes when you paired your device
- · Click 'Login'


Disable Two-Factor Authentication

- Individual admins cannot disable two-factor authentication on their own account as long as it is enabled by the account manager in EM
- If 2FA is disabled by the account manager in EM, then you can deactivate it after logging in to your EM account.
- Login to your account by providing credentials and 2FA code.
- Click 'Settings' > 'Portal Set-Up' then 'User Settings' tab
- Click 'Security Settings'



· Click 'Deactivate'

A confirmation dialog is shown:



One Time Password - Enter the code from your paired device



Click 'Confirm'


A success message is shown:

Two-Factor Authentication Deactivation successful

Two Factor Authentication Activation by Admins


If 2FA is not enabled by your account manager in EM, you can enable it for yourself as follows:

- Login to your EM account
- Click 'Settings' > 'Portal Set-Up' then the 'User Settings' tab
- Click 'Security Settings'



Click 'Activate'






• The device pairing procedure is similar as explained in the section above.

11.2.7. Set-up Administrator's Time Zone and Language


Note:

- Admins added through ITarian must set their time zone in the ITarian console.
- Only admins added directly to Endpoint Manager can set their time and language in the EM console.
- The 'User Settings' tab is only available if you login to EM through your dedicated URL. It is not available if you login through ITarian.
- Click 'Settings' > 'Portal Set-Up'
- Click the 'User Settings' tab then 'Portal Settings'





Click 'Edit' at the top-right




- Choose your time zone and interface language from the drop-down menus
- · Click 'Save'.

Your time zone and language selection will be updated. All logs and interface time indicators will use the set time zone.

11.2.8. Configure Audit Log Settings


Click 'Settings' > 'Portal Set-up' then the 'Logging Settings' tab

- Log settings section is available to customers on request. Please contact your account manager if you want to enable this feature for your EM portal.
- The log settings area lets you configure log forwarding to a syslog server. For example, you can use this setting to integrate your logs with a security intelligence and event management (SIEM) product.
- You can generate an audit log report at 'Dashboard' > 'Audit Logs'
- Note This setting forwards the portal logs, not the endpoint logs.



· Click the 'Edit' button





- Write to syslog server Enable / disable log forwarding
- Host Enter IP or hostname of the syslog server
- Port The port through which the server listens to EM logs
- Click 'Save' to apply your settings

11.3.Integrate Apple DEP with Endpoint Manager

Click 'Settings' > 'Apple DEP'

Apple's Device Enrollment Program (DEP) simplifies the activation and management of iOS and Mac devices in an enterprise network. While you will continue to use Endpoint Manager for day-to-day device management, DEP makes the initial setup process far easier for both admins and users.

After integrating EM with DEP:

- Admins no longer have to manually configure each device, nor individually enroll each device with EM. All
 devices you register with DEP will automatically become managed by Endpoint Manager as soon as they
 are turned on.
- All setup tasks, including EM enrollment, are carried out over-the-air (OTA) at device start-up. You can even choose to skip the various setup wizards that usually appear when a device is first turned on.
- Devices can never become unmanaged without your consent, even if the device is factory reset. Admins
 have to remove them from Endpoint Manager to unmanage them.

Endpoint Manager (EM) currently supports iOS devices only.


See https://www.apple.com/business/docs/site/DEP_Guide.pdf for more information about Apple DEP

Process in brief

- Add Apple devices to your DEP account
- Create a virtual MDM server in your DEP account and link it to Endpoint Manager (EM)
 - Once linked, devices in your DEP account are synced with EM
 - Click 'Settings' > 'Apple DEP' > 'Devices' to view them
- Create a DEP profile and assign it to your devices. The DEP profile lets you enable supervisor mode and skip setup wizards
- User activates the device
- Once activated, EM profiles are applied to the device and it is enrolled into EM



- You can view the devices at 'Devices' > 'Device List'
- If you remove a device from your DEP account, it remains enrolled in Endpoint Manager.
- If you remove a device from EM, it remains enrolled in DEP. You will have to reapply the DEP profile or manually enroll it again to return it to EM.




Click the following links for help to integrate Endpoint Manager with DEP:

- Link Endpoint Manager with Apple DEP
- Manage Apple DEP Devices
- Manage Apple DEP Profiles
- Configure Apple DEP Notification Settings

11.3.1. Link Endpoint Manager with Apple DEP


- You first need to complete the following steps with Apple:
 - Enroll in the Apple Device Enrollment Program (DEP) program if you haven't done so already.
 - Link Endpoint Manager (EM) to your DEP account. EM is the 'MDM solution' referred to in Apple's docs (see link below).
 - Assign devices to your DEP account.
- Please follow the steps in **Apple's help documentation** to complete the processes above.
- Completing these steps will establish a virtual Endpoint Manager server in DEP. The virtual server is synchronized with your physical EM account.
- Next, you need configure settings in Endpoint Manager to complete the link to DEP.
- Click 'Settings' > 'Apple DEP'
- Click the 'Certificate' tab:






- First, you need to install an Apple Push Notification (APN) certificate on your EM portal. This certificate allows Endpoint Manager to communicate with iOS and Mac devices.
- You may already have done this if you are currently using EM to manage iOS devices. If not, then:
 - Click 'Settings' > 'Portal Set-up' > 'Client Settings' > 'mac OS/iOS' > 'Create APN certificate'
 - Complete the certificate application form then click 'Create'.
 - See 'Add Apple Push Notification Certificate' if you need help with this.
- After installing the APN cert, you need to install a DEP certificate. This certificate allows Endpoint Manager to communicate with Apple's DEP servers.
- Click 'Settings' > 'Portal Set-up' > 'Apple DEP'
- · Click the 'Start' button






- Complete all fields on the certificate request form. Enter your Apple ID and your company details.
- Click 'Create' to submit the form, then 'Download Public Key':




- Save the key in a safe place as you will need to upload it to the DEP server later.
- Click 'Next' after you have saved the key.






Next, you need to create a virtual EM server on Apple's DEP server:

- Click 'Go to DEP Portal' and login to your DEP account
- Open the 'Device Management Settings' page then click 'Add MDM Server'
- Create a name for your virtual server in the 'MDM Server Info' field. This can be anything you choose.
- · Make sure 'Allow this MDM server to release devices' is enabled
- Click 'Choose File...' to upload the public key you saved.
- Click 'Save':






 After authenticating your request, DEP will generate a token which you need to upload to Endpoint Manager:




Click 'Download Token'




- · Click 'Download Server Token' and save it.
- Go back to Endpoint Manager and upload the token
 - Click 'Settings' > 'Apple DEP' > 'Certificate'
 - Click 'Browse', locate your token then click 'Open':





· Click 'Complete'

The 'Certificates' tab will now show your DEP certificate details:



 Your Endpoint Manager and Apple DEP accounts are now synced. You can now add devices and configure your DEP profile.


11.3.2. Manage Apple DEP Devices

- Click 'Settings' > 'Apple DEP' then the 'Devices' tab
- DEP registered devices are automatically synced with EM after you have linked your account
- After enrollment, the devices will appear in two places:
 - i. **Settings > Apple DEP > Devices** Device identified by serial number.
 - ii. **Devices > Devices List** Device identified by name. Open device details to view the serial number.
- DEP enrolled devices will have two profiles:
 - i. DEP Profile Created during enrollment to the DEP program. You can create and assign new DEP profiles in the 'Profiles' tab. See Manage Apple DEP Profile
 - ii. **Endpoint Manager Profile** The default OS profile is applied by default. You can change this as required.



The DEP 'devices' area allows you to:

- Assign DEP profiles to devices
- Remove profiles
- Update device information from DEP
- Update DEP information



Column Heading	Description		
os	Operating system of the registered device. Currently only iOS is supported.		
Serial Number	Apple assigned device identification number		
Model	Type of Apple device		
Profile Assigned	The DEP profile delegated to the device. See 'Profile Status' below for more info:		
Profile Status	Empty - No profile is assigned to the device		
	 Assigned - Profile is ready for deployment, but the user has not yet activated the device. 		
	Pushed - User has activated the device and the DEP profile is installed		
	Removed - DEP profile was installed then deleted from the device		
Added	Date and time the device was registered in DEP		
EM Enroll Status	'EM enrolled' means that the endpoint manager profile has been installed on the device. This means you can manage the device via the Endpoint Manager console.		
	 User has completed the device setup process and installed the DEP profile. 		
	 The EM iOS profile is installed right afterwards to bring the device under MDM control 		
	 You can view enrolled devices at 'Devices' > 'Device List' 		
	Not Enrolled - User has not started the device setup process.		
Control buttons:			




Assign Profile	Delegate a DEP profile to the device. The profile will be installed when the device is activated. See Assign Profiles to Device
Unassign Profile	Removes the selected profile from a device. See Remove Profiles
Sync with DEP (only selected)	Update profile information for the device from DEP. See Update Device Information from DEP
Update info (Global)	Checks DEP server the status of all devices. See Update DEP Information

- · Click the funnel icon to filter devices by various criteria
- · Click a column header to sort by ascending / descending order

Assign DEP Profiles to Devices


· Select target devices then click 'Assign Profile':



- Start typing the name of a profile and select from the suggestions
- · Click 'Assign'
- The following confirmation is shown:

Device(s) assigned successfully

Users are asked to install the profile when the device is activated:




Endpoint Manager profiles are applied as follows:

- · Custom device profiles are assigned if they exist.
 - See Assign Configuration Profiles to User Devices, and Assign Configuration Profiles to a User Group
- The 'default' profiles are applied if no custom profiles exist.
 - See Manage Default Profiles if you want help with default EM profiles.

Remove DEP Profiles

Select target devices then click 'Unassign Profile':





The following confirmation is shown:

Profile unassigned successfully

Note - The device stays enrolled to Endpoint Manager, and all EM profiles remain in place.

Update Device Information from DEP

Endpoint Manager periodically contacts the DEP server to update the status of device profiles. You can manually run this update as follows:

Select the target devices then click 'Sync with DEP (only Selected)'

Device enqueued for sync.

The device profile status is refreshed.

Update DEP Information

Device information from DEP is updated periodically. You can update in real-time if required.

Click 'Update Info (Global) at the top

Request for updating sent successfully: Added 0, Deleted 3, Modified 0



11.3.3. Manage Apple DEP Profiles


Click 'Settings' > 'Apple DEP' > 'Profiles'

- A DEP profile is assigned to target devices when you enroll them to Apple's Device Enrollment Program.
- Each profile lets you enable supervisor mode and other top-level management settings. Profiles also let you skip the setup wizards that appear when a user first activates a device.
- The profile is enabled right after the user activates the device. Activated profiles are listed as 'Pushed' in the 'Devices' tab.
- After enrollment, the device will appear in two places:
 - Settings > Apple DEP > Devices Device identified by serial number.
 - Devices > Devices List Device identified by name. Open device details to view the serial number.

The profiles area lets you:

- Create, clone and remove profiles
- Specify profile details:
 - Top-level device management settings
 - Enable / disable various setup wizards
 - Enable / disable various iOS features
- Publish the profile to the DEP server. Only published profiles can be assigned to devices.

Click 'Settings' > 'Apple DEP' then the 'Profiles' tab:






Column Heading	Description					
Name	DEP profile label					
Created By	Name of the admin that configured the profile					
Created At	Date and time the profile was configured					
Updated At	Date and time the profile was modified					
Published	Published means the profile has been submitted to, and accepted by, the DEP server.					

Add a DEP profile

- Click 'Settings' > 'Apple DEP' > 'Profiles'
- Click 'Add Profile'
- Type a label for the profile then click 'Add':



- You will go straight to the profile configuration screen
- Click the 'Edit' button to review and modify profile settings:




General

• Change the profile name and general description.

Settings

Specify top-level device management settings, contact details and device department.:





- Allow Pairing Specify whether the device can pair with other devices. For example, with Apple
 watches, earphones and other Bluetooth devices.
- **Is Supervised** Puts the target device in supervised mode. You must enable this setting to manage the device.
- **Is Multi User** More than one user account can be stored on the device. This lets multiple users share a single device, while maintaining the privacy of all users. This is required for education functionality such as Apple School Manager.
- **Is Mandatory** If enabled, the user must enroll the device to EM at device activation. The user cannot skip installation of the EM profile.
- Department The department of your company that they device belongs to.
 - ITarian users This is not connected to Service Desk departments programmatically. However, you can use a Service Desk department name here for the sake of identification.
- Support Email Address The address at which device users can contact your IT staff.
- Support Phone Number The number at which device users can contact your IT staff.
- Await Device Configured If enabled, users will not be able to proceed in the setup assistant until
 Endpoint Manager sends a command that states the device is configured. This setting only applies if
 the devised is in supervised mode.
- Is MDM removable If enabled, the Endpoint Manager (EM) profile can be removed from the device.
 This removes it from EM control. Note The EM profile cannot be removed if the device is in supervised mode.
- Do Not Ask User Credentials
 - **Enabled** The device can be activated without a user authentication. The admin can assign the device to any user.
 - Disabled The user has to login to the device at activation. Note The user should be already
 have be added to Endpoint Manager.




Click 'Save'.

Skip Setup Items

Specify which setup wizards should be shown during device activation. User can configure these items later if allowed by the Endpoint Manager profile.

- Click 'Skip Setup Items'. All setup items are enabled/shown by default.
- · Click 'Edit' to disable specific items.



· Click 'Save' to apply your changes.


The next step is to publish the profile to the DEP server.

Publish Profile

You have to submit the profile to the DEP server in order to push it to devices.

- Click 'Settings' > 'Apple DEP' > 'Profiles'
- Click the name of a profile. Note Published profiles cannot be re-published or deleted.





Click Publish Profile at top-left

A confirmation message is shown:

Profile successfully published

You can assign a published profile to devices. See Manage Apple DEP Devices.

Edit a Profile

- · Click on the name of a profile then click 'Edit' at top-left
- The process is the same as explained above for adding a profile
- You cannot modify a published profile

Clone a Profile

- Select a profile and click the 'Clone Profile' button
- You can create a new profile by copying an existing profile making changes as required
- · You can clone both published and unpublished profiles


Delete a Profile

- Select a profile and click 'Delete Profile'
 OR
- · Click the name of the profile and click 'Delete Profile'
- You cannot delete a published profile




11.3.4. Configure Apple DEP Notifications

- Click 'Settings' > 'Apple DEP' > 'Settings'
- · Click 'Edit':



Send Notifications - Choose whether or not you want to see alerts from DEP in the notifications area:



If enabled, you will see alerts when:

- A DEP profile is published (submitted to the DEP server)
- A DEP profile is unassigned or unassigned ('Settings' > 'Apple DEP' > 'Devices')
- A device is enrolled to DEP, or removed from DEP.




11.4. View Version and Support Information

Click 'Settings' > 'Support'

The support panel shows contact information, Endpoint Manager version, and a list of platforms supported by this version.

View version and support details


Click 'Settings' > 'Support'



- Contact Information Support telephone numbers and email addresses
- Supported Device Platforms The devices and operating systems supported by this version of Endpoint Manager.
- Latest Platform and Client Versions Version numbers of the Endpoint Manager server and client software.


Submit Ticket - End-users can submit tickets to your Service Desk module for your technicians to handle.

Right-click on the communication client tray icon and select 'Submit ticket'



The 'Submit ticket' dialog opens:





- **Issue Summary** Provide a short description of the issue.
- **Department** Select the department to whom the ticket should be assigned.
- Priority Level Select the priority from the drop-down. The levels are: Low, Normal, High and Critical.
- Issue Details Provide detailed description of the issue.
- Click 'Submit'.

Tip: You can rebrand the 'Submit ticket' window, and/or add specific departments for the end-user to choose. See **Communication Client and Comodo Client - Security Application UI Settings** in **Create Windows Profiles** for help with this.

A support ticket will be created in the Service Desk module of the ITarian account based on your subscription and assigned to the selected department.




12. License Management

Click 'License Management' > 'License Management'

This section allows you to:

- · View license details
- Add a new license
- Delete a license
- Renew a license
- Use a single license to enroll devices for multiple customers (MSPs only)
- Assign multiple licenses to a single customer (MSPs only)
- Configure license usage reports



Admins with appropriate privileges will see subscription alerts such as unpaid dues, license is about to expire in 'x' days and so on. Examples of license alerts are shown below:

Unpaid bills without valid AEP licenses alert within grace period:

All Endpoint Manager functionalities will be disabled in 6 days due to unpaid bill(s) In order to continue using Endpoint Manager functionalities, pay unpaid bill(s), or add new licenses. Pay Now Buy New License

Unpaid bills alert after the grace period:

HIVES that are not covered by your AEP analyst Electrocepts are becomes, in order to commune using Encoporal Manager Functionalistics, you need to pay unpaid delign) or also new incenses. Pay New Excesses

Click 'Pay Now' or 'Buy New License' and complete the purchase process.

See the following sections for help with each tab:

- Licenses View and manage your licenses
- License Allocation- Use your licenses for multiple customers
- Bill Forecast View estimated future charges




12.1. Manage your Licenses

- Click 'License Management' > 'License Management'
- This area lets you add, delete and renew licenses, view license details, change license allocation, configure reports, and more.

See the following for more help:

- · License table columns
- Add a license
- Delete a license
- View license details, change allocation type
- Renew a license
- Configure usage report settings
- Export list of licenses

License table columns




Column	Description
Allocation Type	States whether you can use the license for multiple customers or a single customer. • Global (G) - You can use the license for multiple customers • Allocated (A) - You can use the license on a single customer You can change the allocation type of a license as follows: • Select a license • Click the 'Details' button at the top • Click the 'Edit' button • Select 'Global' or 'Customer' in the 'Allocation type' drop-down. • Click 'Save' See 'View License Details and Change Allocation Type' if you need more help.
License Key	Unique identifier for the license.
License Configuration	The security features which are included on the license.
Seats	Number of devices covered by the license. The infinity symbol icon indicates unlimited seats. These licenses support unlimited devices, but are limited to a one month term.



Allocated	The number of seats that you have already assigned to devices. Seats can be assigned to a single customer or multiple customers.			
Free	Number of seats remaining on the license.			
Days to Expiration	Number of days left on the license.			
Expires	License period end date and time			
License Type	Indicates whether the subscription is free, premium or managed.			

- Click column headers to sort items in ascending or descending order
- You can enter license keys in the search box to locate specific licenses.
- Click the funnel at top-right to open more filters:





Add a License


You can purchase new licenses from Comodo Account Manager (CAM) at https://accounts.comodo.com.

- Log in at https://accounts.comodo.com with your Comodo username and password
- Select 'Endpoint Manager' and complete the purchase process.

Your license key will be sent to your registered email address.

Upgrade a license

- Alternatively, click 'License Options' at the top of the Endpoint Manager interface.
- This opens a comparison of available license types:



Click 'Upgrade Now' under the license type you want.


You will be taken to the order forms to complete the purchase.

Register the license

Once you have obtained a new license, you need to register it in Endpoint Manager.

- Click 'License Management' > 'License Management'
- · Open the 'Licenses' tab
- Click 'Add New License' at the top left.





- Enter the license key from your confirmation email.
- · Click 'Add'.

Your new license is shown in the 'License Key' column.

Delete a License

- · Click 'License Management' > 'License Management'
- Open the 'Licenses' tab
- Select the license and click 'Delete License' at the top



Click 'Delete' to remove the license from the list.

Note - You can add the license again if required. See above how to add a license.

View License Details and Change Allocation Type

- Click 'License Management' > 'License Management'
- · Open the 'Licenses' tab
- Select the license and click 'Details' at the top.

The license details screen opens:

The license details screen has three tabs:

• **License Summary** - Details of your subscriptions for Endpoint Manager and other Comodo products. You can change the license allocation type from here too.



- Customers Shows how your license seats are allocated among your customers. You can change seat
 allocation from here.
- Report Settings Configure license usage reports.

License Summary


- Main License Details Info about your Endpoint Manager subscriptions.
- Sub License Details Info about additional subscriptions included with the main license. These licenses are for other Comodo products such as Valkyrie.

Change License Allocation Type

- Click on a license key to open its details screen
- Click the 'Edit' button on the right
- Use the drop-down menu to change the allocation type:
 - Global (G) You can use the license for multiple customers
 - Allocated (A) You can use the license on a single customer








- Click 'Save'
- You can assign seats to specific customers in the 'Customers' tab.

Customers

The customers area shows how your seats are distributed among your customers. You can reallocate seats, add new licenses to a customer, renew licenses, and more.



The top row shows the total number of seats covered by the license, total seats assigned to customers and the number of seats remaining.

Column Heading	Description
Customer	Name of your client. Click the name to view their license usage.




Device Total	Number of endpoints you have assigned to the customer in Endpoint Manager.					
Device with CCS	lumber of endpoints which have Comodo Client Security (CCS) installed					
Total Seats	Number of seats available on all licenses assigned to the customer					
Used Seats	Number of seats currently assigned to the customer's endpoints					
Unlicensed Devices	Number of devices enrolled for the customer and have CCS installed, exceeding the total number of seats allotted for the customer.					
Unused Seats	Number of seats remaining on the license					
	 Unused seats = Total seats - Used seats 					
Allocate Seats	Add or remove seats to/from the customer					
Controls	Add License - Import a new license to a your account. See Add a License for more details.					
	Apply - Save your settings.					
	Unallocate - Remove licenses from a customer					
	Renew - Renew a license for a customer.					

The interface allow you to:

- Redistribute seats to customers See 'Select a license and assign it to different customers' for more help with this.
- Generate a report of seat distribution

Export the seat distribution report for a license

- Click 'License Management' > 'License Management'
- Open the 'Licenses' tab
- · Select the license and click 'Details' at the top
- Click the 'Customers' tab
- Click the 'Export' button above the table then choose 'Export to CSV':






- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

Configure Usage Report Settings

The report contains details on the license period, allocation type, customers covered by the license, total devices used, and so on.

- Click 'License Management' > 'License Management'
- · Open the 'Licenses' tab
- Select the license and click 'Details' at the top
- Open the 'Report Settings' tab and click 'Edit' at top-right




- **Period** How frequently the report is generated.
- EM Administrators Send the report to users with the admin role
- Send to email list Add the mail addresses of people to whom the report should be sent.
 - Enter an email address then press 'Enter'. Repeat the process to add more addresses.
- Send to users Add enrolled users to whom the report should be sent.
 - Enter the first few letters of a username then select from the suggestions.
- Click 'Save'.


Renew a License

- Click 'License Management' > 'License Management'
- Open the 'Licenses' tab
- Select the license and click 'Renew License' at the top





The 'License Options' screen shows a comparison of available license types:



Click 'Upgrade Now' under the license type you want.


You will be taken to the order forms to complete the purchase.

Export the list of licenses

- Click 'License Management' > 'License Management'
- Open the 'Licenses' tab



- Click the funnel icon to filter which records are included in the report.
- Click the 'Export' button above the table then choose 'Export to CSV':



- The CSV file will be available in 'Dashboard' > 'Reports'
- See Reports in The Dashboard for more details.

12.2. Manage License Allocation

- You can use a single license on multiple customers, or use multiple licenses on a single customer
- Make sure the license allocation type is 'Global':
 - Select the license, click 'Details' at the top then 'Edit'
 - Locate the 'Allocation type' drop-down.
 - Change the type to 'Global'

Allocate licenses to customers

View license usage by customers

Allocate licenses to customers


There are two ways to assign licenses to customers:

- Method 1 Select a license and assign it to different customers
- Method 2 Select a customer and assign them licenses

Select a license and assign it to different customers


- Click 'License Management' > 'License Management'
- Open the 'Licenses' tab
- Expand a license row to view your customers





OR

Select a license then click 'Details' > Click the 'Customers' tab



Allocate seats to a customer

- Type a number in the 'Allocate seats' box next to a customer to assign seats to them.
- Click 'Apply'
- Make sure enough free seats are available on the license.

Remove seats from customer


Select a customer and click 'Unallocate'.

Allocate seats from multiple licenses to a customer

- Click 'License Management' > 'License Management'
- Click the 'License Allocations' tab
- · Click the down-arrows on the right to view all licenses assigned to a customer

ITarian Endpoint Manager - Administrator Guide





- Type a number in the 'Allocate seats' box to assign seats from a specific license.
- Click 'Apply'
- Make sure enough free seats are available on the license.


View license usage

- Click 'License Management' > 'License Management'
- · Open the 'License Allocations' tab






Click a customer name to open their details screen:



This interface has two tabs:

- Customer Summary Overall licensing information about the company.
- Related Licenses Details of seat allocation from different licenses.



• You can allocate / remove seats as explained above.



12.3. Bill Forecast

Click 'License Management' > 'License Management' > 'Bill Forecast'

The bill forecast area summarizes license usage on your account.

- Total seats The number of licensed seats you have available per-product, across all licenses.
- **Enrolled Endpoints** The number of devices you have enrolled in each product category. Here are the conditions under which a device is classed as 'enrolled' for each category:
 - Endpoint Manager Device has the communication client (CCC) installed, but not the security client (CCS) or Endpoint Detection and Response (EDR) client.
 - Advanced Endpoint Protection Device has CCS installed.
 - Endpoint Detection and Response Device has the EDR client installed.

If a device has both the CCS and EDR clients installed, it will be added to the counts for both products.

 Overuse - The number of unlicensed endpoints. You will need to purchase licenses for unlicensed endpoints.

Product Category	Product name.				
Total Seats	The number of licenses you have available for deployment for the product.				
	An infinity symbol indicates a free license with unlimited seats.				
Enrolled Endpoint Count	Devices count as enrolled for each category as follows:				
	Endpoint Manager - Devices that only have CCC installed. These are 'manage only' devices that do not have the security or EDR clients installed.				
	Advanced Endpoint Protection (AEP) - Devices that have Comodo Client Security installed.				
	Endpoint Detection and Response (EDR) - Devices that have the EDR client installed.				
	A device that has both the EDR and CCS clients will count as an enrolled device in both the AEP and EDR columns.				
Overuse	Number of endpoints over your licensed limit. Some scenarios:				
	Endpoint Manager - You can add more endpoints than covered by your licenses, but we will charge you for the excess.				
	We will bill you for the additional devices on the last day of the month.				
	We will block the additional devices if no payment is received within 14 days.				
	AEP - All endpoints must be licensed or CCS is disabled on all devices.				
	If you deployed CCS in bulk then any excess endpoints are shown here.				
	 You have to purchase licenses for the excess devices or security functionality is disabled for all devices. 				
	Alternatively, you can remove CCS from the excess devices.				
	EDR - You must purchase licenses beforehand. You cannot deploy EDR on more devices than allowed by your license. There is no bulk installation option for EDR as of now.				



Appendix 1a: Endpoint Manager Services - IP Nos, Host Names and Port Details EU Customers

Note: This page contains information for customers located in Europe. Click here to see USA information instead.

- Endpoint Manager communicates with Comodo servers and your devices to issue commands, run virus scans, deploy updates and more.
- You need to configure your firewall accordingly to allow these connections.
- All client to server communications are encrypted over https connections using the strongest TLS protocols, RSA 2048 bit keys and SHA 256 algorithms.
- The tables on this page show firewall requirements for the following ITarian services:
 - Communication Client (CC)
 - Comodo Client Security (CCS)
 - Endpoint Manager Server (on premise installations)
 - Remote Control sessions
 - Remote Control Direct connection
 - Remote Control Peer to Peer connection
 - Remote Control Relay connection
 - Diagnostic Tools
 - All settings grouped by port

Communication Client (CC)

Communication Client (CC)							
Service Purpose		Hostname IP		Port	Criticality and notes		
CC	Communication between device and EM server	subdomain.cmdm.co modo.com	Dynamic (Amazon load balancing)	443	Mandatory		
Enrollment	To get client certificates	mdmsupport.comodo .com (up to CCC 6.29) mdmsupport.cmdm.c omodo.com (CCC 6.30+)	Dynamic (Amazon load balancing)	443	Mandatory		
Monitoring and alerts	Access to Monitoring and alerts server	plugins.cmdm.comod o.com	Dynamic (Amazon load balancing)	443	Mandatory		
File rating management	Access to Local Verdict Server	subdomain.cmdm.co modo.com	Dynamic (Amazon load balancing)	443	Optional This is for reporting data from CCS		



Windows push service (XMPP)	Device communication (push messages)	xmpp.cmdm.comodo.	18.197.167.137 34.227.128.175	443	Mandatory
LDAP synchronizati on	Synchronization with LDAP via device	User's LDAP server host	User's LDAP server IP	389 636 (LDAPS)	Optional For LDAP sync via device only. Related to Device to LDAP server connections only
SSO	Single Sign On	one.comodo.com	Dynamic (Amazon load balancing)	443	Mandatory
Client Security installation	Download and install/upgrade Client Security agent. Requests to download.comodo. com are redirected to cdn.download.com odo.com which is managed by The CDN provider, and those IP addresses can change	download.comodo.co m cdn.download.comod o.com	178.255.82.5 Cloudflare's IP range: 104.37.182.3	443, 80	Optional For CCS installation/upgrade only
OCSP	Client certificate revocation checking http://ocsp.comodoc		Dynamic load balancing	80	Optional For mobile devices only. The Windows client does not perform OCSP checks.
CRL	Client certificate revocation om/ checking		Dynamic load balancing	80	Optional For mobile devices only. The Windows client does not perform CRL checks.
3rd Party Patch Management	3rd party applications updates	patchportal.one.com odo.com	Dynamic (Amazon load balancing)	443	Optional For 3rd party software updates only
Telemetry	Sending telemetry data for analysis	cescollector.cwatcha pi.com	Dynamic (Amazon load balancing)	443	Optional
Local distribution of packages	Distribute different types of updates via local network	Local hostname	Local IP	6881, 6882	Optional. Used for updates distribution locally by torrent principle. Ports are

ITarian Endpoint Manager - Administrator Guide



			bound by EM Service. 6882 is used if 6881 is in use already.

Comodo Client - Security (CCS)

	Comodo Client - Security (CCS)							
Service	Purpose	Hostname	IP	Port	Protocol	Criticality and notes		
FLS	FLS lookup	fls.security.co modo.com	199.66.201.16	4447 (optional), 53	UDP	Mandatory - choose *either* UDP or TCP for FLS UDP is the main, preferred FLS lookup channel 53 - Default port. 4447 - Reserve port. Can be specified manually in profile. At least one of the two ports must be open.		
	FLS lookup	fls.security.co modo.com	199.66.201.16	4448 (optional), 80	TCP	Mandatory - choose *either* UDP or TCP for FLS TCP is the reserve FLS lookup channel. 80 - Default port 4448 - Reserve port. Can be specified manually in profile. At least one of the two ports must be open		
Valkyrie	Valkyrie lookup	valkyrie.como do.com	Dynamic (Amazon load balancing)	443	HTTPS	Optional Valkyrie lookup is currently disabled on CCS, CCS gets Valkyrie verdicts from LVS.		
	Submit to Valkyrie	valkyrie.como do.com	Dynamic (Amazon load balancing)	443	HTTPS	Mandatory		
cdn.downloa d.comodo.c om	Update / upgrade mirror	cdn.download. comodo.com	Cloudflare's IP range: 104.37.182.3	80	HTTP	Mandatory		
		cdn.download.	Cloudflare's IP	443	HTTPS			



		comodo.com	range:			
			104.37.182.3			
download.co modo.com	Update/upgrade	download.com odo.com	178.255.82.5	80	HTTP	Mandatory
	Requests to download.como do.com are redirected to	download.com odo.com	178.255.82.5	443	HTTPS	
	cdn.download.c omodo.com which is managed by					
	The CDN provider, and those IP addresses can change					
LVS	Download the EM verdicts database	s3.eu-central- 1.amazonaws. com	Dynamic (Amazon load balancing)	443	HTTPS	Mandatory
	LVS lookup	subdomain.cm dm.comodo.co m	Dynamic (Amazon load balancing)	443	HTTPS	
OCSP	Client certificate revocation checking	http://ocsp.co modoca.com/	Dynamic load balancing	80	-	Optional CCS does not perform CRL checking yet
CRL	Client certificate revocation checking	http://crl.como doca.com/	Dynamic load balancing	80	-	Optional CCS does not perform CRL checking yet
FLEVEN	Sending telemetry data for analysis	cis.td.security. comodo.com	Dynamic (Amazon load balancing)	443	-	
Telementry	Sending telemetry data for analysis	tel.security. comodo.com	159.203.65.195	261	-	
CWATCH	Sending telemetry data for analysis	api.mssp. comodo.com	Dynamic (Amazon load balancing)	443	-	

Endpoint Manager Server (on premise installation)

Endpoint Manager Server (on premise)								
Service	Service Purpose Hostname IP Port							
E-mail	Connection to the configured SMTP server for e-mail sending	SMTP server hostname	SMTP server IP	25				



LDAP synchronization	Direct synchronization with LDAP	User's LDAP server host	User's LDAP server IP	389 636 (LDAPS)
Connection to Comodo Accounts Manager	License verification	https://accounts.como do.com	178.255.85.140	443
Google Cloud Messaging	To push messages	https://android.google apis.com/gcm/send	Dynamic	443
Local Verdict Server	File rating management	EM server hostname	EM server IP	443

Remote Control

Remote Control							
Service	Purpose	Hostname	IP	Port	Protocol	Criticality and notes	
XMPP	Remote Control Session (with new version of Comodo RC*	xmpp.cmdm.c omodo.com	18.196.138.4 18.197.8.210	443	HTTPS	Mandatory for both RC host and target device	
STUN server	To receive possible network configuration, external ip etc.	stun.l.google. com	Dynamic	19302	UDP	Mandatory for both RC host and target device for peer-to- peer and relay connections.	
Direct connection	Establish direct connection between RC and target device.	-	IP of the RC host AND target host	Local port range specified in profile. Win7+/MacO S. Default port range= 49152 - 65535 WinXP/2003. Default port range = 1025-5000	UDP	Mandatory for both RC host and target device	
Peer-to-peer connection	Establish peer- to-peer connection RC and target device.	-	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478	UDP	Mandatory for both RC host and target device for peer-to-peer connections.	
Relay	Establish relay	-	18.196.107.208	3478, 49152	UDP	Mandatory	



connection connection between RC and target device.	52.29.123.206 34.232.133.48 18.208.23.45	- 65535	for both RC host and target device for relay connections.
---	--	---------	--

Remote Control - Direct connection by traffic direction *

Outgoing Traffic						
	Source		Destination	Protocol		
IP	Port	IP	Port			
Local IP 1	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	Local IP 2	local port range specified in profile (Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	UDP		

Incoming Traffic						
	Source		Destination			
IP	Port	IP	Port	Protocol		
Local IP 2	local port range specified in profile (Win7+/MacOS default port range: 49152 - 65535) (WinXP/2003 default port range: 1025- 5000)	Local IP 1	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535) (WinXP/2003 default port range: 1025-5000)	UDP		

^{* -} applies to both sides - RC host and target

Remote Control - Peer to Peer Connection by traffic direction *

Outgoing Traffic					
	Source	Destina	ition	Protocol	
IP	Port	IP	Port		
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478	UDP	
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535)(WinXP/2003 default port range: 1025-5000)	stun.l.google.com	19302		

Incoming Traffic				
Source	Destination	Protocol		



IP	Port	IP	Port	
18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	UDP
stun.l.google.com	19302	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535)(WinXP/2003 default port range: 1025-5000)	

^{* -} applies to both sides - RC host and target

Remote Control - Relay connection by traffic direction*

Outgoing Traffic					
	Source	Destina	Destination		
IP	Port	IP	Port		
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478, 49152 - 65535	UDP	
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	stun.l.google.com	19302		

Incoming Traffic					
Soul	Source		Destination		
IP	Port	IP	Port		
18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478, 49152 - 65535	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	UDP	
stun.l.google.com	19302	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)		

• - applies to both sides - RC host and target

Diagnostic Tools

Diagnostic Tools					
Service	Purpose	Hostname	IP	Port	Critically and



					notes
CCS Report Tool	Collect event logs to help more effectively troubleshoot issues.	c1report.comodo. com	178.255.85.136	22	Optional. For manual log uploads

All settings grouped by port

This table contains the same information as the other four tables on this page but with services grouped by port number.

	Settings Grouped by Port						
Port	Service	IP	URL / Hostname	Protocol	Component		
443	CC	Dynamic (Amazon load balancing)	subdomain. cmdm.como do.com	HTTPS	Communication Client		
	Enrollment	Dynamic (Amazon load balancing)	mdmsuppor t.comodo.co m (up to CCC 6.29)	HTTPS			
			mdmsuppor t.cmdm.com odo.com (CCC 6.30+)				
	Monitoring and alerts	Dynamic (Amazon load balancing)	plugins.cmd m.comodo.c om	HTTPS			
	File rating managemen t	Dynamic (Amazon load balancing)	subdomain. cmdm.como do.com	HTTPS			
	Windows push service (XMPP)	18.197.167.137 34.227.128.175	xmpp.cmdm .comodo.co m	HTTPS			
	SSO	69.4.89.244	one.comod o.com	HTTPS			
	3rd party patch managemen t	Dynamic (Amazon load balancing)	patchportal. one.comod o.com	HTTPS			
	Client Security	178.255.82.5	download.c omodo.com	HTTPS			



	installation	Cloudflare's IP range: 104.37.182.3	cdn.downlo ad.comodo. com	HTTPS	
	Telemetry	Dynamic (Amazon load balancing)	cescollector. cwatchapi.c om	HTTPS	
	Valkyrie	178.255.87.4	valkyrie.co modo.com	HTTPS	Comodo Client Security
	Update/upgr ade. Requests to download.co modo.com are redirected to	178.255.82.5	download.c omodo.com	HTTPS	
	cdn.downloa d.comodo.c om which is managed by The CDN provider, and those IP addresses can change				
	Updates/upg rades mirror	Cloudflare's IP range: 104.37.182.3	cdn.downlo ad.comodo. com	HTTPS	
	FLEVEN	Dynamic (Amazon load balancing)	cis.td.securi ty. comodo.co m	HTTPS	
	CWATCH	Dynamic (Amazon load balancing)	api.mssp. comodo.co m	HTTPS	
	LVS	Dynamic (Amazon load balancing)	s3.eu- central- 1.amazona ws.com	HTTPS	
		Dynamic (Amazon load balancing)	subdomain. cmdm.como do.com	HTTPS	
	License verification	178.255.85.140	accounts.co modo.com	HTTPS	EM server (on premise)
	Google cloud messaging	Dynamic	android.goo gleapis.com /gcm/send	HTTPS	
	Apple push notifications	Dynamic	gateway.pu sh.apple.co	HTTPS	



			m		
	Local Verdict Server	EM server IP	EM server hostname	HTTPS	
	XMPP	18.196.138.4 18.197.8.210	xmpp.cmdm .comodo.co m	HTTPS	Remote Control
80	Client Security	178.255.82.5	download.c omodo.com	HTTPS	Communication Client
	installation	Cloudflare's IP range: 104.37.182.3	cdn.downlo ad.comodo. com	HTTPS	
	OCSP	Dynamic load balancing	http://ocsp.c omodoca.co m/	HTTPS	
	CRL	Dynamic load balancing	http://crl.co modoca.co m/	HTTPS	
	FLS Lookup	199.66.201.16	fls.security.c omodo.com	HTTPS	Comodo Client Security
	Update/upgr ade.	178.255.82.5	download.c omodo.com	HTTPS	
	Requests to download.co modo.com are redirected to				
	cdn.downloa d.comodo.c om which is managed by The CDN				
	provider, and those IP addresses can change				
	Updates/upg rades mirror	Cloudflare's IP range: 104.37.182.3	cdn.downlo ad.comodo. com	HTTPS	
	OCSP	Dynamic load balancing	http://ocsp.c omodoca.co m/	HTTPS	
	CRL	Dynamic load balancing	http://crl.co modoca.co m/	HTTPS	
	Apple push	Dynamic	gateway.pu	HTTPS	EM server (on



	notifications		sh.apple.co m		premise)
22	CCS Report Tool	178.255.85.136	c1report.co modo.com	SSH	Comodo Client Security
25	Email	SMTP server IP	SMTP server hostname	SMTP	EM server (on premise)
53	FLS Lookup	199.66.201.16	fls.security.c omodo.com	UDP	Comodo Client Security
261	Telementry	159.203.65.195	tel.security. comodo.co m	HTTPS	Comodo Client Security
4447 (Optional)	FLS Lookup	199.66.201.16	fls.security.c omodo.com	UDP	Comodo Client Security
4448 (Optional)	FLS Lookup	199.66.201.16	fls.security.c omodo.com	UDP	Comodo Client Security
389	LDAP synchronizat ion	User's LDAP server IP	User's LDAP server IP	-	Communication Client
	LDAP synchronizat ion	User's LDAP server IP	User's LDAP server IP	-	EM server (on premise)
636	LDAP synchronizat ion	User's LDAP server IP	User's LDAP server IP	-	Communication Client
	LDAP synchronizat ion	User's LDAP server IP	User's LDAP server IP	-	EM server (on premise)
2195	Apple push notifications	Dynamic	gateway.pu sh.apple.co m	-	EM server (on premise)
6881, 6882	Local distribution of packages	Local IP	Local hostname	TCP	Communication Client
2196	Apple push notifications	Dynamic	gateway.pu sh.apple.co m	-	EM server (on premise)
19302	STUN server	Dynamic (Amazon load balancing)	stun.l.googl e.com	UDP	Remote Control tool
Win7+/MacOS. Default port range = 49152 - 65535	Direct connection	IP of the RC host AND target host	N/A	UDP	
WinXP/2003. Default port range = 1025-					

ITarian Endpoint Manager - Administrator Guide



5000					
3478	Peer-to-peer connection	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	-	UDP	
3478, 49152 - 65535	Relay connection	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	-	UDP	



Appendix 1b: Endpoint Manager Services - IP Nos, Host Names and Port Details US Customers

Note: This page contains information for customers located in the USA. **Click here** to see Europe information instead.

- Endpoint Manager communicates with Comodo servers and your devices to issue commands, run virus scans, deploy updates and more.
- You need to configure your firewall accordingly to allow these connections.
- All client to server communications are encrypted over https connections using the strongest TLS protocols, RSA 2048 bit keys and SHA 256 algorithms.
- The tables on this page show firewall requirements for the following ITarian services:
 - Communication Client (CC)
 - Comodo Client Security (CCS)
 - Endpoint Manager Server (on premise installations)
 - Remote Control sessions
 - Remote Control Direct connection
 - Remote Control Peer to Peer connection
 - Remote Control Relay connection
 - Diagnostic Tools
 - All settings grouped by port

Communication Client (CC)

	Communication Client (CC)							
Service	Purpose	Hostname	IP	Port	Criticality and notes			
СС	Communication between device and EM server	subdomain.itsm- us1.comodo.com	Dynamic (Amazon load balancing)	443	Mandatory			
Enrollment	To get client certificates	mdmsupport.comodo.c om (up to CCC 6.29) mdmsupport.cmdm.co modo.com (CCC 6.30+) mdmsupport.itsm- us1.comodo.com (CCC 6.30+)	Dynamic (Amazon load balancing)	443	Mandatory			
Monitoring and alerts	Access to Monitoring and alerts server	plugins.itsm- us1.comodo.com	Dynamic (Amazon load balancing)	443	Mandatory			
File rating	Access to Local	subdomain.itsm-	Dynamic	443	Optional			



management	Verdict Server	us1.comodo.com			
			(Amazon load balancing)		This is for reporting data from CCS
Windows push service (XMPP)	Device communication (push messages)	xmpp.itsm- us1.comodo.com	18.197.167.137 34.227.128.175	443	Mandatory
LDAP synchronizati on	Synchronization with LDAP via device	User's LDAP server host	User's LDAP server IP	389 636 (LDAPS)	Optional For LDAP sync via device only. Related to Device to LDAP server connections only
SSO	Single Sign On	one-us.comodo.com	Dynamic (Amazon load balancing)	443	Mandatory
Client Security installation	Download and install/upgrade Client Security agent. Requests to download.comod o.com are redirected to cdn.download.co modo.com which is managed by The CDN provider, and those IP addresses can change.	download.comodo.com cdn.download.comodo. com	178.255.82.5 Cloudflare's IP range: 104.37.182.3	443, 80	Optional For CCS installation/upgrade only
OCSP	Client certificate revocation checking	http://ocsp.comodoca.c om/	Dynamic load balancing	80	Optional For mobile devices only. The Windows client does not perform OCSP checks.
CRL	Client certificate revocation checking	http://crl.comodoca.co m/	Dynamic load balancing	80	Optional For mobile devices only. The Windows client does not perform CRL checks.
3rd Party Patch Management	3rd party applications updates	patchportal.one-us. comodo.com	Dynamic (Amazon load balancing)	443	Optional For 3rd party software updates only
Telemetry	Sending telemetry data for analysis	cescollector.cwatchapi.	Dynamic (Amazon load balancing)	443	Optional
Local	Distribute	Local hostname	Local IP	6881, 6882	Optional. Used for

ITarian Endpoint Manager - Administrator Guide



distribution of packages	different types of updates via local network		updates distribution locally by torrent principle. Ports are bound by EM Service. 6882 is used if 6881 is in use already.
			in use already.

Comodo Client - Security (CCS)

		Comod	o Client - Securi	ty (CCS)		
Service	Purpose	Hostname	IP	Port	Protocol	Criticality and notes
FLS	FLS lookup	fls.security.c omodo.com	199.66.201.16	4447 (optional), 53	UDP	Mandatory - choose *either* UDP or TCP for FLS UDP is the main, preferred FLS lookup channel 53 - Default port. 4447 - Reserve port. Can be specified manually in profile. At least one of the two ports must be open.
	FLS lookup	fls.security.c omodo.com	199.66.201.16	4448 (optional), 80	TCP	Mandatory - choose *either* UDP or TCP for FLS TCP is the reserve FLS lookup channel. 80 - Default port 4448 - Reserve port. Can be specified manually in profile. At least one of the two ports must be open
Valkyrie	Valkyrie lookup	valkyrie.com odo.com	Dynamic (Amazon load balancing)	443	HTTPS	Optional Valkyrie lookup is currently disabled on CCS, CCS gets Valkyrie verdicts from LVS.
	Submit to Valkyrie	valkyrie.com odo.com	Dynamic (Amazon load balancing)	443	HTTPS	Mandatory
cdn.download.c omodo.com	Update / upgrade mirror	cdn.downloa d.comodo.c om	Cloudflare's IP range: 104.37.182.3	80	HTTP	Mandatory
		cdn.downloa d.comodo.c	Cloudflare's IP range:	443	HTTPS	



		om	104.37.182.3			
download.com odo.com	Update/upgrade. Requests to	download.co modo.com	178.255.82.5	80	HTTP	Mandatory
	download.como do.com are redirected to cdn.download.c omodo.com which is managed by The CDN provider, and those IP addresses can change	download.co modo.com	178.255.82.5	443	HTTPS	Mandatory
LVS	Download the EM verdicts database	s3.us-east- 1.amazonaw s.com	Dynamic (Amazon load balancing)	443	HTTPS	Mandatory
	LVS lookup	subdomain.it sm- us1.comodo .com	Dynamic (Amazon load balancing)	443	HTTPS	
OCSP	Client certificate revocation checking	http://ocsp.c omodoca.co m/	Dynamic load balancing	80	-	Optional CCS does not perform CRL checking yet
CRL	Client certificate revocation checking	http://crl.co modoca.co m/	Dynamic load balancing	80	-	Optional CCS does not perform CRL checking yet
Telementry	Sending telemetry data for analysis	tel.security. comodo.co m	159.203.65.195	261	HTTPS	
FLEVEN	Sending telemetry data for analysis	cis.td.securit y. comodo.co m	Dynamic (Amazon load balancing)	443	HTTPS	
CWATCH	Sending telemetry data for analysis	api.mssp. comodo.co m	Dynamic (Amazon load balancing)	443	HTTPS	

Endpoint Manager Server (on premise installation)

	Endpoint Manager Server (on premise)						
Service	Purpose	Hostname	IP	Port			
E-mail	Connection to the configured SMTP server for e-mail sending	SMTP server hostname	SMTP server IP	25			



LDAP synchronization	Direct synchronization with LDAP	User's LDAP server host	User's LDAP server IP	389 636 (LDAPS)
Connection to Comodo Accounts Manager	License verification	https://accounts.como do.com	178.255.85.140	443
Google Cloud Messaging	To push messages	https://android.google apis.com/gcm/send	Dynamic	443
Local Verdict Server	File rating management	EM server hostname	EM server IP	443

Remote Control

			Remote Contro	ol		
Service	Purpose	Hostname	IP	Port	Protocol	Criticality and notes
XMPP	Remote Control Session (with new version of Comodo RC*	xmpp.itsm- us1.comodo.c om	34.193.74.83 54.163.100.185	443	HTTPS	Mandatory for both RC host and target device
STUN server	To receive possible network configuration, external ip etc.	stun.l.google. com	Dynamic	19302	UDP	Mandatory for both RC host and target device for peer-to-peer and relay connections.
Direct connection	To establish direct or relay connection between RC and target device.	-		1025 - 65535	UDP	Mandatory for both RC host and target device
Direct connection	Establish direct connection between RC and target device.	-	IP of the RC host AND target host	Local port range specified in profile. Win7+/Mac OS. Default port range= 49152 - 65535 WinXP/2003 Default port range = 1025-5000	UDP	Mandatory for both RC host and target device
Peer-to-peer connection	Establish peer- to-peer	-	18.196.107.208 52.29.123.206	3478	UDP	Mandatory for both RC host



	connection RC and target device.		34.232.133.48 18.208.23.45			and target device for peer-to-peer connections.
Relay connection	Establish relay connection between RC and target device.	-	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478, 49152 - 65535	UDP	Mandatory for both RC host and target device for relay connections.

Remote Control - Direct connection by traffic direction *

	Outgoing Traffic							
Source			Protocol					
IP	Port	IP	Port					
Local IP 1	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	Local IP 2	local port range specified in profile (Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	UDP				

	Incoming Traffic							
	Source							
IP	Port	IP	Port	Protocol				
Local IP 2	local port range specified in profile (Win7+/MacOS default port range: 49152 - 65535) (WinXP/2003 default port range: 1025- 5000)	Local IP 1	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535) (WinXP/2003 default port range: 1025-5000)	UDP				

^{* -} applies to both sides - RC host and target.

Remote Control - Peer to Peer Connection by traffic direction *

Outgoing Traffic						
	Source	Destina	Protocol			
IP	Port	IP	Port			



Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478	UDP
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535)(WinXP/2003 default port range: 1025-5000)	stun.l.google.com	19302	

Incoming Traffic						
Source		Destination	Protocol			
IP	Port	IP	Port	_		
18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 - 65535)(WinXP/2003 default port range: 1025-5000)	UDP		
stun.l.google.com	19302	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535)(WinXP/2003 default port range: 1025-5000)			

^{* -} applies to both sides - RC host and target.

Remote Control - Relay Connection by traffic direction*

Outgoing Traffic					
	Source Destination			Protocol	
IP	Port	IP	Port		
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478, 49152 - 65535	UDP	
Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	stun.l.google.com	19302	UDP	

Incoming Traffic			
Source	Destination		



IP	Port	IP	Port	Protocol
18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	3478, 49152 - 65535	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	UDP
stun.l.google.com	19302	Local IP	local port range specified in profile(Win7+/MacOS default port range: 49152 — 65535) (WinXP/2003 default port range: 1025-5000)	UDP

^{* -} applies to both sides - RC host and target.

Diagnostic Tools

Diagnostic Tools					
Service	Purpose	Hostname	IP	Port	Critically and notes
CCS Report Tool	Collect event logs to more effectively troubleshoot issues	c1report.comodo.	178.255.85.136	22	Optional. For manual log uploads

All settings grouped by port

This table contains the same information as the other four tables on this page but with services grouped by port number.

	Settings Grouped by Port					
Port	Service	IP	URL / Hostname	Protocol	Component	
443	CC	Dynamic (Amazon load balancing)	subdomain.itsm- us1.comodo.com	HTTPS	Communication Client	
	Enrollment	Dynamic (Amazon load balancing)	mdmsupport.itsm- us1.comodo.com	HTTPS		
	Monitoring and alerts	Dynamic (Amazon load balancing)	plugins.itsm- us1.comodo.com	HTTPS		
	File rating management	Dynamic (Amazon load balancing)	subdomain.itsm- us1.comodo.com	HTTPS		
	Windows push service (XMPP)	18.197.167.137 34.227.128.175	xmpp.itsm- us1.comodo.com	HTTPS		
	SSO	69.4.89.244	one-us.comodo.com	HTTPS		



Single patch management management management (Amazon load balancing) Dynamic (Amazon management management management (Amazon management management management management management (Amazon management mana					
Client Security 178.255.82.5 download.comodo.com HTTPS					
installation Cloudflare's IP range: 104.37.182.3 Telemetry Dynamic (Amazon load balancing) Valkyrie Update/upgrade. Requests to download.comodo.com are redirected to cdn.download.comodo.com which is managed by The CDN provider, and those IP addresses can change Updates/upgrade smirror Updates/upgrade to Dynamic (Amazon load balancing) Cloudflare's IP range: 104.37.182.3 FLEVEN Dynamic (Amazon load balancing) CWATCH Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) License verification License verification Google cloud messaging Apple push notifications Dynamic gateway.push.apple.com HTTPS Comodo Client Security HTTPS Comodo Client Security HTTPS HTTPS HTTPS FEVEN Dynamic (Amazon load balancing) Dynamic marzonaws.com HTTPS EM server (on premise)		(Amazon load		HTTPS	
Cloudflare's IP range: 104.37.182.3 Telemetry Valkyrie Valkyrie 178.255.87.4 Valkyrie comodo.com HTTPS Valkyrie 178.255.82.5 download.comodo.com License verification Comodo Client Security Comodo Client Security HTTPS HTTPS Comodo Client Security HTTPS Comodo Client Security HTTPS HTTPS Comodo Client Security HTTPS Comodo Client Security HTTPS HTTPS Comodo Client Security HTTPS Comodo Com Comodo.com Live IP Agriculture License Verification License Verification Dynamic Apple push notifications Dynamic gateway.push.apple.com HTTPS HTTPS EM server (on premise)		178.255.82.5	download.comodo.com	HTTPS	
Telemetry Dynamic (Amazon load balancing)	installation	range:		HTTPS	
Valkyrie 178.255.87.4 valkyrie.comodo.com HTTPS Update/upgrade. Requests to download.comodo o.com are redirected to cdn.download.comodo.com which is managed by The CDN provider, and those IP addresses can change Updates/upgrade S mirror Dynamic (Amazon load balancing) CWATCH Dynamic (Amazon load balancing) LVS Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) License verification Dynamic android.googleapis.com/ gem/send Apple push notifications Valkyrie 178.255.82.5 valkyrie.comodo.com HTTPS download.comodo.com HTTPS Comodo Client Security The CDN download.comodo.com HTTPS download.comodo.com HTTPS cdn.download.comodo.c HTTPS om 104.37.182.3 FLEVEN Dynamic (Amazon api.mssp. comodo.com HTTPS comodo.com load balancing) License verification Dynamic accounts.comodo.com HTTPS expression HTTPS EM server (on premise)		104.37.182.3			
Update/upgrade. Requests to download.comod o.com are redirected to cdn.download.co modo o.com which is managed by The CDN provider, and those IP addresses can change Updates/upgrade s mirror Updates/upgrade s mirror Dynamic (Amazon load balancing) CWATCH Dynamic (Amazon load balancing) LVS Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) LVS Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) LVS Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) License verification Tr8.255.85.140 Apple push notifications Dynamic gateway.push.apple.com HTTPS Adownload.comodo.com HTTPS Security Security Security Antipes Security Antipes Security Adownload.comodo.com HTTPS EM server (on premise) HTTPS EM server (on premise)	Telemetry	(Amazon load	-	HTTPS	
Update/upgrade, Requests to download.comod o.com are redirected to cdn.download.com which is managed by The CDN provider, and those IP addresses can change	Valkyrie	178.255.87.4	valkyrie.comodo.com	HTTPS	
FLEVEN Dynamic (Amazon load balancing) CWATCH Dynamic (Amazon load balancing) api.mssp. Comodo.com LVS Dynamic (Amazon load balancing) Subdomain.itsmus1.comodo.com License verification Type Dynamic Dynamic android.googleapis.com/ gcm/send Apple push notifications Dynamic gateway.push.apple.com HTTPS Text Dynamic (Amazon load balancing) Subdomain.itsmus1.comodo.com HTTPS EM server (on premise) EM server (on premise)	Requests to download.comod o.com are redirected to cdn.download.co modo.com which is managed by The CDN provider, and those IP addresses can	178.255.82.5	download.comodo.com	HTTPS	Security
CWATCH Dynamic (Amazon load balancing) Comodo.com HTTPS		range:		HTTPS	
LVS Dynamic (Amazon load balancing) Dynamic (Amazon load balancing) License verification Google cloud messaging Apple push notifications Dynamic (Amazon load balancing) LVS Dynamic (Amazon subdomain.itsmus1.comodo.com us1.comodo.com HTTPS EM server (on premise) EM server (on premise) Android.googleapis.com/ gcm/send HTTPS BM server (on premise) HTTPS Apple push notifications Dynamic gateway.push.apple.com HTTPS	FLEVEN			HTTPS	
License verification Dynamic Dynamic Subdomain.itsmus1.comodo.com HTTPS EM server (on premise)	CWATCH			HTTPS	
License verification Google cloud messaging Apple push notifications License verification License verification 178.255.85.140 accounts.comodo.com HTTPS accounts.comodo.com HTTPS gem/send HTTPS gem/send HTTPS BM server (on premise) HTTPS gem/send HTTPS Apple push notifications	LVS			HTTPS	
verification premise) Google cloud messaging Dynamic android.googleapis.com/ gcm/send Apple push notifications Dynamic gateway.push.apple.com HTTPS				HTTPS	
messaging gcm/send Apple push notifications Dynamic gateway.push.apple.com HTTPS		178.255.85.140	accounts.comodo.com	HTTPS	,
notifications		Dynamic		HTTPS	
Local Verdict EM server IP EM server hostname HTTPS		Dynamic	gateway.push.apple.com	HTTPS	
	Local Verdict	EM server IP	EM server hostname	HTTPS	



	Server				
	XMPP	34.193.74.83 54.163.100.185	xmpp.itsm- us1.comodo.com	HTTPS	Remote Contro tool
80	Client Security installation	178.255.82.5	download.comodo.com	HTTPS	Communication Client
	IIIStallation	Cloudflare's IP range: 104.37.182.3	cdn.download.comodo.c om	HTTPS	Cilent
	OCSP	Dynamic load balancing	http://ocsp.comodoca.co m/	HTTPS	
	CRL	Dynamic load balancing	http://crl.comodoca.com/	HTTPS	
	FLS Lookup	199.66.201.16	fls.security.comodo.com	HTTPS	Comodo Clien
	Update/upgrade. Requests to download.comod o.com are redirected to cdn.download.co modo.com which is managed by The CDN provider, and those IP addresses can change	178.255.82.5	download.comodo.com	HTTPS	County
	Updates/upgrade s mirror	Cloudflare's IP range: 104.37.182.3	cdn.download.comodo.c om	HTTPS	
	OCSP	Dynamic load balancing	http://ocsp.comodoca.co m/	HTTPS	
	CRL	Dynamic load balancing	http://crl.comodoca.com/	HTTPS	
	Apple push notifications	Dynamic	gateway.push.apple.com	HTTPS	EM server (on premise)
22	CCS Report Tool	178.255.85.136	c1report.comodo.com	SSH	Comodo Clien Security
25	Email	SMTP server IP	SMTP server hostname	SMTP	EM server (on premise)
53	FLS Lookup	199.66.201.16	fls.security.comodo.com	UDP	Comodo Clien Security
261	Telementry	159.203.65.195	tel.security. comodo.com	HTTPS	Comodo Clien Security
4447	FLS Lookup	199.66.201.16	fls.security.comodo.com	UDP	Comodo Clien



(Optional)					Security
4448 (Optional)	FLS Lookup	199.66.201.16	fls.security.comodo.com	UDP	Comodo Client Security
389	LDAP synchronization	User's LDAP server IP	User's LDAP server IP		Communication Client
	LDAP synchronization	User's LDAP server IP	User's LDAP server IP		EM server (on premise)
636	LDAP synchronization	User's LDAP server IP	User's LDAP server IP		Communication Client
	LDAP synchronization	User's LDAP server IP	User's LDAP server IP		EM server (on premise)
2195	Apple push notifications	Dynamic	gateway.push.apple.com		EM server (on premise)
6881, 6882	Local distribution of packages	Local IP	Local hostname	TCP	Communication Client
2196	Apple push notifications	Dynamic	gateway.push.apple.com		EM server (on premise)
19302	STUN server	Dynamic (Amazon load balancing)	stun.l.google.com	UDP	Remote Control tool
Win7+/MacO S. Default port range = 49152 - 65535 WinXP/2003. Default port range = 1025-5000	Direct connection	IP of the RC host AND target host	N/A	Win7+/Mac OS. Default port range = 49152 - 65535 WinXP/200 3. Default port range = 1025- 5000	Remote Control tool
3478	Peer-to-peer connection	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	-	3478	
3478, 49152 - 65535	Relay connection	18.196.107.208 52.29.123.206 34.232.133.48 18.208.23.45	-	3478, 49152 - 65535	



Appendix 2 - Endpoint Manager License Types

Each Endpoint Manager license offers different levels of protection and features.

The four license types are:

- Free
- Standard
- Premium

The following table shows the features available with each license type:

Feature	Free	Standard	Premium
7-layer Advanced Endpoint Protection (AEP) with Default Deny security posture (including world's best Containment technology). See https://www.comodo.com/aep.php to read more.	30 days	×	✓
Valkyrie - File intelligence service (automated artificial intelligence analysis)	30 days	×	✓
Valkyrie - File intelligence service (manual analysis by human experts)	30 days	*	✓
Patch management	50 devices	✓	✓
Monitoring - Proactive monitoring	50 devices	✓	✓
Procedures - Standalone instruction scripts	50 devices	✓	✓
Remote Access - Remote Desktop connection	50 devices	✓	✓
Full MDM (Mobile Device Management)	50 devices	✓	✓
Full MAM (Mobile Application Management)	50 devices	✓	✓
Full MSM (Mobile Security Management)	50 devices	✓	✓
BYOD support (Bring Your Own Device support)	50 devices	✓	✓
Community support	50 devices	✓	✓

ITarian Endpoint Manager - Administrator Guide



24/7 professional support 50 devices ✓
--



Appendix 3: Pre-configured Profiles

Endpoint Manager ships with the following built-in profiles:

- Windows Security Level 1 Profile (default profile)
- Windows Security Level 1 Profile [Former Standard Profile]
- · Windows Security Level 2 Profile
- Windows Security Level 3 Profile
- Mac OS Security Level 1 Profile for EM (default profile)
- iOS Security Level 1 Profile for EM (default profile)
- Android Security Level 1 Profile for EM (default profile)
- Linux Security Level 1 Profile for EM (default profile)

'Default' profiles are automatically applied to devices which match their operating system IF no custom profile exists for the device.

Windows Profile Settings

Section	Security Level 1	Security Level 1 [Former 'Standard' profile]	Security Level 2	Security Level 3
Containment Rule	All malicious files are blocked and quarantined All files in suspicious and containment	All malicious files are blocked and quarantined All files in suspicious and containment folders are blocked	All malicious files are blocked and quarantined All files in suspicious and containment folders are blocked	All malicious files are blocked and quarantined All files in suspicious and containment folders are blocked
	folders are blocked	Metro apps are not contained	All unrecognized files are contained.	All unrecognized files are contained.
	Metro apps are not contained All unrecognized files are contained	All unrecognized files are contained.	All contained files are logged	All contained files are logged
HIPS	Enabled	Enabled	Enabled	Enabled
	'Safe Mode' action = 'Allow	'Safe Mode' action = 'Allow Requests'	'Safe Mode' action = 'Block Requests'	Safe Mode action = 'Block Requests'
	Requests' 'Enhanced	'Enhanced Protection Mode' = Disabled	'Enhanced Protection Mode' = Enabled	'Enhanced Protection Mode' = Disabled
	Protection Mode' - Disabled,	'Enable Embedded Code Detection and Heuristic Command- line Analysis for Certain Applications' = Enabled		'Enable Embedded Code Detection and Heuristic Command- Line Analysis for Certain Applications' = Enabled with all applications selected
Firewall	Enabled	Enabled	Enabled	Enabled
	'Safe Mode' action = 'Allow	'Safe Mode' action =	'Safe Mode' action =	'Safe Mode' action =

ITarian Endpoint Manager - Administrator Guide



	Requests'	'Allow Requests'	'Block Requests'	'Block Requests'
VirusScope	Enabled	Enabled	Enabled	Enabled
	'Monitor Contained Applications only' = Enabled	'Monitor Contained Applications only' = Enabled	'Monitor Contained Applications only' = Disabled	'Monitor Contained Applications only' = Disabled
File Rating	Enabled	Enabled	Enabled	Enabled
	'Detect potentially unwanted applications' = Enabled	'Detect potentially unwanted applications' = Enabled	'Detect potentially unwanted applications' = Enabled	'Detect potentially unwanted applications' = Enabled
Antivirus	'Realtime Scan' - Enabled	'Realtime Scan' - Enabled	'Realtime Scan' - Enabled	'Realtime Scan' - Enabled
	Full Scan - 'Use cloud while scanning' - Disabled	Full Scan - 'Use cloud while scanning' - Disabled	Full Scan - 'Use cloud while scanning' - Disabled	Full Scan - 'Use cloud while scanning' - Enabled
Miscellaneous	Unrecognized autorun entries related to new/modified registry items are ignored.	Unrecognized autorun entries related to new/modified registry items are <i>ignored</i> .	Unrecognized autorun entries related to new/modified registry items are <i>terminated</i> <i>and disabled</i> .	Unrecognized autorun entries related to new/modified registry items are quarantined and disabled.